

User's Manual



Release		
Information	Document Version Number	NextGENe-2.4.2-UG001
	Software Version	2.4.2
	Document Status	Final
Copyright	© 2016. SoftGenetics, LLC, All rights	reserved.
	The information contained herein is proprietary and confidential and is the exclusive property of SoftGenetics. It may not be copied, disclosed, used, distributed, modified, or reproduced, in whole or in part, without the express written permission of SoftGenetics, LLC.	
Limit of Liability	SoftGenetics, LLC has used their best effort in preparing this guide. SoftGenetics makes no representations or warranties with respect to the accuracy or completeness of the contents of this guide and specifically disclaims any implied warranties of merchantability or fitness for a particular purpose. Information in this document is subject to change without notice and does not represent a commitment on the part of SoftGenetics or any of its affiliates. The accuracy and completeness of the information contained herein and the opinions stated herein are not guaranteed or warranted to produce any particular results, and the advice and strategies contained herein may not be suitable for every user.	
	The software described herein is furnished under a license agreement or a non-disclosure agreement. The software may be copied or used only in accordance with the terms of the agreement. It is against the law to copy the software on any medium except as specifically allowed in the license or the non-disclosure agreement.	
Trademarks	US Patent No. 8,271,206), and the Flo	tGENe <i>Condensation Tool</i> (covered by <i>ton/Floton-PE</i> assembly methods are SoftGenetics, LLC. All other products might be trademarks or registered
Customer Support	Customer support is available to organ that have an annual support agreement	÷
	SoftGenetics, LL	.C
	100 Oakwood A	
	State College, Pa	A <i>16803</i>
	(814) 237-9340	
	(000) 701 1070	

(888) 791-1270 (US Only) tech_support@softgenetics.com www.softgenetics.com

Table of Contents

Chapter 1: Getting Started with NextGENe 21
NextGENe System Requirements
Installing NextGENe
To install NextGENe
Starting NextGENe
The NextGENe Main Window
Title bar
Main menu
Toolbar
Viewing NextGENe License Information
Configuring User Management
To configure user management
To turn on user management 35
To turn off user management
Managing Groups in NextGENe
To manage groups in NextGENe
To add a new group 41
To edit a group 41
To delete a group 42
Managing Users in NextGENe 44
To manage users in NextGENe 44
To add a user 46
To edit a user
To delete a user
Chapter 2: Project Setup 49
Overview of the Project Wizard
Setting up a New NextGENe Project

To specify data analysis information in the Project Wizard	. 54
To load the sample data files	. 55
To load the reference files	. 56
To load a GenBank or .fasta reference file (Reference < 250 Mbp)	. 57
To load a preloaded reference	. 57
To set ROI regions from a BED or GBK file	. 58
To specify the output file name and location	. 59
To specify the values for the data analysis steps	. 60
To specify the values for the Sequence Condensation step	. 60
To specify the values for the Sequence Assembly step	. 63
To specify the values for the Sequence Alignment step	. 64
To specify the post-processing options for a Sequence Alignment project	. 64
To select the Mutation Report as a post-processing option	. 66
To select a report other than the Mutation report as a post-processing option	. 67
To exported aligned sequences as a post-processing option	. 68
To export a BAM file relative to an ROI BED file	. 69
To export the project output to a BAM file	. 69
To export the project output to Geneticist Assistant	
To finish the project	. 71
To run multiple projects in a series using the Project Wizard	. 72
To carry out a secondary analysis	. 72
Saving and Loading Project Settings	74
To save project settings	. 75
To load project settings	. 75
Batch Processing of Project Files Using the Project Log	. 76
Project Log and Project Wizard	. 76
To use the Project Log to create multiple new projects	77
To use the Project Log and Project Wizard to batch process multiple project files	. 79

To run a saved job file	80
Specifying NextGENe Process Options	81
To specify NextGENe process options	81
Chapter 3: File Format and Conversion	85
NextGENe's Format Conversion Tool	87
To convert a sample file	87
Trim or Reject Read While >= [x] Bases with Score <= [y]	
Trim by Sequences	91
Trim by Sequences in the File	92
Chapter 4: Sequence Condensation Tool	95
Overview of the NextGENe Sequence Condensation Tool	
Illumina, SOLiD System and Ion Torrent data	
Consolidation	
Elongation	
Error Correction	99
Roche/454 data	100
Sequence Condensation Tool - General Settings	102
Merging Paired End Reads	105
Sequence Condensation Tool - Advanced Settings for Illumina Data, SOLiE or Ion Torrent Data	
Sequence Condensation Tool - Advanced Settings for Roche/454 Data	112
Sequence Condensation Tool Output Files	113
Consolidation output files	113
Elongation output files	114
Error Correction output files	115
Chapter 5: Sequence Assembly Tool	117
Sequence Assembly Tool Settings	119

General Assembly settings	120
De Bruijn assembly method for Illumina, SOLiD System, and Ion Torrent data	120
Maximum Overlap assembly method for Illumina data	121
Greedy assembly method for Roche/454 data	121
Skeleton assembly method for Roche/454 data	122
PE assembly method for Roche/454, Illumina, and Ion Torrent data	123
Floton/Floton-PE assembly method for Roche/454 and Ion Torrent data	124
Sequence Assembly Output Files	127
Chapter 6: Sequence Alignment Tool	129
NextGENe Sequence Alignment Algorithms	131
Genomic regions or genomes smaller than 250 Mbp	131
Preloaded Reference Alignment	132
Sequence Alignment Tool Settings	133
Alignment settings—.fasta or GenBank reference file	134
Alignment settings—Preloaded reference	135
BAM Sample Files settings	136
Sample Trim settings	136
Mutation Filter settings	137
File Type settings	138
Other settings	138
NextGENe Viewer	140
To load a sequence alignment project in the NextGENe Viewer	140
NextGENe Viewer layout and navigation	141
NextGENe Viewer title bar	142
NextGENe Viewer main menu	142
Save Optional Reference Info	144
Exported BED file	144

Exported Gap.fasta file	
SAM/BAM Output	144
Export Project	146
NextGENe Viewer toolbar	
Tracks Display	148
Whole Genome viewer	149
Alignment viewer	150
Alignment viewer navigation	151
Alignment viewer functions	153
Segment Breakpoints	155
Status bar	155
Paired Reads Alignment	156
Paired Reads Gap Distribution report	157
Paired Reads Statistics report	158
Opposite Direction Paired Reads report	159
Same Direction Paired Reads report	161
Single Reads report	163
Paired Reads Graph report	165
Export SV Reads function	167
Transcriptome Alignment Project with Alternative Splicing	168
Transcriptome with Alternative splicing alignment algorithm	168
Transcriptome project with Alternative splicing alignment settings	169
Transcriptome project with Alternative splicing view	171
Transcript report	173
Transcript report settings	174
Differential gene expression analysis of transcriptome data	176
STR (Short Tandem Repeats) Analysis Project	180
STR analysis custom .fasta reference file	

STR project alignment settings	
STR project report	181
STR report toolbar	
STR Reads Histogram report	184
STR Report Settings dialog box	186
Mitochondrial Amplicon Analysis Project	189
Mitochondrial amplicon analysis data requirements	189
Mitochondrial Amplicon report	189
Mitochondrial Amplicon report toolbar	191
Reads Summary Alignment view	191
Mitochondrial Amplicon Report settings dialog box	192
HLA Project	195
HLA analysis data requirements and project settings	195
HLA project report	197
HLA report toolbar	198
HLA Report Settings dialog box	199
HLA (Summary Report) Settings tab	199
Allele Matching Report Settings tab	201
Allele Coverage Report Settings tab	
Output Settings tab	204
HLA project view	205
Reference/Dictionary Sequence pane	
Top Allele Pair Matches pane	
Consensus Sequence panes	206
Unmatched Reads pane	
Sequence Alignment Project Output Files	
Sequence Alignment Project Mutation Report	210
Viewing the Edit history for a variant	213

Mutation Report settings	213
Mutation Report Settings dialog box	
Display tab, Annotation sub-tab	
Display tab, Statistics sub-tab	219
Display tab, Phasing sub-tab	221
Filter tab, Annotation sub-tab	223
Filter tab, Bias sub-tab	225
Filter tab, Score sub-tab	226
Ambiguous Gain penalty/Ambiguous Loss penalty	227
Filter tab, ROI sub-tab	
Summary Report tab	230
Output tab	231
Variation Tracks Settings dialog box	
dbNSFP track settings	
Functional Prediction tab	235
Conservation tab	
Population Frequency tab	237
ClinVar track settings	
dbscSNV track settings	239
Gene Tracks Settings dialog box	
Mutation Report functions	
Save Mutation report	241
Save SIFT report	241
Save VCF report (filtered)	241
Save unfiltered VCF report	241
Mutation Report Summary	241
Save consensus sequence	
Save SNP consensus sequence	

Fragment Output	
Seek Sample Position	245
Sequence Alignment Project Reports	
Summary report	
To modify the Summary report view	
To customize the Summary report header	251
Matched/Unmatched report	
Distribution report	
Coverage Curve report	
Mismatched Base Numbers report	
Expression Report	
Expression report for SAGE studies	272
Structural Variation report	273
Score Distribution report	276
NextGENe Viewer Tools	278
Export Sequences tool	278
Export Sequences to CSFASTA tool	279
Advanced GBK Editor tool	
GBK Editor tool - GenBank Tree File	
GBK Editor window- Sequence View pane	
Advanced GBK Editor tool - Auto Create ROI tool	
Advanced GBK Editor tool Output Options	
Advanced GBK Editor tool Save options	
Peak Identification tool	
Peak Identification report	
Synthetic SAGE Data tool	
Create SAGE Library from mRNA tool	
Modify Titles for mRNA GenBank tool	

Resume Project and Load Project	. 290
NextGENe Viewer Comparison Reports and Tools	. 291
Expression Comparison report	. 291
Variant Comparison tool	. 295
To use the Variant Comparison tool to compare multiple projects	. 296
To use the Variant Comparison Tool Top List function	. 299
To use the Variant Comparison tool to analyze family data	. 303
To use the other Variant Comparison Tool functions	. 307
Somatic Mutation Comparison tool	. 310
To generate the Somatic Mutation Comparison Tool report	. 311
CNV (Copy Number Variation) tool (Dispersion and HMM)	. 317
To generate the CNV Tool report (Dispersion and HMM)	. 317
Block CNV report	. 326
CNV Graphs	. 329
CNV (Copy Number Variation) tool (SNP-based Normalization with Smoothing)	. 330
To generate the CNV Tool report (SNP-based Normalization with Smoothing)	. 332
Gene CNV report	. 340
Block CNV report	. 343
CNV Graphs	. 346
Batch CNV Tool	. 348
To use the Batch CNV tool	. 348
Batch CNV graphs	. 350
Chapter 7: Specialized Applications	353
Creating a Reference File with the Peak Identification tool	. 355
To align sample files to peak identification reference file	. 357
Chapter 8: NextGENe Tools	359
The NextGENe Barcode Sorting Tool	. 361

Barcode/Primer File	
To parse barcoded sample files	
The NextGENe Sequence Operation Tool	
To use the NextGENe Sequence Operation tool	
To merge files	
To split files	
To sequence trim reads	
Trim by Sequences	
Trim by Sequences in the File	
Advanced Settings	
To arrange paired reads	
To remove duplicate reads	
The Nucleotide Sequence algorithm for removing duplicate reads	
The UMI algorithm for removing duplicate reads	
To reverse complement sequences	
To create a random subsample	
The NextGENe Reads Simulator Tool	
To use the NextGENe Reads Simulator Tool	
The NextGENe Pseudo Paired Read Constructor Tool	
To use the NextGENe Pseudo Paired Read Constructor	
The NextGENe Condensation Results Filter Tool	
To use the NextGENe Condensation Results Filter tool	
The NextGENe Condensation Results Tool	
Condensed Reads pane	
Index table	
The NextGENe GC Percentage Calculation Tool	
To use the NextGENe GC Percentage Calculation tool	
The NextGENe Overlap Merger Tool	

To use the NextGENe Overlap Merger tool
The NextGENe Long PE Assembly Mapping Tool 389
To use the NextGENe Long PE Assembly Mapping tool
The NextGENe File Preview Tool
To use the NextGENe File Preview tool
Chapter 9: The NextGENe AutoRun Tool 391
The NextGENe AutoRun Job Editor Dialog Box
Title bar
Job Tree pane
Job Editing pane
Main menu
Toolbar
Batch Processing of Multiple Projects
To create a new job file in the NextGENe AutoRun Tool
To specify preprocessing options 403
To select report post-processing options 405
To select the Mutation Report as a post-processing option
To select a report other than the Mutation report as a post-processing option 408
To export aligned sequences as a post-processing option
To export a BAM file relative to an ROI BED file 409
To export the project output to a BAM file 410
To export the output to Geneticist Assistant 411
To group jobs 412
To modify an existing job file 415
To create a new job from an existing AutoRun template 416
To specify the NextGENe AutoRun settings 417
Batch Processing of Previously Processed Projects to Output Reports and Other Export Files

To create a single post-processing Settings file	. 420
To load and run the projects	. 422
To specify the NextGENe AutoRun settings	. 424
Secondary Batch Analysis of Multiple Projects	. 427
Managing NextGENe AutoRun Templates	. 429
To create a NextGENe AutoRun template	. 429
To modify a NextGENe AutoRun template	. 434
To delete an AutoRun template	. 434
Working With NextGENe AutoRun Pre-Built Templates	. 436
To select the samples and reference for a NextGENe AutoRun pre-built template	. 436
To group jobs	. 439
To specify the NextGENe AutoRun settings	. 441
To modify a NextGENe AutoRun pre-built template	. 443
Appendix A: Mutation Report Scores	445
Overall Mutation Score	. 446
Coverage score	. 447
Read Balance Score	. 448
Allele Balance Score	. 449
Homopolymer Score	. 450
Mismatch Score	. 451
Wrong Allele Score	. 452
Index	453
Glossary	463

Preface

Welcome to the *NextGENe User's Manual*. The purpose of the *NextGENe User's Manual* is to answer your questions and guide you through the procedures necessary to use the NextGENe application efficiently and effectively.

Using the manual

You will find the *NextGENe User's Manual* easy to use. You can simply look up the topic that you need in the table of contents or the index. Later, in this Preface, you will find a brief discussion of each chapter to further assist you in locating the information that you need.

Special information about the manual

The *NextGENe User's Manual* has a dual purpose design. It can be distributed electronically and then printed on an as-needed basis, or it can be viewed online in its fully interactive capacity. If you print the document, for best results, it is recommended that you print it on a duplex printer; however, single-sided printing will also work. If you view the document online, a standard set of bookmarks appears in a frame on the left side of the document window for navigation through the document. For better viewing, decrease the size of the bookmark frame and use the magnification box to increase the magnification of the document to your viewing preference.

Conventions used in the manual

The NextGENe User's Manual uses the following conventions:

- Information that can vary in a command—variable information—is indicated by alphanumeric characters enclosed in angle brackets; for example, <Project Name>. Do not type the angle brackets when you specify the variable information.
- A new term, or term that must be emphasized for clarity of procedures, is *italicized*.
- Page numbering is "online friendly." Pages are numbered from 1 to x, *starting with the cover* and ending on the last page of the index.



Although numbering begins on the cover page, this number is not visible on the cover page or front matter pages. Page numbers are visible beginning with the first page of the table of contents.

Preface

- This manual is intended for both print and online viewing.
 - If information appears in blue, it is a hyperlink. Table of Contents and Index entries are also hyperlinks. Click the hyperlink to advance to the referenced information.

Assumptions for the manual

The NextGENe User's Manual assumes that:

- You are familiar with windows-based applications and basic Windows functions and navigational elements.
- References to any third party standards or third party software functions were current as of the release of this version of NextGENe, and might have already changed.

Organization of the manual

In addition to this Preface, the *NextGENe User's Manual* contains the following chapters and appendices:

- Chapter 1, "Getting Started with NextGENe," on page 21 details the NextGENe installation requirements, and the procedures for installing the application and activating your account. It also explains how to launch the application and provides an overview of the major navigational elements for the application. Finally, it details User Management for your NextGENe instance, which requires that a user be authenticated before logging in and using the application.
- Chapter 2, "Project Setup," on page 49 details the use of the NextGENe Project Wizard, which you use to set up a project for analyzing your Next Generation sequencing data.
- Chapter 3, "File Format and Conversion," on page 85 details the NextGENe Format Conversion tool which you use to convert a supplier's format to a standard .fasta format that NextGENe can read and to standardize the data and trim or remove low quality reads before analysis.
- Chapter 4, "Sequence Condensation Tool," on page 95 details the Sequence Condensation tool, which uses depth of coverage to correct sequence reads that contain instrument base calling errors and to elongate reads, while merging identical reads or maintaining read number as necessary for your project.
- Chapter 5, "Sequence Assembly Tool," on page 117 details the Sequence Assembly tool, which assembles the reads that are generated by the Roche/454, Illumina, SOLiD System, and Ion Torrent instruments into larger contigs.
- Chapter 6, "Sequence Alignment Tool," on page 129 details the Sequence Alignment tool, which matches short sequence reads to a reference sequence. It also details the Sequence Alignment Viewer, which is a viewing and editing tool that you can use to view

the results of the Sequence Alignment tool and produce a variety of interactive reports that summarize the sequence alignment information.

- Chapter 7, "Specialized Applications," on page 353 details the procedure for creating a reference file using the Peak Identification tool.
- Chapter 8, "NextGENe Tools," on page 359 details all the NextGENe tools (with the exception of the NextGENe Format Conversion tool and the NextGENe AutoRun tool) that you can use to optimize input data and export results.
- Chapter 9, "The NextGENe AutoRun Tool," on page 391 details the NextGENe AutoRun tool, which a multi-functional tool that you can use for carrying out batch analysis of multiple projects. You can also use the tool for creating and modifying templates for facilitating job setup in the NextGENe AutoRun tool, including jobs for analysis of data for RainDance Thunderbolts panels.
- Appendix A, "Mutation Report Scores," on page 445 provides a detailed explanation of the Overall Mutation Score. It also provides a detailed description, including the underlying algorithms, for each of the scores that are used in the calculation of the Overall Mutation Score.

Preface

The NextGENe software application is designed to enhance the power for discovery from your Next Generation sequencing data. This software is ideal for the analysis of data from the Illumina Genome Analyzer, the Roche Genome Sequencer FLX and FLX Titanium Systems, and Life Technologies's SOLiD System and Ion Torrent sequencer. This chapter details the installation requirements, and the procedures for installing NextGENe and activating your account. It also explains how to launch NextGENe and provides an overview of the major navigational elements for NextGENe, including the menu bar and the toolbar. Finally, it details User Management for your NextGENe instance, which requires that a user be authenticated before logging in and using NextGENe.

This chapter covers the following topics:

- "NextGENe System Requirements" on page 23.
- "Installing NextGENe" on page 24.
- "Starting NextGENe" on page 26.
- "The NextGENe Main Window" on page 27.
- "Viewing NextGENe License Information" on page 30.
- "Configuring User Management" on page 31.
- "Managing Groups in NextGENe" on page 39.
- "Managing Users in NextGENe" on page 44.

NextGENe System Requirements



The following system requirements are for all data types other than Ion Torrent. Ion Torrent does not have these restrictions.

NextGENe is currently available only for the Windows operating system. You must have Administrator rights for the computer on which you are installing NextGENe. NextGENe can function on Windows 32- or 64-bit systems with x86 architecture. NextGENe is compatible with the Windows XP and Vista operating systems; however, for optimum performance, you should run NextGENe on a Windows 7, Windows 8, or Windows 10 operating system.

- Windows 32-bit operating system: You can use NextGENe on a Windows 32-bit system for viewing or editing projects that have already been processed. Using a 32-bit system to process data is not recommended.
- Windows 64-bit Operating System: For all instrument types other than Ion Torrent, a Windows 64-bit system with dual quad processors and 12 GB RAM is required for data processing. For some applications, additional RAM is required. The Ion Torrent instrument type has no minimum processor requirements and minimum requirement of a 3 GB RAM. To align Ion Torrent data to a preloaded reference such as the whole human genome, at least 8GB RAM is required.

Installing NextGENe

NextGENe is licensed in three different ways, each of which follow slightly different installation procedures—Validation, Local, and Network:

• Validation license—The Validation license is a trial license that provides all the functionality of a purchased license. You can load data, create and save new files, analyze and visualize data, and so on. The Validation license expires 30 calendar days from installation.



You must contact SoftGenetics to receive a disc that contains a fully functional, 30 day trial of the software.

- Local license—The Local license is designed for installation on a a single computer.
- Network license—The Network license is for installation on multiple client computers that are connected to a license server computer.

To install NextGENe



If another program other than a SoftGenetics application that uses MySQL or Apache is already installed on the computer on which you are installing NextGENe, contact tech_support@softgenetics.com for assistance first.

For any version of NextGENe, the NextGENe Installation wizard guides you through the steps that are necessary to install the application on your computer. The default installation location is:

C:\Program Files (x86)\SoftGenetics\NextGENe

When you are installing NextGENe, keep in mind the following:

Version	Comments
Validation	To use the preloaded reference alignment function, you must install the Annotation database.
Local	• To use the preloaded reference alignment function, you must install the Annotation database.
	 You must complete the registration information exactly as supplied by SoftGenetics.

Version	Comments
Network	Server Setup
	 You must install the License Server Manager before installing NextGENe.
	 To use the preloaded reference alignment function, you must install the Annotation database.
	 You must complete the registration information exactly as supplied by SoftGenetics.
	Client Setup
	 To use the preloaded reference alignment function, you must install the Annotation database.
	 You must NOT install the License Server Manager.
	 You must complete the registration information exactly as supplied by SoftGenetics.

Starting NextGENe

After NextGENe has been installed on your computer, a shortcut icon for the application is placed on your desktop. An option for NextGENe is also available from your Start menu. You can double-click the desktop icon to launch NextGENe, or you can select the option from your Start menu (Start > All Programs > SoftGenetics > NextGENe).

Figure 1-1: NextGENe desktop icon



Two results are possible:

- If user management has been turned on for your instance of NextGENe, then you are prompted to enter your user name and password to log in to and open NextGENe. The NextGENe Project Wizard then opens automatically in the NextGENe main window.
- If user management has not been turned on then, the NextGENe Project Wizard opens automatically in the NextGENe main window.

See "The NextGENe Main Window" on page 27.

Figure 1-2: NextGENe Project Wizard in the NextGENe main window

	Project Wizard - Ap	plication Type	
		Sho	w Project Log>>
	Step	Instrument type	
NextGENe File Process Tool	Application	C Roche/454 F Illumina C SOLID C Ion Torrent	
No	Load Data	Application type	
Next Gen	Condensation	C de novo Assembly C SNP/Indel discovery C Transcriptome ☐ Alternative splicing C ChIP-Seq	
	Assembly	SAGE STR analysis C Mitochondrial amplicon CNV-Seg HLA Other	
CtHay 9a	Post Processing	Steps Sequence condensation Sequence assembly. Sequence alignment	þ
0		Performance settings: Number of cores to be used : 3 (1~8)	
US Patent No. 8,271,20		Save Settings Load Setting Next >> Cancel Finish	/sis

The NextGENe Main Window

The NextGENe Project Wizard opens in the NextGENe main window when you launch NextGENe.

	Show Project Log.	>>
Step	Instrument type	
e	C Roche/454	- 6
ss Tool	Ilumina	
C A	C SOLID	
	C Ion Torrent	
Load Data	Application type	
	C de novo Assembly	
ext Gen	SNP/Indel discovery	
Condensation	C Transcriptome 📈 Alternative splicing	
	C ChIP-Seq	
	C SAGE	
Assembly	C STR analysis C Mitochondrial amplicon	
	C CNV-Seq	
	C HLA	
Alignment	C Other	
23	Steps	6
Post Processing	Sequence condensation	
100	Sequence assembly	
8.	✓ Sequence alignment	
0	Performance settings:	
	Number of cores to be used : 3 (1~8)	
	Save Settings Load Settings	8
18		/sis
No. 8,271,20	Next >> Cancel Finish	

Figure 1-3: NextGENe Project Wizard in the NextGENe main window

The NextGENe main window is your starting point for the NextGENe application. The window provides quick access to all the NextGENe functions and system tools. The NextGENe main window has three major components—the title bar, the main menu, and the toolbar.

Title bar

The name "NextGENe" is displayed in the title bar at the top of the NextGENe main window. If User Management has been turned on for your instance of NextGENe, then your user name is also displayed in brackets on the Title bar.

Figure 1-4: Title bar with user name displayed

NextGENe [Administrator]



The version of NextGENe that you are running is not displayed in the Title bar. You must use the Help > About option in the main menu to determine the version number. See "Main menu" below.

Main menu

The main menu is set up in a standard Windows menu format with menu commands grouped into menus (File, Process, Tools, and Help) across the menu bar. Some of these menu commands are available in other areas of the application.

Figure 1-5: Main menu

File Process Tools Help

Toolbar

The toolbar provides quick access to all the NextGENe functions.

Figure 1-6: NextGENe toolbar



Button	Function
2	NextGENe Project Wizard button - Opens the NextGENe Project Wizard.
	Load File button - Opens the Load Data page in the NextGENe Project Wizard.
С	Condensation Settings page button - Opens the Condensation Settings page in the NextGENe Project Wizard.
А	Assembly Settings page button - Opens the Assembly Settings page in the NextGENe Project Wizard.
Ż	Alignment Settings page button - Opens the Alignment Settings page in the NextGENe Project Wizard.

Button	Function
	Run Project Wizard button - Runs the currently loaded projects in the NextGENe Project Wizard.
*	Open NextGENe Viewer button - Opens the NextGENe Viewer.
8	Exit button - Immediately closes NextGENe.



All the pages that are referenced above are pages in the NextGENe Project Wizard. Typically, you open the wizard either by launching NextGENe or by clicking the Project Wizard button on the NextGENe toolbar. When you open the wizard using one of these two options, the wizard always opens to the first page the Applications Type page. You can also open the wizard by clicking any of the page-specific buttons on the NextGENe toolbar. See Chapter 2, "Project Setup," on page 49 for detailed information about the NextGENe Project Wizard.

Viewing NextGENe License Information

Your NextGENe license has both a type and an expiration date. You can view this information for your NextGENe license on the NextGENe License dialog box. To open this dialog box, on the NextGENe main menu, click Help > License Information. The NextGENe License dialog box shows the license type (for example, Local) for your NextGENe installation, and the number of days until the license expires from the current day's date. You can click OK to close the dialog box and return to NextGENe.

Figure 1-7: NextGENe License dialog box



Configuring User Management

After NextGENe is installed, user management can be configured for both NextGENe and the NextGENe Viewer. User management requires that a user be authenticated before logging in and using the applications. You can configure user management independently for each computer (localhost) on which NextGENe is installed. In this configuration, the SoftGenetics Server service must be installed on each computer on which NextGENe is installed. Because the same user management configuration is part of the installation process for Geneticist Assistant, the steps that you must follow to install the SoftGenetics Server service depend on whether Geneticist Assistant has already been installed on the localhost. Alternatively, a single server can host the SoftGenetics Server service and you can configure each NextGENe host to connect to this single server to verify user credentials. When you configure user management, you must always configure the Administrator user account first. Only the Administrator user has all the necessary privileges for managing other users. All other users are standard users. After you configure user management, you must turn on user management. You can also always turn off user management at any time without deleting any of the user configuration information.



If you changed the directory for storing the MySQL information that NextGENe uses from the default directory (C:\ProgramData\MySQL\MySQL Server 5.1\Data), then before configuring user management, you must contact tech_support@softgenetics.com.

To configure user management



The following procedures details the configuration of user management independently for each computer (localhost) on which NextGENe is installed. To configure user management with a single server hosting the SoftGenetics Server service, contact tech_support@softgenetics.com.

- 1. If Geneticist Assistant is already installed on the computer on which you are configuring user management for NextGENe, go to "To turn on user management" on page 35; otherwise, do the following:
 - Log on to the host computer as a Windows user that is a local Administrator.
 - To avoid issues with User Account Control settings, right-click the NextGENe desktop shortcut and on the context menu that opens, select Run as administrator.

The NextGENe Project Wizard opens automatically in the NextGENe main window.

2. Close the NextGENe Project Wizard, and then on the NextGENe main menu, click Help > User Management > Install Local Service.

The License page for the SoftGenetics Server Setup wizard opens. The page details the license agreement for installing the SoftGenetics Server service. See Figure 1-8 on page 32.




Figure 1-8: SoftGenetics Server Setup wizard, License Agreement page



3. Click I Agree to accept the license agreement.

The Settings page for the SoftGenetics Server Setup wizard opens. By default, the page is prepped for configuring the Administrator user.

Figure 1-9: SoftGenetics Server Setup wizard, Settings page

Settings Configure the Administrator		0
Administrator Setup		
Username:	Administrator	
Password:		-
Verify:	-	-
Email		-
T100 2,0 d.s		
	< Back. Next	> Cancel

- 4. Do the following:
 - Leave the user name set to Administrator, or modify it as needed.
 - In the Password field, enter the password for the Administrator user.



The only invalid character for the password is a space. There are no other special requirements or restrictions for the Administrator password. It can adhere to your organization's standards and any other requirements as needed. If you forget or lose this password, it is not recoverable.

- In the Verify field, enter the Administrator password *exactly* as you entered it in the Password field.
- In the Email field, enter the email address for the Administrator user.




The current version of User Management does not support email notifications; however, an email address is still required.

5. Click Next.

The Choose Components page for the SoftGenetics Server Setup wizard opens. A single component, the Server, is listed on the page.

Figure 1-10: SoftGenetics Server Setup wizard, Choose Components page





After you select the server, the space requirements for installing the SoftGenetics Server service are displayed on the page. Make sure that you have sufficient space on the computer to install this service.

6. Select Server, and then click Install.

The Installation page for the SoftGenetics Server Setup wizard opens. The page details the components that are being installed and the status of the installation. See Figure 1-11 on page 34.




Figure 1-11: SoftGenetics Server Setup wizard, Installation page

Note the following about the installation:

- If MySQL has *not* already been installed on the localhost, then after installation of MySQL is complete, click Close at the prompt; otherwise, the installation begins with the installation of the other server components (Python, Django, and Apache).
- During the installation of the other server components, you might receive Security Alerts. The installation is set up to handle these alerts and with the exception of a Windows Security Alert for Apache (see below), no special action is required.
- After Apache is installed, a Windows Security Alert opens indicating that the Windows Firewall has blocked some features of the installation. Click Unblock to allow the Apache HTTP Server to operate correctly on the localhost.

Figure 1-12: Windows Security Alert for Apache



After installation is complete, Completed is displayed at the top of the Installation page. Figure 1-13: SoftGenetics Server Setup wizard, Installation page for completed installation

Installation Complete		0
Setup was completed successfully.		C.
Completed		
Loading initial data for histob. Sinstalled O object(s) from 0 future(s) The Apache2, softganetics service is so The Apache2, softganetics service has (05 1004000Hy one usage of each sod no kreening sockets available, shutting of	stopped. ket address (protocol/network address(port) i	14
The eventing second or analysis and only a	2000	

7. Click Close.

The SoftGenetics Server Setup wizard closes. NextGENe remains open.

8. Continue to "To turn on user management" below.

To turn on user management

1. On the NextGENe main menu, click Help > User Management > Manage Settings.

The User Management Settings dialog box opens. The General tab is the open tab.

Figure 1-14: User Management Settings dialog box, General tab

User Management Settings - NextGENe Software [Administrator]	
General Users Groups	
Service host: localhost	Use GA configuration
Turn on user management	
Remember last user	
View Log	
	OK Cancel

2. Leave Service host set to localhost.

- 3. Do one of the following:
 - If you are using only NextGENe (and not Geneticist Assistant), then select Turn on user management.

Remember last user becomes available.

- If you are using both NextGENe and Geneticist Assistant, and you want the same users for both applications, then select Use GA Configuration.
- 4. Leave Remember last user selected, or optionally, clear it.



If Remember last user is selected, then when a user logs into NextGENe, the Username field on the Login dialog box is automatically populated with the user name for the user who last logged into NextGENe.

5. Click OK.

The Administrator Verification dialog box opens. The dialog box indicates that Administrator verification is required to apply the changes.

Figure 1-15: Administrator Verification dialog box

ministrator verifi	cation to the host is required to apply the changes.	
Usemame:	Administrator	_
Password:	[_
	OK Cancel	

- 6. In the Username field, leave the Administrator username as-is, or optionally, modify the name as needed.
- 7. In the Password field, enter the password for the Administrator user.
- 8. Click OK.

A message opens, indicating that to apply the changes that NextGENe must be closed and reopened and asking you if you want to close NextGENe now.

9. Click Yes.

The message closes.

10. Start NextGENe.

The Login dialog box opens. See "Starting NextGENe" on page 26. Figure 1-16: NextGENe Login dialog box

Usemame:	ſ		
Password:	[_
	ОК	Cancel	

11. Enter the Administrator username and password, and then click OK.

The Login dialog box closes. The NextGENe Project Wizard opens automatically in the NextGENe main window. Now, every time a user opens NextGENe, they are prompted to enter a username and password before they can use the application.



If you are the Administrator user, you should now continue to setting up the needed groups and users for your NextGENe instance. See "Managing Groups in NextGENe" on page 39 and "Managing Users in NextGENe" on page 44.

To turn off user management

After configuring and turning on user management for your NextGENe instance, as the Administrator user, you always have the option of turning off user management. This does not delete any user configuration information. It simply means that users are not required to be authenticated before they log in to and use NextGENe. You can always turn user management back on.

1. Start NextGENe.

The Login dialog box opens. See "Starting NextGENe" on page 26.

Figure 1-17: NextGENe Login dialog box

Login - NextGENe	Software		×
Username: Password:	[
	OK Settin	Cancel	

Chapter 1 Getting Started with NextGENe

2. Enter the Administrator username and password, and then click OK.

The NextGENe Project Wizard opens automatically in the NextGENe main window.

- 3. Close the NextGENe Project wizard.
- 4. On the NextGENe main menu, click Help > User Management > Manage Settings.

The User Management dialog box opens. The General tab is the open tab. Turn on user management is selected.

Figure 1-18:	User Management Se	ettings dialog box,	General tab
--------------	--------------------	---------------------	-------------

User Management Settings - NextGENe Software [Administrator]	
General Users Groups	
Service host: localhost	Use GA configuration
✓ Turn on user management	
Remember last user	
View Log	
	OK Cancel

- 5. Clear Turn on user management.
- 6. Click OK.

A message opens, indicating that to apply the changes that NextGENe must be closed and reopened and asking you if you want to close NextGENe now.

7. Click Yes.

The message and NextGENe close. Now, any user can start NextGENe without any authentication. The user configuration information, however, is not deleted, so you can always turn user management back on if needed.

Managing Groups in NextGENe

Users are the people who log into NextGENe, whether they are adding and reviewing content, or just using NextGENe in a read-only capacity. A *group* is a collection of users that have the same permissions in NextGENe. As the Administrator user for NextGENe, you are responsible for managing all the groups for your NextGENe instance and managing the users for these groups to ensure that your users have the appropriate permissions available to them in NextGENe. You can assign users to one of the four default groups that are installed with every instance of NextGENe, or you can create your own groups with the needed permissions, and then assign users to one of these groups.

	NextGENe Default User Group					
	Reporter	Technician	Analyst	Supervisor		
Assigned Permissions						
View Project	Y	Y	Y	Y		
Export Results	Y	Y	Y	Y		
Create and Run Project	N	Y	Y	Y		
Re-run Project	N	N	Y	Y		
Edit Sequence Data	N	N	Y	Y		
Edit Variants	N	N	Y	Y		
Edit Alignment	N	N	Y	Y		
Edit Report Filters	N	N	Y	Y		
Manage Global Settings	N	N	N	Y		
Manage Analysis Settings	N	N	N	Y		
Manage Report Settings	N	N	N	Y		

Managing groups for NextGENe consists of adding new groups, editing existing groups, and deleting groups.

To manage groups in NextGENe

1. On the NextGENe main menu, click Help > User Management > Manage Settings.

The User Management Settings dialog box opens. The General tab is the open tab. See Figure 1-18 on page 38.

2. Click the Groups tab to open it.

The tab lists the four default groups that are installed with every instance of NextGENe as well any groups that have been configured for your NextGENe instance. If applicable, it also lists any groups that have been configured for your Geneticist Assistant instance. See Figure 1-19 on page 40.

No.	Name	View Project	Export Results	Create & Run	Re-run Project	
1	Reporter	Yes	Yes	No	No	
2	Technician	Yes	Yes	Yes	No	
3	Analyst Supervisor	Yes Yes	Yes	Yes	Yes	
•		10				
Jser	ist					

Figure 1-19: User Management Settings dialog box, Groups tab

3. Optionally, to view a list of all users that are currently assigned to a group, select the group.

The users that are assigned to the selected group are displayed alphabetically by username in the User list pane.

- 4. Continue to one of the following:
 - "To add a new group" on page 41.
 - "To edit a group" on page 41.
 - "To delete a group" on page 42.

To add a new group

1. Click Add Group.

The Add Group dialog box opens.

Figure 1-20: Add Group dialog box

<

- 2. In the Group name field, enter the name for the new group.
- 3. On the Permissions list, select the permissions for the new group.
- 4. Click OK.

A message opens, indicating that the new group was successfully created.

5. Click OK.

The message closes. The Groups tab remain opens with the newly added group displayed on the tab.

6. Click OK.

The User Management Settings dialog box closes.

To edit a group

Editing a group from the Group tab consists of modifying the permissions for the group. If you want to edit a group by adding or deleting users, then you must do so from the Users tab. (See "Managing Users in NextGENe" on page 44.) Also, you cannot edit a group name. If you need to rename a group, you must delete the current group, and then create a new group with the new name.




Although you can edit the permissions that are assigned to the NextGENe default groups, SoftGenetics strongly recommends that you not do so. Instead, you should create a new group with the appropriate permissions, and then assign appropriate users to the new group.

Chapter 1 Getting Started with NextGENe

1. Select the group for which you are modifying the permissions, and then click Edit Group.

The Edit Group dialog box opens. The group name is displayed in the Group name field, and you cannot edit it. The permissions that are currently assigned to the group are also displayed.



Wew Project Export Results Create & Run Project Gdit Sequence Data Edit Variants Edit Variants Edit Variants Edit Report Filters Ømanage Global Settings Ømanage Report Settings		
	Create & Run Project Re-run Project Edit Sequence Data Edit Variants Edit Alignment Edit Report Filters Ø Manage Global Settings Ø Manage Analysis Settings	Create & Run Project Re-run Project Edit Sequence Data Edit Variants Edit Alignment Edit Report Filters V Manage Global Settings

- 2. Modify the permissions for the group as needed.
- 3. Click OK.

A message opens, indicating that the group was successfully edited.

4. Click OK.

The message closes. The Groups tab remain opens.

5. Click OK.

The User Management Settings dialog box closes.

To delete a group



Although you can delete any of the NextGENe default groups, SoftGenetics strongly recommends that you not do so. Instead, you should delete only those custom groups that you have added for your NextGENe installation.

1. Select the group that you are deleting, and then click Delete Group.

A message opens, indicating that you are deleting the selected group and prompting you to click OK to confirm the deletion.

2. Click OK.

The message closes, and a second message opens, indicating that you have successfully deleted the selected group.

3. Click OK.

The second message closes. The entry for the group is removed from the Groups tab. The Groups tab remains open.

4. Click OK.

The User Management Settings dialog box closes.

Managing Users in NextGENe

Users are the people who log into NextGENe, whether they are adding and reviewing content, or just using NextGENe in a read-only capacity. If you are the Administrator user for NextGENe, then you are responsible for managing all the other users for your NextGENe instance. Managing users for NextGENe consists of adding new users, editing existing users, and deleting users. You can also view the activity for your NextGENe users (logging in to or logging out of NextGENe) in a log file.

To manage users in NextGENe

1. On the NextGENe main menu, click Help > User Management > Manage Settings.

The User Management Settings dialog box opens. The General tab is the open tab. See Figure 1-18 on page 38.

2. Optionally, to view the activity for your NextGENe users (logging in to or logging out of NextGENe) in a log file, click View Log.


The User Management Log file opens onscreen. The file lists login and logout activity for your NextGENe users, and if applicable, all the activities for your Geneticist Assistant users as well. You can click Save to File to save the log file with a name and a location of your choosing.

User Management	Logs			
vent Logs				Save to File.
Time	User	Client	Event	Detail
2014-07-17 08:34:01	Administrator		Crash	Geneticist Assistant crashed with User Administrator at time 2014-06-20
2014-07-17 08:34:01	Administrator		Login	User Administrator logged in.
2014-07-17 10:17:37	Administrator		Crash	Geneticist Assistant crashed with User Administrator at time 2014-07-17
2014-07-17 10:17:37	Administrator		Login	User Administrator logged in.
2014-07-17 14:17:12	Administrator		Crash	Geneticist Assistant crashed with User Administrator at time 2014-07-17
2014-07-17 14:17:12	Administrator		Login	User Administrator logged in.
2014-07-24 10:00:18	Administrator		Crash	Geneticist Assistant crashed with User Administrator at time 2014-07-17
2014-07-24 10:00:18	Administrator		Login	User Administrator logged in.
2014-07-24 10:10:05	Administrator		Logout	User Administrator logged out.
2014-07-24 10:51:06	Administrator		Login	User Administrator logged in.
2014-07-24 10:54:34	Administrator		Crash	Geneticist Assistant crashed with User Administrator at time 2014-07-24
2014-07-24 10:54:34	Administrator		Login	User Administrator logged in.
2014-07-24 10:55:33	Administrator		Logout	User Administrator logged out.
2014-07-24 11:02:15	Administrator		Login	User Administrator logged in.
2014-07-25 08:38:54	Administrator		Crash	Geneticist Assistant crashed with User Administrator at time 2014-07-24
2014-07-25 08:38:54	Administrator		Login	User Administrator logged in.
2014-07-25 09:55:37	Administrator		Logout	User Administrator logged out.
2014-07-25 09:55:52	Administrator		Login	User Administrator logged in.
2014-07-25 10:03:39	Administrator		Edit	User Administrator added Permission Can view panel group to User tvan
2014-07-25 10:03:39	Administrator		Edit	User Administrator added Permission Can add panel group to User tvanb
2014-07-25 10:03:39	Administrator		Edit	User Administrator added Permission Can delete panel group to User tva
2014-07-25 10:03:39	Administrator		Edit	User Administrator added Permission Can change panel group to User tv
2014-07-25 10:03:39	Administrator		Edit	User Administrator deleted Permission Can add user from User tvanboen
2014-07-25 10:03:39	Administrator		Edit	User Administrator deleted Permission Can view panel group from User t
2014-07-25 10:03:39	Administrator		Edit	User Administrator deleted Permission Can add panel group from User tv
2014-07-25 10:03:39	Administrator		Edit	User Administrator deleted Permission Can change user from User tvanb
2014-07-25 10:03:39	Administrator		Edit	User Administrator deleted Permission Can view user from User tvanboer
2014-07-25 10:03:39	Administrator		Edit	User Administrator deleted Permission Can delete user from User tvanbo
2014-07-25 10:03:39	Administrator		Edit	User Administrator deleted Permission Can delete panel group from User
2014-07-25 10:03:39	Administrator		Edit	User Administrator deleted Permission Can change panel group from Use
2014-07-25 10:03:53	Administrator		Logout	User Administrator logged out.
•				· · · · · · · · · · · · · · · · ·

Figure 1-22: User Management Log file

3. Click the Users tab to open it.

The tab lists all the user accounts that have been configured for your NextGENe instance, and if applicable, any user accounts that have been configured for your Geneticist Assistant instance.



No.	Username	Group	Sys Admin	Active	Email
1 2 3	Administrator tvanboening johnqpublic	Research Stu	Yes No Yes	Yes Yes Yes	admin@softgenetics.com tammyvb@spectrumwrit john@msn.com
	d User				Edit User Delete User

- 4. Continue to one of the following:
 - "To add a user" on page 46.
 - "To edit a user" on page 47.
 - "To delete a user" on page 48.

To add a user

1. Click Add User.

The Add User dialog box opens.

Figure 1-24: Add User dialog box

Username:	1	
Password:		
Confirm password:		
Email (Optional):	1	
User group:	-	•
User permissions:	View Project Export Results Create & Run Project Re-run Project Edit Sequence Data	Ē
	Edit Variants	+

- 2. Enter the information for the new user:
 - In the Username field, enter the appropriate user name.
 - In the Password field, enter the password for the user.



The only invalid character is a space. There are no other special requirements or restrictions for the user password. It can adhere to your organization's standards and any other requirements as needed. If you forget or lose this password, it is not recoverable.

- In the Verify field, enter the user password *exactly* as you entered it in the Password field.
- Optionally, in the Email field, enter the email address for the user.



The current version of User Management does not support email notifications; however, you can still enter an email address.

3. Assign the user to a selected group.



Assigning a user to a group assigns the user's permissions for NextGENe. If the appropriate group is not available, then you must add the group. See "Managing Groups in NextGENe" on page 39.

4. Optionally, if the user is to be responsible for User Management in NextGENe (managing groups and users), then select System administrator.

5. Click OK.

A message opens, indicating that the new user was created successfully.

6. Click OK.

The message closes. The entry for the new user is displayed on the Users tab. The Users tab remains open.

7. Click OK.

The User Management Settings dialog box closes.

To edit a user

You can edit the password, the email address, and the groups for a user. For any user other than the default Administrator user, you can edit the System administrator status. You cannot edit the username for any user. To edit the username, you must delete the user, and then create a new user with a different username. See "To delete a user" on page 48.

1. Select the user that you are editing, and then click Edit User.

The Edit User dialog box opens.

Figure 1-25: Edit User dialog box

Edit User - tvanboen	ing		×
Username:	fvanboening		
New password:			
Confirm password.		-	
Email (Optional):	tammyvb@spectrumwritinglc.c	om	
User group:	[•
User permissions:	View Project Export Results Create & Run Project Re-run Project Edit Sequence Data Edit Variants		* 10
System administra	East	ОК	Cancel

- 2. Edit the information for the user as needed:
 - To edit the password, select New password, and then do the following:
 - i. In the Password field, enter the password for the user.



The only invalid character is a space. There are no other special requirements or restrictions for the user password. It can adhere to your organization's standards and any other requirements as needed. If you forget or lose this password, it is not recoverable.

ii. In the Verify field, enter the user password *exactly* as you entered it in the Password field.

Chapter 1 Getting Started with NextGENe

- Enter an email address for the user, or edit the existing address as needed.
- Select a different group for the user.
- Select or clear the System administrator status for the user.
- 3. Click OK.

A message opens, indicating that the new user was updated successfully.

4. Click OK.

The message closes. The entry for the user is updated accordingly on the Users tab.

5. Click OK.

The User Management Settings dialog box closes.

To delete a user

You cannot delete the default Administrator user. To edit the name for a user, you must delete the user, and then create a new user with a different user name. See "To add a user" on page 46.

1. Select the user that you are deleting, and then click Delete User.

A message opens, indicating that you are deleting the user and asking you to click OK to continue.

2. Click OK.

The message closes, and a second message opens indicating that the selected user was successfully deleted.

3. Click OK.

The second message closes. The entry for the user is removed from the Users tab. The Users tab remains open.

4. Click OK.

The User Management Settings dialog box closes.

Chapter 2 Project Setup

The NextGENe software application is designed to enhance the power for discovery from your Next Generation sequencing data from four platforms—the Illumina Genome Analyzer, the Roche Genome Sequencer FLX and FLX Titanium Systems, and Life Technologies's SOLiD System and Ion Torrent. Each platform can be used to generate data for a multitude of applications. NextGENe is equipped with a Project Wizard that guides you through the necessary steps for setting up a project for each possible instrument platform and application combination.

This chapter covers the following topics:

- "Overview of the Project Wizard" on page 51.
- "Setting up a New NextGENe Project" on page 53.
- "Saving and Loading Project Settings" on page 74.
- "Batch Processing of Project Files Using the Project Log" on page 76.
- "Specifying NextGENe Process Options" on page 81.

Chapter 2 Project Setup

Overview of the Project Wizard

You use the NextGENe Project Wizard to set up a project for analyzing your Next Generation sequencing data. The NextGENe Project Wizard opens automatically when you launch NextGENe, or you can do one of the following:

- Click the Project Wizard icon ion the application toolbar.
- On the NextGENe main menu, click File > Open Project Wizard.
- On the NextGENe main menu, click Process > Project Wizard.

The first page that opens is the Application Type page.

	Show Project Log>>	
-Step	Instrument type	
Ve	C Roche/454	
ess Tool		
C A 2	ation C SOLID	
	C Ion Torrent	
Load I	Data Application type	
	C de novo Assembly	
lext Gen	 SNP/Indel discovery 	
Conden	isation C Transcriptome IV Alternative splicing	
	C ChIP-Seq	
	C SAGE	
Asser	mbly C STR analysis C Mitochondrial amplicon	
	C CNV-Seq	
2.74	(C HLA	
Alignm	C Other	
A 06	Steps	
Pos Proces		1
2.2	F Sequence assembly	
5 8	I Sequence alignment	
80	Performance settings:	
6.2	Number of cores to be used : 3 (1~8)	
46	Save Settings Load Settings	3®
No. 8,271,20	Next >> Cancel Finish	sis

Figure 2-1: NextGENe Project Wizard, Application Type page

The Project Wizard is a standard wizard consisting of multiple pages that are linked by Next and Back buttons. After you complete the steps on a page, you click Next to move to the next page. At any time, you can click Back as many times as needed and modify your selections for a previously completed step or steps. In addition to the standard Next and Back buttons, the Project Wizard has page-specific buttons that you can click to open the indicated page. These buttons are listed in the left pane of the wizard in the same order in which the pages open when you click Next. If a page is unavailable, then the page-specific button is dimmed. For example, in Figure 2-1, the Application Type page is open. While on this page, you can click Next to open the Load Data page, or you can click the Load Data button. In the same figure, because Sequence Assembly is not a supported step for the SNP/Indel application type, the Assembly button is dimmed.

You have a variety of options for processing a NextGENe project in the Project Wizard.

- You can set up a new NextGENe project. See "Setting up a New NextGENe Project" on page 53.
- You can use the Save Settings function to save the settings from a project to a configuration file, and then you can use the Load Settings function to load this configuration file for use in another project. See "Saving and Loading Project Settings" on page 74.
- You can process a single project, or you can process multiple projects sequentially. See "Batch Processing of Project Files Using the Project Log" on page 76.

Setting up a New NextGENe Project

Setting up a new NextGENe project consists of the following high-level steps:

- Specifying the instrument type and the application type:
 - Four types of instrument systems produce data that NextGENe can analyze—the Roche/454 instrument series, the Illumina Genome Analyzer, and Life Technologies's SOLiD System and Ion Torrent sequencer. You must specify the instrument type that you used to produce the data that is being analyzed.
 - The application type determines how you are going to analyze the data—*de novo assembly*, SNP/Indel Discovery, and so on. The application type that you specify, in turn, determines the steps that are available to you for analyzing your data—Sequence Condensation, Sequence Assembly, and Sequence Alignment. You must also specify the method by which to analyze the data and the number of cores that are to be used for processing the data.

See "To specify data analysis information in the Project Wizard" on page 54.

- Loading the data files—The data files that are being analyzed must be in .fasta format or BAM format. With the exception of the BAM format, if the files are not in .fasta format, for example, .fastq, then you must use the NextGENe conversion tool to convert the files before loading them. See "To load the sample data files" on page 55.
- Loading the reference files—For all application types other than *de novo Assembly*, a reference is required for aligning reads. The reference can be a .fasta file, a GenBank file, a preloaded reference that SoftGenetics supplies, or for STR analysis, a custom .fasta file that you create. See "To load the reference files" on page 56.
- Specifying the output location and saving the output file—You must specify the location for the output folder and the name of the output folder. See "To specify the output file name and location" on page 59.
- Specifying the values for the analysis steps—You can accept the default values that NextGENe generates, or you modify the values as needed. See "To specify the values for the data analysis steps" on page 60.
- Specifying post-processing options for the project—Optionally, you can specify which outputs (reports and sequences) to automatically generate and save after project analysis for a sequence alignment project is completed. See "To specify the post-processing options for a Sequence Alignment project" on page 64.
- Run the project—You can process a single project, or you can process multiple projects sequentially. You can also carry out a secondary analysis on a previously run project. See "To finish the project" on page 71.

Chapter 2 Project Setup

To specify data analysis information in the Project Wizard

1. On the Application Type page, in the Instrument Type pane, select the instrument type that was used to produce that data.

Figure 2-2: Specifying the instrument type

Instrument Type	
C Roche/454	
Illumina	
C SOLiD	
○ Ion Torrent	

2. In the Application Type pane, select the method by which the data is to be analyzed. (SNP/Indel Discovery is selected by default.)

Figure 2-3:	Specifying	the application	type
-------------	------------	-----------------	------

Application type	
C de novo Assembly	
SNP/Indel discovery	
C Transcriptome	Alternative splicing
C ChIP-Seq	
C SAGE	
C STR analysis	C Mitochondrial amplicon
C CNV-Seq	
C HLA	
◯ Other	

The Application Type that you select determines the sequencing steps that are available for analyzing the data.

Application Type	Available Sequencing Steps
de novo Assembly	Condensation, Assembly
SNP/Indel Discovery	Condensation, Alignment
Transcriptome (including Alternative Splicing)	Alignment
ChIP-Seq	Condensation, Alignment
SAGE	Alignment
STR analysis	Condensation, Alignment
Mitochondrial amplicon	Condensation, Alignment
CNV-Seq	Condensation, Alignment
HLA	Alignment
Other	Condensation, Assembly, Alignment

3. In the Performance Settings pane, enter the number of cores that are to be used for processing in the Project Wizard.



The default value is one less than the total number of available cores, which allows you to review other projects and/or carry out any other needed project activities while the current project is being processed.

4. Continue to "To load the sample data files" below.

To load the sample data files

You can load a data file as-is only if the data file is in BAM format or in .fasta format, which includes Roche .fna files and SOLiD System .csfasta files. With the exception of the BAM format, if the data file is not in .fasta format, you must convert the file to the .fasta format before loading it. (See Chapter 3, "File Format and Conversion," on page 85.)



Preprocessing of files must also be necessary before you can load the files. For example, if you used barcoding or multiplexing, then you must sort the data before you can load it. Be aware of any preprocessing that you must carry out before you can covert and/or load sample and/or reference files.

1. Click Next or Load Data.

The Load Data page opens.

Figure 2-4: Project Wizard, Load Data page

	st	now Project Log
	Load data	
tep		nvert to fasta:
1	Sample files:	nat Conversion
Application		Load
		Remove
Load Data		RemoveAll
Condensation	Reference files:	-
		Load
T		Preloaded
Assembly		Remove
	1	RemoveAll
Alignment	Output:	-
	E	Set
Post Processing	□ Set Amplicon BED file □ Set ROI regions from GBK files	
		Set
	Query annotation and tracks of preloaded reference:	
	human_v36_i_dna_compressed]
		1
	< Back Next >>> Cancel	Finish

2. In the Sample Files pane, click Load.



By default, .fasta is the selected file type. To process BAM files, you must select BAM files as the file type.

3. In the Open dialog box, browse to and select the data file that you analyzing, and then click Open to load the selected file in to the Project Wizard.



A data file in the .fasta format has a file extension of ".fasta," ".fna," or ".csfasta." The name of a data file that has been converted to the .fasta format by NextGENe's Format Conversion tool is appended with the phrase "_converted" as shown in Figure 2-5 below.



You can load multiple data files for the same single sequence read project. If you are using the Somatic Mutation Comparison tool to analyze your data, then SoftGenetics recommends a minimum of four normal samples to create a single pooled project. See "Somatic Mutation Comparison tool" on page 310.

Figure 2-5: Example of a converted .fasta file

SRR018422_converted.fasta	1/26/2010 2:39 PM	FASTA File	343,785 KB
---------------------------	-------------------	------------	------------

- 4. If you loaded a .fasta file or an *unaligned* BAM file, then go Step 5. If you loaded an *aligned* BAM file, and you want to realign the data, then leave Realignment (below the Output field) selected, and then go to Step 5; otherwise, if you do not want to realign the data, then clear this option, and go to Step 5.
- 5. If you selected the *de novo* Assembly application type, continue to "To specify the output file name and location" on page 59; otherwise, continue to "To load the reference files" below.

To load the reference files

For all application types other than *de novo* Assembly, a reference is required for aligning the reads of the data file that is being analyzed against a reference genome.

- For all application types other than transcriptome, STR analysis, or Mitochondrial amplicon analysis:
 - If you are aligning the data against a small genome (one that is less than or equal to 250 Mbp), then you can align data against a reference file that is in either .fasta format or GenBank format. See "To load a GenBank or .fasta reference file (Reference < 250 Mbp)" on page 57.



You can download GenBank format references from the NCBI website (http://www.ncbi.nlm.nih.gov/). For information about NextGENe's alignment algorithms, see "NextGENe Sequence Alignment Algorithms" on page 131. • If you are aligning the data against a large genome (one that is greater than 250 Mbp, such as the whole human genome), then you must align the data against a preloaded reference that SoftGenetics supplies or a custom preloaded reference that was built using the NextGENe Build Preloaded Reference tool. See "To load a preloaded reference" on page 57.



For detailed information about building a custom preloaded reference, see the Reference & Track Manager Tool User's Manual or Online Help. For detailed information about the algorithm that NextGENe uses to align reads to a preloaded reference, see "NextGENe Sequence Alignment Algorithms" on page 131.

- The transcriptome application type always requires a preloaded reference that is created from an annotated GenBank file or supplied by SoftGenetics. See "Transcriptome Alignment Project with Alternative Splicing" on page 168.
- The STR application type requires a custom .fasta reference file. See "STR (Short Tandem Repeats) Analysis Project" on page 180.
- The Mitochondrial amplicon application type requires the mitochondrial Genbank reference file. You must also load a BED file that details the amplicon locations. See "To set ROI regions from a BED or GBK file" on page 58.

To load a GenBank or .fasta reference file (Reference < 250 Mbp)

- 1. In the Reference Files pane, click Load.
- 2. In the Open dialog box, browse to and select the GenBank or .fasta reference file.



A data file in the .fasta format has a file extension of ".fasta." A GenBank reference file has a file extension of ".gbk" or ".gb."

3. Continue to "To specify the output file name and location" on page 59.

To load a preloaded reference

1. In the Reference Files pane, click Preloaded.

The Select Preloaded Reference dialog box opens. This dialog box lists all the preloaded references that have been imported into your NextGENe installation or custom built for your NextGENe installation. If the dialog box is blank, then no references have been imported or downloaded. See Figure 2-6 on page 58.



You can import reference files from the Reference discs that are included with NextGENe or download them from the SoftGenetics ftp site. You can also click Manage References > Build Reference to open the Build Preloaded Reference tool and build the necessary reference. For detailed information about importing or downloading a reference, or building a custom preloaded reference, see the Reference & Track Manager Tool User's Manual or Online Help. Chapter 2 Project Setup

Reference	Annotation Database ID	Genome Build	Comment
		The second second	Comment
Aedes_aegypti_L1.3	sg_aaegl1_3	reference::Aedes_aegypti_L1.3	
human_v36_1_dna_compressed	sg_v36_1_human_dna	Human_NCBI36	
Human_v36_3_dna	sg_v36_3_human_dna	Human_NCBI36	
Human_v37_1_dna	sg_v37_1_human_dna	Human_GRCh37	
✓ Human_v37_2_dna Human_v37_2_snp134_dna	sg_v37_2_human_dna sg_v37_2_snp134_human_dna	Human_GRCh37 Human_GRCh37	

Figure 2-6: Select Preloaded Reference dialog box


- 1. Select the appropriate preloaded reference.
- 2. Click OK.


The Select Preloaded Reference dialog box closes. The selected reference is displayed in the Reference files pane.

3. Continue to "To specify the output file name and location" on page 59.

To set ROI regions from a BED or GBK file

If you select Mitochondrial amplicon analysis, then in addition to loading the GenBank Mitochondrial reference file, you must load a BED file that includes the amplicon regions. You can also select this option for targeted sequencing analysis to display bases that align outside of the target regions or to primer regions as soft-clipped and the ROI Viewer track displays a solid pink link indicating the amplicon regions. (See "Tracks Display" on page 148.) In this case, ROIs can be defined in either a BED file or GenBank file.







Setting regions from GBK files is applicable only if you load a GBK reference file. You can download GenBank format references from the NCBI website (http://www.ncbi.nlm.nih.gov/). If the GBK file does not have the necessary information about the ROIs, then you can manually add the information to the file. See "Advanced GBK Editor tool - Auto Create ROI tool" on page 284.

- 1. Load the reference file.
- 2. Select one of the following as appropriate—Set Amplicon BED file or Set ROIs from GBK files.



For detailed information about the required format for a BED file, see "BED file" on page 463.

- 3. Do one of the following:
 - If you selected Set Amplicon BED file, click Set to open a dialog box, and then browse to and select the appropriate BED file.
 - If you selected Set ROIs from GBK files, no further action is required.
- 4. Continue to "To specify the output file name and location" below.

To specify the output file name and location

The Load Data page displays a single option for specifying the location of the saved output file and by default, it is populated with the directory path for the first sample file that was loaded.

Figure 2-8: Output option

Output:	
C:\Users\Spectrum Writing\Spectrum Writing Info\Active Client Work\SoftG	Set

- 1. Do one of the following:
 - In the Output field, leave the default location for the output folder as-is, and then continue to "To specify the values for the data analysis steps" on page 60.
 - Click Set to open a Save As dialog box to browse to and select a new location for the output folder. The location can be a local drive or a network drive.



If the location is a network drive, then you can specify a Local Temp Directory option to speed up the processing of the data. See "Specifying NextGENe Process Options" on page 81.



The default Output folder name is based on the name of the data file that you loaded and is appended with the phrase "_Output" as shown in Figure 2-9 on page 60.

Chapter 2 **Project Setup**

Figure 2-9: Example of an Output folder

> 1/12/2010 9:32 AM File folder SRR018422_converted_Output

2. Continue to "To specify the values for the data analysis steps" below.

To specify the values for the data analysis steps

The application type that you select determines the steps that are available for analyzing the data and the default values for each applicable analysis step. You can accept these default values, or you can modify them as needed. See:

- "To specify the values for the Sequence Condensation step" below.
- "To specify the values for the Sequence Assembly step" on page 63.
- "To specify the values for the Sequence Alignment step" on page 64.

To specify the values for the Sequence Condensation step

1. Click Next or Condensation.

The Condensation Settings page opens. The Reference Length options vary depending on the selected Application Type—*de novo* Assembly (see Figure 2-10 below), or all application types other than *de novo* Assembly. (See Figure 2-11 on page 61.)



For a detailed discussion of the Sequence Condensation tool and its settings, see Chapter 4, "Sequence Condensation Tool," on page 95.

Figure 2-10: Condensation Settings page for de novo Assembly

Project Wizard - Cond	ensation	×
	Show Project Log>>	
Step	Condensation General Settings	
	Instrument Illumina	
Application	Application de novo Assembly	
	Read Counts Less than 1 million	
Load Data	Read Lengths 36	
	Reference Length 🔽 Set Manually(Kbps): 0 Inspect Input	Π
Condensation	Expected Depth of Coverage Less than 30X	
	Condensation Type Consolidation Paired]
Assembly		

ject Wizard - Condens	ation	
		Show Project Log>>
-Step -C	ondensation General Settings	
A	Instrument Illumina	a
Application	Application Other	
	Read Counts Less t	nan 1 million 💌
Load Data	Read Lengths 36	
	Reference Length Less th	nan 1 Mbps
Condensation	Expected Depth of Coverage Less th	Input Files
Condensation		N-P
		Paired
Assembly		
Alignment		
Aignment		
Post	Open Advanced Settings	
Processing		
	Save Score	
		Save Settings Load Settings
		Save Settings
	<< Back No	ext >> Cancel Finish

Figure 2-11: Condensation Settings page (for all application types other than de novo Assembly)

2. On the Condensation Type dropdown list, for Illumina data, SOLiD System data, or Ion Torrent data, select the condensation method that you are using (Consolidation, Elongation, or Error Correction.)



For Roche/454 data, Error Correction is the only available method and the Condensation Type field is automatically set to this value.

3. For for Illumina data, SOLiD System data, or Ion Torrent data, click Inspect Input Files. For Roche data, go to Step 4.

The NextGENe Project Wizard scans your data file and sets a variety of default values for the general sequence condensation settings. You can modify these values if needed. See "Sequence Condensation Tool - General Settings" on page 102.



If you load multiple sample files for analysis, all the data is evaluated as whole, not by individual sample files.

Chapter 2 Project Setup

- 4. Click Open Advanced Settings.
 - For the Roche/454 instrument type, the advanced settings are unique and are populated with values that SoftGenetics has determined, from experience, are appropriate for most datasets for the instrument. (See Figure 2-12 below and "Sequence Condensation Tool Advanced Settings for Roche/454 Data" on page 112.)
 - For the Illumina, SOLiD, and Ion Torrent instrument types, the available settings are the same and the advanced settings are populated based on the Read Lengths and Expected Depth of Coverage values that were set in Step 3. (See Figure 2-12 on page 62 and "Sequence Condensation Tool - Advanced Settings for Illumina Data, SOLiD System Data, or Ion Torrent Data" on page 106.)

Figure 2-12: Condensation Settings page, Advanced Settings for Roche instrument type

Condensation - Advanced Settings	×
Error Correction	
Options of Keyword Selection after Homopolymer Breaker	
KeyWord Length: 16 Bases	
Long Keyword >= 60 Bases (50-60 Bases, Breaks at AAT or ATT)	
Frequency <= 2 Counts and <= 25 %, or <= 8 %	
✓ Combine Both Forward and Reverse	
Default Settings	
OK	

	mber of Cycles: 1 Set Memory Ratio 1 View Condensation Resul
Cycl	e 1
	Minimum Read Length for Condensation 25 Bases Condens/Read
	✓ Range in Read to Index : 1 Bases to Length minus 6 Bases
	Auto Indexing Based on Expected Coverage = 500 X(>500)
	Reads Required for Each Group in One Direction 5 to 60000
	Reads Required for Each Group in Each Direction 2 to 60000
	Bridge Reads Required for Each Subgroup: 2 and 1 %
	Total Reads Required for Each Subgroup: 5 and 0.2 %
	Recover Best Subgroup for Repeat Indexes
	Forward and Reverse Balance 0.1 (0~0.5)
	Remove Indexes with PCR bias: Min. Ratio = 20 Min. Coverage= 100
	C Fixed Shoulder Sequence Length = 12 Bases
	C Fixed, then Extended Shoulder Length = 12 Bases and Score <= 1.01
	Flexible Sequence Length = 11.9.7. (10.8.6)
	C Homopolymer Index Checking
	☐ Start Index at 2 (2 or 3) Homopolymers ☐ AT,GC,ATT, Complements
	Use Only 5' Bases for Consensus
	Remove Low Quality Ends when Score <= 10 (< 100)
	Require Bridge Read Covering Middle 70 %
	□ Index Error Correction if Frequency <= 15 % of Majority Index

Figure 2-13: Condensation Settings page, Advanced Settings for Illumina instrument type

- 5. Leave the default values as-is, or make any changes as needed.
- 6. If applicable, continue to the next analysis step for the project; otherwise, if this is your last analysis step, click Finish, and then continue to "To finish the project" on page 71.

To specify the values for the Sequence Assembly step

1. Click Next or Assembly.

The Assembly Settings page opens. The assembly settings on this page vary depending on the selected instrument type and, if applicable, the selected condensation options.



For a detailed discussion of the Sequence Assembly tool and its settings, see Chapter 5, "Sequence Assembly Tool," on page 117.

2. If applicable, continue to the next analysis step for the project; otherwise, if this is your last analysis step, click Finish, and then continue to "To finish the project" on page 71.

To specify the values for the Sequence Alignment step

1. Click Next or Alignment.

The Alignment Settings page opens. The alignment settings that are available on the Alignment Settings page for any application type *other than* Transcriptome with alternative splicing, STR analysis, or HLA depend on the type of reference file (.fasta, GenBank, or preloaded) that was loaded for the project.



For a detailed discussion of the Sequence Alignment tool and its settings, see Chapter 6, "Sequence Alignment Tool," on page 129.

- 2. Leave the default values as-is, or make any changes as needed.
- 3. Do one of the following:
 - To specify post-processing options for an alignment project, continue to Figure below.
 - To finish the project, click Finish, and then continue to "To finish the project" on page 71.

To specify the post-processing options for a Sequence Alignment project

	Show Project Log>
Post processing Report	Settings
Cave summery report	Add Remove All
Export	Settings
Export BAM	Add Remove All
Coutput to Geneticist Assistant	Dakalis Semple Name
	Report Cave summary report Export Cave Summary report Export Cave Summary report Cave S

Figure 2-14: Post-processing page for a sequence alignment project

Optionally, you can specify post-processing options for a sequence alignment project.

- Report post-processing options—If you specify report post-processing options, then selected reports, including the Summary report, are generated automatically and saved for the project after project analysis is completed. Each report is generated and saved based on the settings that were specified in a saved Settings file (.ini file) for the report. You can generate and save multiple versions of different reports, or multiple versions of the same report as long as each report version uses a different Settings file. To specify post-processing options for the *first* time, you must have previously saved a Settings file for at least one of the following reports:
 - Mutation report (The general report settings and/or the variation tracks settings). See "Mutation Report settings" on page 213.
 - Distribution report. See "Distribution report" on page 254.
 - Coverage Curve report. See "Coverage Curve report" on page 258.
 - Expression report. See "Expression Report" on page 265.
 - Structural Variation report. See "Structural Variation report" on page 273.
 - HLA report. See "HLA project report" on page 197.



The HLA report is available as a post-processing option only if HLA is selected as the application type. See "HLA Project" on page 195.

• Transcript report. See "Transcript report" on page 173.



The Transcript report is available as a post-processing option only if Transcriptome with Alternative splicing is selected as the application type. See "Transcriptome Alignment Project with Alternative Splicing" on page 168.

• Summary report. See "Summary report" on page 246.



Save Summary Report is available only after you select at least one other post-processing report and its Settings file. The information that is contained in the Summary report is relative to the post-processing reports that you select for the project.

- Export post-processing options:
 - Export Sequence If you specify export sequence post-processing options, then a .fasta file that contains all the reads that aligned to a specific region in the reference sequence is automatically generated after project analysis is completed. The sequence is generated and saved based on the settings that were specified in a saved Settings file (.ini file) for the sequence. To specify post-processing options for the first time, you must have previously saved a Settings file for the sequence using the Export Sequences tool. See "Export Sequences tool" on page 278.

Chapter 2 Project Setup

• Export ROI BAM – If you specify ROI BAM as a post-processing option, then instead of the entire BAM file being exported, a BAM file for alignments that fall only within the ROIs is exported.

You can also export the project output to just a BAM file, and you can export the project output (BAM and VCF files) to Geneticist Assistant.

1. Click Post Processing.

The Post Processing page opens.

- 2. Select any of the post-processing options as needed. See:
 - "To select the Mutation Report as a post-processing option" below.
 - "To select a report other than the Mutation report as a post-processing option" on page 67.
 - "To exported aligned sequences as a post-processing option" on page 68.
 - "To export a BAM file relative to an ROI BED file" on page 69.
 - "To export the project output to a BAM file" on page 69.
 - "To export the project output to Geneticist Assistant" on page 70.

To select the Mutation Report as a post-processing option

If you select the Mutation report as a post-processing option, two different Settings files are available. The General Report Settings file contains all the general options for the Mutation report. The Variation Tracks Settings file contains all the tracks settings for the Mutation report based on the variation databases that were imported for the project.



For detailed information about the Mutation report settings, see "Mutation Report settings" on page 213. For details about importing variation databases into NextGENe, see the Reference & Track Manager Tool User's Manual or Online Help.

1. On the Report dropdown list, select Mutation Report.

A blank Settings field opens next to the selected report.

2. Next to the blank Settings field, click Set.

The Set Mutation Report Settings dialog box opens.

Figure 2-15: Set Mutation Report Settings dialog box

Set Mutation Report Settings		X
General Report Settings:		Set
Variation Track Settings:		Set
	ОК	Cancel

NextGene User's Manual

- 3. Under General Report Settings click Set to display the Open dialog box, and then browse to and select a saved Settings file (*.ini file) for the report.
- 4. Optionally, to specify display or filtering settings based on imported variation tracks, under Variation Tracks Settings, click Set to display the Open dialog box, and then browse to and select a saved Settings file (*.ini file) for the report.
- 5. Click OK.

The Set Mutation Report Settings dialog box closes. The Post-Processing page remains opens.

6. Optionally, click Save Summary report to have a Summary report automatically generated for the project as well.



Remember, Save Summary report is available only after you select at least one other post-processing report and its Settings file. For information about the Summary report, see "Summary report" on page 246.

- 7. If you are done with specifying the needed post-processing options, then Click Finish, and continue to "To finish the project" on page 71; otherwise, continue specifying any other needed post-processing options. See:
 - "To select a report other than the Mutation report as a post-processing option" below.
 - "To exported aligned sequences as a post-processing option" on page 68.
 - "To export a BAM file relative to an ROI BED file" on page 69.
 - "To export the project output to a BAM file" on page 69.
 - "To export the project output to Geneticist Assistant" on page 70.

To select a report other than the Mutation report as a post-processing option

1. On the Report dropdown list, select the report that is to be automatically generated and saved for the project after project analysis is complete.

A blank Settings field opens next to the selected report.

- 2. Next to the blank Settings field, click Set and then browse to and select a saved Settings file (.ini file) for the report.
- 3. Repeat Step 1 and Step 2 until you have added all the needed reports and their Settings files.

4. Optionally, click Save Summary report to have a Summary report automatically generated for the project as well.



Remember, Save Summary report is available only after you select at least one other post-processing report and its Settings file. For information about the Summary report, see "Summary report" on page 246.

- 5. If you are done with specifying the needed post-processing options, then Click Finish, and continue to "To finish the project" on page 71; otherwise, continue specifying any other needed post-processing options. See:
 - "To select the Mutation Report as a post-processing option" on page 66.
 - "To exported aligned sequences as a post-processing option" below.
 - "To export a BAM file relative to an ROI BED file" on page 69.
 - "To export the project output to a BAM file" on page 69.
 - "To export the project output to Geneticist Assistant" on page 70.

To exported aligned sequences as a post-processing option



For information about generating and saving an export sequence Settings file, see "Export Sequences tool" on page 278.

1. On the Export dropdown list, select Export Sequence.

A blank Settings field opens next to the Export Sequence option.

- 2. Next to the blank Settings field, click Set and then browse to and select a saved Settings file (.ini file) for the sequence that is to be generated.
- 3. Repeat Step 1 and Step 2 until you have added all the needed sequences and their Settings files.
- 4. If you are done with specifying the needed post-processing options, then Click Finish, and continue to "To finish the project" on page 71; otherwise, continue specifying any other needed post-processing options. See:
 - "To select the Mutation Report as a post-processing option" on page 66.
 - "To select a report other than the Mutation report as a post-processing option" on page 67.
 - "To export a BAM file relative to an ROI BED file" on page 69.
 - "To export the project output to a BAM file" on page 69.
 - "To export the project output to Geneticist Assistant" on page 70.

To export a BAM file relative to an ROI BED file

To export a BAM file for the alignment results for the regions that are defined only in the BED file, select ROI BAM as an export option.

1. On the Export dropdown list, select ROI BAM.

A blank Settings field opens next to the ROI BAM option.

- 2. Next to the blank Settings field, click Set and then browse to and select a saved BED (*.bed) file.
- 3. Repeat Step 1 and Step 2 until you have added all the needed BED files.
- 4. If you are done with specifying the needed post-processing options, then Click Finish, and continue to "To finish the project" on page 71; otherwise, continue specifying any other needed post-processing options. See:
 - "To select the Mutation Report as a post-processing option" on page 66.
 - "To select a report other than the Mutation report as a post-processing option" on page 67.
 - "To exported aligned sequences as a post-processing option" on page 68.
 - "To export the project output to a BAM file" below.
 - "To export the project output to Geneticist Assistant" on page 70.

To export the project output to a BAM file

If you export NextGENe sequence alignment project files to a BAM format, then the standard index file, index.bai, that other alignment viewers require is also exported.



If you do not select this post-processing option, you always have the option of exporting the project output to a BAM format from the File menu on the NextGENe viewer. See "NextGENe Viewer main menu" on page 142.

- 1. Select Export BAM.
- 2. If you are done with specifying the needed post-processing options, then Click Finish, and continue to "To finish the project" on page 71; otherwise, continue specifying any other needed post-processing options. See:
 - "To select the Mutation Report as a post-processing option" on page 66.
 - "To select a report other than the Mutation report as a post-processing option" on page 67.
 - "To exported aligned sequences as a post-processing option" on page 68.
 - "To export a BAM file relative to an ROI BED file" on page 69.
 - "To export the project output to Geneticist Assistant" on page 70.

To export the project output to Geneticist Assistant

For Output to Geneticist Assistant to be enabled, User Management must be turned on for your NextGENe instance and you must be logged in appropriately. See "To turn on user management" on page 35. Also, the path for the Geneticist Assistant executable must be specified in the NextGENe process options. See "Specifying NextGENe Process Options" on page 81.

1. Select Output to Geneticist Assistant.

Edit details is enabled as are the Run Name and Sample Name fields. By default, the Sample Name is set to the same as that of the first sample file that was loaded for the AutoRun job.



When output is exported to Geneticist Assistant, an unfiltered VCF file is automatically produced and exported, even if loaded post-processing options specify both an unfiltered VCF file and a filtered VCF file.

- 2. Enter a Run Name and/or edit the Sample Name.
- 3. Click Edit details.

The Geneticist Assistant Input Settings dialog box opens. The first time that the dialog box opens, all options are blank; otherwise, the settings that were last specified are displayed.

Figure 2-16:	Geneticist Assistant Input Settings dialog box
--------------	--

eticist Assistant Input Settings	
Settings	
Reference	•
Panel	•
Chemistry	•]
Instrument	•
Submit BAM	
	OK Cancel

- 4. Specify the Geneticist Assistant run variables.
- 5. To submit the BAM and VCF output to Geneticist Assistant, select Submit BAM; otherwise, to import only the VCF output, leave this option cleared.
- 6. Click OK.

The Geneticist Assistant Input Settings dialog box closes.

- 7. If you are done with specifying the needed post-processing options, then Click Finish, and continue to "To finish the project" below; otherwise, continue specifying any other needed post-processing options. See:
 - "To select the Mutation Report as a post-processing option" on page 66.
 - "To select a report other than the Mutation report as a post-processing option" on page 67.
 - "To exported aligned sequences as a post-processing option" on page 68.
 - "To export a BAM file relative to an ROI BED file" on page 69.
 - "To export the project output to a BAM file" on page 69.

To finish the project

After you click Finish, the NextGENe projects dialog box opens. This dialog box provides options for immediately running this single project, running multiple projects in sequence, running a secondary analysis on a previously run project, or exiting the wizard without running any projects.

Figure 2-17: NextGENe projects dialog box

NextGENe Pro	jects	
-		
E	Run NextGENe	
-	Create More Projects (New Project)	1
-	Create More Projects (Secondary Analysis)	1
	Exit Wizard	1

Do one of the following:

- To immediately run this single project, click Run NextGENe.
- To exist the Project Wizard without running the project, click Exit Wizard.



Although you did not run a project, because the Project Wizard "remembers" the settings from its last session, the next time that you open the wizard, you can run a project using these settings.

- To run multiple projects in sequence, see "To run multiple projects in a series using the Project Wizard" on page 72.
- To carry out a secondary analysis on the project that you just created, see "To carry out a secondary analysis" on page 72.

To run multiple projects in a series using the Project Wizard

Because the Project Wizard "remembers" the settings from its last session, every time you open the wizard, you can leave the settings as-is or modify them as needed. This means that you can use this approach to swap out sample files and configure multiple projects as needed with the same settings.



You can also run multiple projects in a series using the Project Log function. See "Batch Processing of Project Files Using the Project Log" on page 76.

1. Click Create More Projects (New Project).

A new Project Wizard session opens for configuring a project.

- 2. Leave the settings from the last session as-is, or optionally, modify the settings as needed.
- 3. After you configure your last project in the series, select Run NextGENe.

The projects are run individually in the order in which you created them.

To carry out a secondary analysis

You can use secondary analysis to set up a new project that is based on the output from a previously created project that has yet to be processed. After the previously created project is run, then the secondary analysis of its output files is automatically carried out.



You can also carry out a secondary analysis of a previously created project using the NextGENe AutoRun tool. See Chapter 9, "The NextGENe AutoRun Tool," on page 391.

1. Click Create More Projects (Secondary Analysis).

The Project Wizard is opened again.

2. Select the application type for the secondary analysis, and then click Load Data.

The Load Data page opens. The sample files and reference files from the previously created project remain loaded. The page now contains a Load Previous Run Result at the top of the page.

Figure 2-18: Project Wizard, Load Data page for a secondary analysis

oject Wizard - Loai	i Data	Show Project Log>
Step	Load data Previous run result: Load Previous Run Result	To convert to fasta:
	Sample files:	Format Conversio
Application	Ci\Data\test\test.fasta	Load
		Remov
I c ad Pia(ta		Removed

3. Next to the Sample files pane, click Removal All.

All the previously loaded sample files are removed.

4. Click Load Previous Run Result.

The Load Previous Run Result dialog box opens. The availability of what you can select for secondary analysis—Matched reads, Unmatched reads, Pseudo paired reads, Exported reads, and Assembled sequences—is dependent on the settings for the previous run.

Typically, Unmatched reads is always available for a secondary analysis.

Figure 2-19: Load Previous Run Result dialog box

C Matched rands C Unmatched read	s C	Pseudo paired reads	Exported reads	Assembled sequ	(ennes.
Unmatched Reads Files in Previous Run test_unmatched.fasta	_		Selected Unmatche	d Reads Files	
		Add to List ==>			
-		<==Remove from List			
	_		-	tri	-

5. Select the data type for the secondary analysis.

The Previous run result (Original) list is updated with the appropriate output files from the previous run.

6. Select the appropriate file or files (CTRL-click to select multiple files) in the Previous run result (Original) list, and then click Add to List.

The selected output files are moved to the Previous run result (Added) list.

7. Click OK.

The Load Previous Run Result dialog box closes. You return to the Load Data page in the Project Wizard. The added files are now displayed in the Sample files pane.


8. Modify any settings as needed, and then complete the running of the project in the wizard.

Saving and Loading Project Settings

Because NextGENe supports several instruments types and multiple applications, the settings for the analysis steps can easily vary from project to project; however, if you have a group of settings that you frequently use, and you do not want to recreate these settings every time that you need to use them, then you can save these settings to a Configuration file. Several pages in the Project Wizard contain a Save Settings button. When you click this button, you are prompted to name and save a configuration file with an .ini extension. This configuration file includes all the settings for the Sequence Condensation step, the Sequence Assembly step, and the Sequence Alignment step. On the same pages that have a Save Settings button, you can click a Load Settings button to load this file for any new project that uses the same data analysis steps and settings.



The Load Data information—the sample files, the reference files, and the output settings—are not saved in this configuration file.



Project Wizard - Conde	ensation	×
		Show Project Log>>
Step	Condensation General Settings	
	Instrument	Illumina
Application	Application	Other
	Read Counts	Less than 1 million
Load Data	Read Lengths	36
	Reference Length	Less than 1 Mbps Inspect Input
Condensation	Expected Depth of Coverage	Less than 30X Files
	Condensation Type	Consolidation Paired
Assembly		
Alignment		
Post Processing	Open Advanced Settings	
	Save Score	
		Save Settings Load Settings
	<< Back	Next >> Cancel Finish

To save project settings

- 1. Open the Project Wizard.
- 2. Select the application type, and confirm that your current settings for the data analysis steps are as you want them.
- 3. Click Save Settings.

The Save As dialog box opens. By default, the file type is set to Configuration File (.ini) as shown in Figure 2-21 below.

```
Figure 2-21: Save as type default for project settings
```

Save as type: Configuration File(*.ini)

4. Enter a filename, browse to the location in which you are saving the file, and then click Save.

To load project settings

- 1. Open the Project Wizard.
- 2. Click Load Settings.

An Open dialog box opens.

3. Browse to and select the configuration file that contains the settings you want to load, and then click Open.

You return to the Project Wizard with the saved project settings loaded for the opened project.



Remember, the Load Data information—the sample files, the reference files, and the output settings—are not saved in the configuration file. You must specify this information for every Project Wizard project. Chapter 2 Project Setup

Batch Processing of Project Files Using the Project Log

As discussed in "To finish the project" on page 71, the Project Wizard provides the Create More Projects option which you can use to carry out the batch processing of a series of projects in the Project Wizard. When you this option, batch jobs are set up so they can be run to completion without manual intervention. Two other options that are available for the batch processing of project files are the Project Log and manually created .ngjob files. You can use the Project Log to quickly configure multiple projects, which is ideal if you have saved project settings files or you have many projects that use identical configurations. The Project Log also allows for manual intervention before you carry out batch processing. You can rename projects, create new projects, duplicate projects, and even save and load project settings. After you create multiple projects in the Project Log, you can then carry out batch processing of the projects in the log.



Sample data files must be in either.fasta format (which includes Roche .fna files and SOLiD System .csfasta files), or in .bam format. If the sample files are not in .fasta or .bam format, you must first convert the files to one of these formats before loading them. (See Chapter 3, "File Format and Conversion," on page 85.) If you used barcoding or multiplexing, then you must sort the data before you can load it. (See "The NextGENe Barcode Sorting Tool" on page 361.) To batch process project files without carrying out format conversion and/or barcode sorting separately, see Chapter 9, "The NextGENe AutoRun Tool," on page 391.

Project Log and Project Wizard

You can use the Project Log to quickly configure multiple new projects, or you can use the Project Log in conjunction with the Project Wizard to configure multiple projects. When you use the Project Wizard to create a project, the project information is automatically saved to the Project Log in temporary runjob files. As a result, you have several options for using the Project Log tool in conjunction with the Project Wizard to carry out batch processing of multiple project files:

- You can create a single project in the Project Wizard, use the Project Log functions to duplicate and modify this single project to create multiple projects for analysis, and then either run these projects from the Project Log immediately, or save the projects to a NextGENe job file and run them at a later date. See "To use the Project Log to create multiple new projects" on page 77.
- You can create a series of projects in the Project Wizard. The Project Log contains multiple tabs labeled Project1, Project2, Project3, and so on, which represent the projects in the order in which you created them in the Project Wizard. You can run these projects from the Project Log immediately, or save the projects to a NextGENe job file, and then run them at a later date. See "To use the Project Log and Project Wizard to batch process multiple project files" on page 79.

To use the Project Log to create multiple new projects

- 1. Do one of the following:
 - On the NextGENe main menu, click Process > Project Log Viewer.
 - Open the Project Wizard, and in the upper right corner of the wizard, click Show Project Log.

The Log View window opens. If you opened the Log View window from the main menu, then the Project Wizard also opens. If the Project Wizard does not contain a project, the Log View window is blank; otherwise, the Log View window is populated with the settings from the current/last run project in the Project Wizard.

Figure 2-22:	Project	Wizard and	Log	View	window
--------------	---------	------------	-----	------	--------

roject Wizard - Application Type	X	Log View
	<th>New Load Save Save As Show CMD</th>	New Load Save Save As Show CMD
Step Instrument Type		
C Roche/454		Project1
Application (Illumina		PROJECT: Remove Duplicate
C SOUD		
C Ion Torrent		
Load Data		SAMPLE: Load Remove All
Application Type		
C de novo Assembly		
Condensation		
C Transcriptome	E	
C ChIP-Seq	🔽 Alternative Splicing	
		REFERENCE: Load Preloaded Remove Remove All
ANGL		
C Forensic		
C CNV-Seq		
Alignment C Other		
Steps		
Post E Sequence Condenestio	0	CONFIGURATION: Save As Load
Processing		
Sequence Alignment		OUTPUT: Browse
Performance Settings:		
Number of Cores to be Us	red : 3 (1~4)	1
	Save Settings Load Settings	
		Run Close
	Next >> Cancel Finish	

- 2. Optionally, click New to clear all the settings from the current/last run project in the Project Wizard.
- 3. Create a project:
 - a. In the Project field, enter a descriptive name for the project. (If you intend to run this project at a later date, make sure that the name clearly identifies that project so that you can easily locate the project when needed.)
 - b. In the Sample field, leave the current settings as is, or click Load to select a different sample file.
 - c. In the Reference field, leave the current settings as is, or click Load or Preloaded as appropriate to select a different reference file.

Chapter 2 Project Setup

- d. In the Configuration field, click Save As to save the current settings in the Project Wizard to a configuration file and load this file for the project, or click Load to select a different configuration file.
- e. In the Output field, leave the current settings as is, or click Browse to select a different output location.
- 4. Do one of the following to add more projects:
 - Click Add Project. A second blank tab labeled Project2 is added to the Log View window.
 - Click Duplicate. A second tab labeled Project2 and populated with all the information from the Project1 tab is added to the Log View.



The project settings are duplicated for the project that is open when you click Duplicate. For example, if you have created Project1 and Project2, and you want to create Project3, you do so either by clicking Duplicate on the Project1 tab (which duplicates the settings for Project1), or by clicking Duplicate on the Project2 tab (which duplicates the settings for Project2).

5. Repeat Step 3 and Step 4 as needed to add all your projects.



To remove a project in its entirety, open the project tab, and then in the PROJECT pane, click Remove.

- 6. Do one of the following:
 - To run all the projects immediately in the order in which you created them, click Run.
 - To save all the projects to a NextGENe job file that you can run at a later date, click Save or Save As, and then go to "To run a saved job file" on page 80.

A NextGENe job file has an .ngjob extension as shown in Figure 2-23 below.

Figure 2-23: Saving a NextGENe job file

Save as type: NextGENe Job File(*.ngjob)

To use the Project Log and Project Wizard to batch process multiple project files



The NextGENe application provides multiple ways of working with the Project Wizard and the Project Log to create multiple project files for batch processing. For brevity and ease of use, this procedures describes only two of the available approaches above; however, you can use whatever method best suits your working needs.

- 1. Create one or more projects in the Project Wizard. See one of the following:
 - "Setting up a New NextGENe Project" on page 53.
 - "Saving and Loading Project Settings" on page 74.
- 2. Do one of the following:
 - On the NextGENe main menu, click Process > Project Log Viewer.
 - Open the Project Wizard, and in the upper right corner of the wizard, click Show Project Log.

The Log View window opens, populated with the settings from the current project in the Project Wizard.

Figure 2-24: Log View open after creating a project in the Project Wizard

t Wizard - Applicati	ion Type	Log View
	< <hide log<="" project="" th=""><th>New Load Save Save As Show C</th></hide>	New Load Save Save As Show C
Step	Instrument Type	Number of Projects: 1 Add Project
	C Roche/454	Project1
Application	Illumina	PROJECT: Remove Duplicate
	C SOLD	
Load Data	C Ion Torrent	SAMPLE: Load Remove Remove All
	Application Type	C: \Users\Spectrum Writing\Spectrum Writing Info\Active Clie
	C de novo Assembly	
Condensation	SNP/Indel Discovery	
	C Transcriptome 🔽 Alternative Splicing	* +
Assembly	C ChIP-Seq C SAGE	REFERENCE: Load Preloaded Remove All
- Albectifully	C SAGE	C:\Program Files (x86)\SoftGenetics\NextGENe\References\
	C CNV-Seq	
Alignment	C Other	
	Steps	• <u> </u>
Post Processing	☐ Sequence Condensation	CONFIGURATION: Save As Load
riocessing	F Sequence Assembly	C:\Users\Spectrum Writing\Spectrum Writing Info\Active Clie
	✓ Sequence Alignment	OUTPUT: Browse
	Performance Settings: Number of Cores to be Used : 3 (1~4)	
	Save Settings Load Settings	Run Close
	Next >> Cancel Finish	Liose

Chapter 2 Project Setup

- 3. You now have a variety of options to create multiple projects, including:
 - In the Project Wizard, clicking Finish, and then on the NextGENe Projects dialog box, clicking Create More Projects and then clicking OK.

A new wizard session opens for configuring a project. Because the wizard "remembers" the settings from its last session, leave the settings as is or modify them as needed. As you create a series of projects in the Project Wizard, the Project Log is updated with multiple tabs labeled Project1, Project2, Project3, and so on, which represent the projects in the order in which you created them in the Project Wizard.

- In the Project Log, using Add Project and Duplicate as needed to create multiple projects. (See "To use the Project Log to create multiple new projects" on page 77.)
- 4. For either option, after you have created all the needed projects, do one of the following:
 - Click Run to run these projects from the Project Log immediately.
 - Click Save or Save As to save the projects to a NextGENe job file and run them at a later date. See "To run a saved job file" below.



If you save the job file, it is saved with an .ngjob extension. See Figure 2-23 on page 78.


To run a saved job file



This section describes running a saved NextGENe job file using options in the Project Log. You can also use a text editor to manually create an .ngjob file. If you want to use a text editor to create a job file, SoftGenetics recommends that you first use the Project Log to create a file with a single project, which ensures that the file will have the correct format. You can then open this file in a text editor and copy the information for the existing project and modify it as needed to create other projects. Contact SoftGenetics at tech_support@softgenetics.com for assistance.

1. On the NextGENe main menu, click File > Load Project Log file.

In the Open dialog box, browse to and select the job file that you are loading. The Log View window and the Project Wizard open. The Log View window is populated with the settings from the loaded job file.



2. Click Run.

Specifying NextGENe Process Options

You use process options in NextGENe to specify the following:

- Whether to save local or network data in a temporary local folder.
- Whether to save post-processing outputs in a location other than the project output folder.
- View the location of the Template root directory, which is the directory in which all NextGENe AutoRun templates are saved.
- Set the location of the Geneticist Assistant installation directory.
- Whether to save the reference annotation files in the project folder, or simply link to the information, which greatly reduces the size of the output folder.

For some of these process options, you must specify a value, while for other options, default values are provided. Typically, these default values are the preferred values; however, if needed, you can edit some of these values. You can also use the options that are available to manage your references for your NextGENe projects.

To specify NextGENe process options

1. On the NextGENe main menu, click Process > Options.

The Options dialog box opens.



Options	— ×-
Process	
✓ Use local temp directory ✓ Only for remote data	
C:\Users\Spectrum Writing\AppData\Local\SoftGenetics\NextGENe\LocalTemp	Set
Save copies of reports to directory	
	Set
Template root directory	
C:\Users\Public\Documents\SoftGenetics\NextGENe\Templates\	Set
GA executable path	
	Set
✓ Save a copy of annotation to project folder	
OK Cancel	

Chapter 2 Project Setup

- 2. Optionally, do any or all the following as needed:
 - Use the Local Temp Directory option to process network or local data files on a specified local drive without having to manually transfer the data files. Instead, NextGENe automatically transfers the data files for processing to the indicated temporary local directory, which reduces the data processing time. After the project is run, NextGENe removes the data files from the temporary local directory and stores them back onto the appropriate local or network drive.
 - To process *network* data, leave both Select Use local temp directory and Only for remote data selected.
 - To process *local* data files, leave Select Use local temp directory selected and clear Only for remote data.

For either option, you can leave the default Temp folder location set as-is, and or click Set to open the Browse for folder dialog box, and browse to and select the a different folder for temporary data storage.

- By default, post-processing outputs are saved to the project output folder. To also save these outputs in a single global location, select Save copies of reports to directory, and then click Set to open the Select copies of outputs folder dialog box, and browse to and select the appropriate folder.
- All NextGENe AutoRun templates are saved in the Template root directory. The default value is C:\Users\Public\Documents\SoftGenetics\NextGENe\Templates\ and SoftGenetics strongly recommends that you do *not* modify this value.
- If you intend to export any outputs to Geneticist Assistant, then you must specify the location of your Geneticist Assistant installation. Click Set to open a dialog box, and then browse to and select the Geneticist Assistant executable (geneticist_assistant.exe).



If you have not changed the default location for the Geneticist Assistant executable, then it is located in: C:\Program Files\Softgenetics\Geneticist Assistant\ga_exe.

- By default, Save a copy of the annotation to the project folder is selected, which results in the reference annotation information being saved to the project output folder. Do one of the following:
 - Although this increases the size of the output folder, you should leave this option selected if your projects are regularly copied to multiple computers for viewing.
 - Clear this option to simply link the reference annotation information to the project output folder.



Although linking to the annotation information instead of saving it reduces the size of your projects' output folders, you should select this option only if your projects are not regularly copied to multiple computers.

3. Click OK.

The Options dialog box closes. Your process options are saved.

Chapter 2 Project Setup

Chapter 3 File Format and Conversion

The Roche Genome Sequencer FLX and FLX Titanium Systems, the Illumina Genome Analyzer and Life Technologies's SOLiD System or Ion Torrent sequencer generate millions to hundreds of millions of the short sequence reads, and each instrument supplier has its own format or formats for organizing the reads and assigning the quality scores. Before you use NextGENe to analyze this data, you must use the NextGENe Format Conversion Tool to convert the supplier's format to a standard .fasta format that NextGENe can read. Optionally, you can also use the tool to trim or remove low quality reads before analysis.

This chapter covers the following topics:

• "NextGENe's Format Conversion Tool" on page 87.



Although NextGENe provides many tools for optimizing input data and exporting results, the Format Conversion Tool is the most commonly used of all the tools and that is why it is afforded its own chapter. All other NextGENe tools, with the exception of the NextGENe AutoRun tool, are discussed in detail in Chapter 8, "NextGENe Tools," on page 359. The NextGENe AutoRun tool is discussed in Chapter 9, "The NextGENe AutoRun Tool," on page 391.

Chapter 3 File Format and Conversion

NextGENe's Format Conversion Tool

The NextGENe Format Conversion tool converts the format that the instrument uses to organize reads and assign quality scores to a standard .fasta format that NextGENe can read. In .fasta format, comment lines are marked with the greater than (>) symbol. The comment line contains the name that is assigned to a read. The sequence read base call line follows the comment line.

Figure 3-1: Example of a NextGENe .fasta file

>s 5 0001 5 1 84 598
GTTATTTAACATAAGGTTATAGAACTCTCTACACTT
>s_5_0001_5_1_482_766
GTATAGAGTTCTATAACCTTATGTTAAATAACCTCA
>s 5 0001 5 1 742 905
GCTGCTAATTAATGAAGGTTATAGAACTTAATTGGT

Figure 3-1 above shows three of the reads in a .fasta file that is named is "s_5.fasta." Each sequence read contains 36 nucleotides, and the name assigned to each read (from top to bottom, respectively) is: _0001_5_1_84_598, _0001_5_1_432_766, and _0001_5_1_742_905. You can specify values for quality settings to trim or remove low quality reads before you convert a supplier's format to NextGENe's .fasta format.

To convert a sample file



Before you begin the file conversion process, review the information in the table below and make sure that you have correctly named your files or carried out any other needed preparation before you load them in to the NextGENe Format Conversion tool. In addition, before you convert the file, you can use the NextGENe File Preview tool to preview some basic information about the file, which can be helpful for determining settings for the File Conversion process. See "The NextGENe File Preview Tool" on page 390.

File Format	Comments
SEQ/PRB	The file names do not need to be identical, but they must be appended with the phrases "_seq" and "_prb" respectively. For example, SRR01842a_seq.txt and SRR01842c_prb.txt.
FASTQ (merged pairs)	Select this option for paired end files in FASTQ format that contain both reads in a pair in the same line in opposite orientation (Read 1 -> <- Read2). NextGENe converts these files by splitting each read in two. Two new files are created titled *_1.fasta and *_2.fasta with read names >*/1 and >*/2. The second half of the original read and the quality scores are reverse complemented. The file is then converted to .fasta format and quality filtering is implemented as with other FASTQ files.
SCARF Numeric SCARF ASCII	Caution: Make sure to choose the correct quality score format— either Numeric or ASCII.

Chapter 3 File Format and Conversion

File Format	Comments				
• CFASTA	The SOLiD System instrument produces color space sequence reads in a .fasta format labeled as CSFASTA. If you select the CFASTA option and choose FASTA as the output format type, then NextGENe converts the reads from color space to base space.				
	Note: Errors in color space can lead to the propagation of errors downstream within the read when converted to base-space, so SoftGenetics recommends that you leave the reads in color space.				
	You can select CSFASTA as the output format type to quality filter the CSFASTA files without conversion. If you select this option, the output file remains in color space. This option can be used to quality trim reads while maintaining color-space.				
	Note: This is the preferred conversion option for SOLiD System data.				
	Note: You can quality trim reads using the .csfasta and .qual files only if the file names are identical, for example, SRR01842.cfasta and SRR01842_QV.qual.				
FASTA	Select this option and choose CSFASTA as the output format type to convert .fasta files in base space into .csfasta files in color space.				
Mate-Pair SFF	Select this option for mate-pair files in SFF format that contain both reads in a pair in the same line. NextGENe converts these files by splitting each read in two. Two new files are created titled *_1.fna and *_2.fna with read names >*/1 and >*/2. The file is then converted to .fasta format and quality filtering is implemented as with other SFF files.				
Mate-Pair FASTQ	Select this option for mate-pair files in FASTQ format that contain both reads in a pair in the same line. NextGENe converts these files by splitting each read in two. Two new files are created titled *_1.fna and *_2.fna with read names >*/1 and >*/2. The file is then converted to .fasta format and quality filtering is implemented as with other FASTQ files.				

- 1. Do one of the following:
 - On the NextGENe main menu, click Tools > Format Conversion.
 - In the Project Wizard, on the Load Data page, click Format Conversion.

The Format Conversion dialog box opens.

Figure 3-2:	Format	Conversion	dialog	box
-------------	--------	------------	--------	-----

61	
Instrument	
Type : Illumna	
Input	
Sample files :	-
	Add
	Remove
	Remove All
Input format type : BAM	
Output	
Output format type : FASTQ Output :	
	Set
Settings	
I I </td <td><= 3</td>	<= 3
Called base number of each read >= 25	
Trim or reject read when >= 3 base(s) with score <= 16	
P Foreitream data	
□ Remove 5' 0 base(s) and 3' 0 base(s)	efault Settings
T Keep only bases 0 0	
Trim by sequences	
T Trim by sequences in file	•
F Oustom/Infe	

- 2. On the Instrument pane, select the instrument type.
- 3. In the Input pane, do the following:
 - a. Click Add to browse to and select the input data file.

After you load the file, NextGENe automatically selects the correct instrument/file type option in the Instrument pane.

b. On the Input format type dropdown list, select the input format type, for example, BAM.

- 4. In the Output pane, do the following:
 - a. On the Output format type dropdown list, select the output format type.
 - b. In the Output field, you can leave the default value for the location of the output files as is (the default value is the directory path for the last input data file that you selected), or you can click Set to select a different location.
- 5. Optionally, in the Settings pane, do one of the following:
 - Click Default Settings to automatically select the quality settings that SoftGenetics has determined, from experience, are appropriate for the file type that is being converted.
 - Select the options by which you want to filter and trim low quality reads.



Even if you select the options by which to filter and trim low quality reads, at any time, you can click Default Settings to clear your options and replace them with SoftGenetics's preset values.

- Click Load to browse to and select a Settings file (.ini file) to convert the files based on the saved settings in the file.
- 6. Optionally, before you process the files, click Save to save the settings that you have specified to a Settings file (.ini file).



You can always load this file at a later date and process other data files according to the saved settings in the file.

7. Do one of the following:

- Click Add Job to save this job, and open another tab for a file conversion. Repeat this step to add all needed conversion jobs, and then click OK to run the jobs in the order in which you created them. The converted files are saved in the directory that you specified in Step 4.
- Click OK to immediately run this job. The converted file is saved in the directory that you specified in Step 4.

The conversion generates the following output files:

Figure 3-3: Output files generated by the NextGENe Conversion tool

SRR018422_convert.log	1/26/2010 2:39 PM	Text Document	5 KB
SRR018422_converted.fasta	1/26/2010 2:39 PM	FASTA File	343,785 KB
SRR018422_removed.fasta	1/26/2010 2:39 PM	FASTA File	18,418 KB

Figure 3-4: Example of a .log file generated by the NextGENe Conversion tool

Filter F	Results]
Total F	Reads in the Input File]: 10651414
	[Reads Converted Successfully]: 10179982
	[Reads Failed to Convert]: 471432
	[Reads Filtered by "Median Score"]: 352853
	[Reads Filtered by "Uncalled Bases"]: 62188
	[Reads Filtered by "Called Base Number in Each Read"]: 111
	[Reads Rejected by "Base's Score"]: 56280
	[Reads Trimmed by "Base's Score"]: 1177117
	[Trimmed Bases by "Base's Score"]: 17764943

Trim or Reject Read While >= [x] Bases with Score <= [y]

With this option selected, the software inspects only the 3'ends of reads for consecutive low quality base calls. For Illumina and SOLiD System reads, the second half of the read is examined. NextGENe searches for the first base from the 3'end that has a quality value above the threshold. If no such bases are found, the entire read is removed. If the software finds a base that is above the threshold, it then searches the second half of the read from the 5' end for at least "X" number of consecutive bases below the threshold. If this condition is met, the read is trimmed from this point back to the 3' end of the read.

For Roche reads, only the last 20% of the read is examined. The software starts at the 5' end of the last 20% of the read to find a base with a quality score above the threshold. When a base is found with a score above the threshold, the software then searches for at least "X" number of consecutive bases with scores below the threshold. When this condition is met, the read is trimmed from this point back to the 3' end of the read. Homopolymers are ignored.

Trim by Sequences

NextGENe allows for trimming by sequences in two cases:

- The sequence has an error in it.
- Only part of the sequence is present.

In these situations, NextGENe breaks the input sequence into smaller segments and checks the read for the small segments instead of the whole sequence.

- If the input sequence is >= 16 bp, then it is broken into small segments with a length of 12 bp.
- If the input sequence is < 16 bp but > 7 bp, then it is broken into small segments with a length of 8 bp.
- If the input sequence is < 8 bp but > 3 bp, then it is broken into small segments with a length of 4 bp.

No mismatches are allowed for an input sequence < 4 bp.

Trim by Sequences in the File

The file that contains the trimming sequences is a tab-delimited text file with up to four fields:

Field	Description
1st	Name
2nd	5' Trim Sequence
3rd	3' Trim Sequence
4th	Option Code:
	E - Exact match
	L - Loose match
	P - Partial match

Loose match uses the method described in "Trim by Sequences" with the following caveat: An input sequence with a length < 4 bp cannot be used for Loose match; however, the sequence can be used for Partial match and miRNA trimming. (See "miRNA Trimming" on page 372.)

In a Partial match, just a single base can be matched. Partial match allows for mismatches up to 10% of the matched length. This means the following:

- No mismatches are allowed if the adapter is < 10 bp in length or if only 10 bp of the adapter are overlapped.
- The adapter must be at the end of the read. 3' sequences can only partially overlap at the beginning of the sequence and the end of the read while 5' sequences can only partially overlap at the end of the sequence and the beginning of the read.

Values for the first and fourth fields are always required. Because you are trimming by sequence, you must have at least one sequence. This means that a trim sequence for either the second or third fields is required. If you have a 5' trim sequence (second field), then the 3' trim sequence (third field) is optional. Conversely, if you have a 3' trim sequence (third field), then the 5' trim sequence (second field) is optional. You still must use a placeholder if you do not have values for an optional field. For example, if you have a 5' trim sequence (second field), but not a 3' trim sequence (third field), then you must still enter a dash (-) in the third field, which is used as a placeholder.



This option is backwards-compatible with older text formats. Loose match is assumed for the Match Type.

If both 5' and 3' sequences are specified, then the 5' sequences are checked first. If multiple

matches are found, then the best match for both the 5' and 3' ends are used for trimming.

Chapter 3 File Format and Conversion

Chapter 4 Sequence Condensation Tool

The NextGENe Condensation Tool uses depth of coverage to correct sequence reads that contain instrument base calling errors and to elongate reads, while merging identical reads or maintaining read number as necessary for your project.

This chapter covers the following topics:

- "Overview of the NextGENe Sequence Condensation Tool" on page 97.
- "Sequence Condensation Tool General Settings" on page 102.
- "Sequence Condensation Tool Advanced Settings for Illumina Data, SOLiD System Data, or Ion Torrent Data" on page 106.
- "Sequence Condensation Tool Advanced Settings for Roche/454 Data" on page 112.
- "Sequence Condensation Tool Output Files" on page 113.

Chapter 4 Sequence Condensation Tool

Overview of the NextGENe Sequence Condensation Tool

The NextGENe Condensation Tool uses depth of coverage to correct sequence reads that contain instrument base calling errors and to elongate reads, while merging identical reads or maintaining read number as necessary for your project. Three methods are available for condensation—Consolidation, Elongation, and Error Correction. All three of the methods correct low frequency instrument errors by generating a consensus sequence from clustered reads. The type of data that you are analyzing—Illumina, SOLiD System, Ion Torrent, or Roche/454— determines the available methods.



If you load multiple sample files for analysis, all the data is evaluated as whole, not by individual sample files.

Illumina, SOLiD System and Ion Torrent data

If you are analyzing Illumina data, SOLiD System data, or Ion Torrent data, then all three condensation methods—Consolidation, Elongation, and Error Correction—are available and all three methods use the same general method for clustering similar reads and generating a consensus sequence. Reads are evaluated for common indices, or anchor sequences, that can be found in multiple sequencing reads. All sequence reads that contain an identical 12 bp anchor sequence form a group. Because this sequence might not be unique within the genome, the groups are organized into separate subgroups based on the anchor's flanking shoulder sequences, which are the left and right bases that are immediately adjacent to the anchor sequence. Reads that contain, at a minimum, both shoulder sequences are called bridge reads. Bridge reads can also extend past or "bridge" both shoulder sequences. To form a subgroup, a minimum number of bridge reads are required. By evaluating the shoulder sequences on either side of the anchor sequence, a single group can be divided into multiple subgroups with an identical anchor sequence and varying shoulder sequences. Although reads contain an identical 12 bp anchor sequence, multiple subgroups might exist because of a variant or polymorphism within a shoulder sequence or a given 12 bp anchor sequence might occur more than once in different regions of the genome.

Each subgroup can be used to generate a consensus sequence. For Illumina data, SOLiD System data, and Ion Torrent data, it is assumed that the quality of bases that are at the 5' end of each read is higher than the Phred 20 quality scores and that the remainder of the read is of lower quality, which results in the base calls that are on the 5' end of the sequences having a higher weight of accuracy. The consensus base calls are calculated by scoring each nucleotide that is seen at a given position according to the following rules:

- 5' sequences are assigned a higher weight than 3' sequences.
- Each 5' read with a given nucleotide is assigned a score of 7.
- Each 3' read with the same given nucleotide is assigned a score of 2.

Chapter 4 Sequence Condensation Tool

• Scores for all the reads with the same nucleotide are summed to provide the score for the nucleotide.

Score for Nucleotide "x" = (7 x No. of 5' reads) + (2 x No. of 3' reads)


For example, consider the case in which a position within a subgroup of reads includes some reads that show a "T" at a given position while other reads show a "C" for the position. The "T" nucleotide is seen in the 5' end of two reads and in the 3' end of six reads. The "C" nucleotide is seen in the 5' end of four reads and in the 3' end of two reads. To determine the consensus base call, quality scores are calculated for both the "T" and "C" nucleotides as follows:

- Score for the "T" nucleotide = $(7 \times 2) + (2 \times 6) = 26$
- Score the for "C" nucleotide = $(7 \times 4) + (2 \times 2) = 32$

Because the score for the "C" nucleotide is greater than the score for the "T" nucleotide, the consensus sequence includes a "C" nucleotide at this position.

Consolidation

When you use the Consolidation method of condensation for Illumina data, SOLiD System data, or Ion Torrent data, overlapping sequences are merged and the consensus sequence is used in place of all the original reads that are in the subgroup. Information about the original reads, however, is maintained so that the original coverage information is not lost. The Consolidation method is recommended for datasets that have a high depth of coverage in the raw reads. Figure 4-1 below is an example of the output from the Condensation Tool when Consolidation is selected for the condensation method.






Figure 4-2 below is an example of the output consensus sequences and their read names, which reflect the anchor sequence, shoulder sequences, and counts of forward and reverse reads used.

Figure 4-2: Output consensus sequences

>1	CTTTGGAACCTC	24	ACACATGGCT	CTCTGCCTCC	105	95
TTCAGT	ATTACATGACACATG	GCTCTT	TGGAACCTCCTCTGCC	TCCACTCTGCCCAGC	IG	
>2	AGACCTACAAAT	24	TAGAGGAATTAA	AACAGACTGAAA	831	714



For detailed information about viewing Condensation Tool results when Consolidation is the selected method, see "The NextGENe Condensation Results Tool" on page 383.

Elongation

When you use the Elongation method of condensation for Illumina data, SOLiD System data, or Ion Torrent data, overlapping reads are not merged. Instead, a new elongated read with errors corrected is created for each read in the subgroup. Because a given read is likely to match more than one anchor sequence, all instances of a given read are pooled "as is" into multiple subgroups. These corrected and elongated reads are then compared to each other to produce a single consensus sequence. Reads that do not match any of the indices are not removed as in consolidation, but instead, are kept in the output file.




The Elongation method is recommended for datasets that have low coverage in the raw reads, and for paired end/mate paired data.


Error Correction

The Error Correction method is very similar to the Consolidation and Elongation methods. Reads are clustered in the same fashion and low frequency errors are corrected; however, read length is not extended and reads are not merged. Instead, each original read is maintained at its original length with the instrument errors corrected.

Figure 4-3 on page 100 is an example of SNP discovery using the Condensation Tool. On the left side of this figure, raw reads are aligned to the reference. Low frequency variations, most likely errors, are highlighted in gray while variant calls are highlighted in blue. On the right of the figure, condensed reads are aligned to the reference. The likely errors were eliminated while the true SNP was maintained.

Chapter 4 Sequence Condensation Tool





Roche/454 data

Roche/454 produces longer reads than Illumina or the SOLiD System; however, the reads that are produced are fewer in number. As a result, when Roche/454 is selected as the instrument type, the only condensation method that is available is an Error Correction method that has been specifically designed to correct homopolymer errors and other base calls errors that are produced by the pyrosequencing technique. Roche/454 Error Correction works by parsing sequencing reads into shorter keywords and comparing the keywords between the reads to help determine the correct bases at the ends of each keyword. Keywords are produced by dividing the reads where a homopolymer is found and there are at least 16 bases between the homopolymers. Reads that include variations that are found at low frequencies are corrected. You can set relative and absolute frequencies for acceptable variations. Figure 4-4 on page 101 is an example of indel discovery using the Condensation Tool. In this figure, a 13 bp deletion of "TGACCATACACCA" was detected at position 12243-12255.



Figure 4-4: Indel discovery using the Condensation Tool

Sequence Condensation Tool - General Settings

		-1
		Show Project Log>
Condensation General Settings		
_		_
Instrument	Illumina	
Application	de novo Assembly	_
Read Counts	Less than 1 million	•
Read Lengths	36	
Reference Length	Set Manually(Kbps):	Inspect Input
Expected Depth of Coverage	Less than 30X	▼ Files
Condensation Type	Consolidation	▼ Paired
Open Advanced Settings		
Open Advanced Securitys		
Save Score		
	Save Settings	Load Settings
<< Back	Next >> Car	ncel Finis
	Read Counts Read Lengths Reference Length Expected Depth of Coverage Condensation Type	Instrument Illumina Application de novo Assembly Read Counts Less than 1 million Read Lengths 36 Reference Length Set Manually(Kbps): 0 Expected Depth of Coverage Less than 30X Condensation Type Consolidation Open Advanced Settings Save Score Save Score

Figure 4-5: Condensation Settings page, General Settings

Setting	Description		
Inspect Input Files	Available only if you are analyzing Illumina data, SOLiD System data, or Ion Torrent data. Click this button to have the Condensation Tool scan your data files and determine optimum settings on this page as well on the Advanced Settings page.		
Read Counts	The range that best describes the number of reads that are included in your sample dataset. After you click Inspect Input Files, the value for Illumina datasets, SOLiD System datasets, or Ion Torrent datasets is automatically set, but you can modify the value if needed. Note: If multiple data files are being analyzed, this value is the total for all files.		
Read Lengths	The number that best represents the length of reads for your sample dataset. After you click Inspect Input Files, the value for Illumina datasets, SOLiD System datasets, or Ion Torrent datasets is automatically set, but you can modify the value if needed.		

Chapter 4 Sequence Condensation Tool

Setting	Description				
Reference Length	The number that best represents the length of reads for the reference sequence. When a reference file is loaded, after you click Inspect Input Files, the value for Illumina datasets, SOLiD System datasets, or Ion Torrent datasets is automatically set but you can modify the value if needed. For preloaded reference files, you must manually enter the value. Note: For <i>de novo</i> Assembly, which does not include a reference file,				
	you can manually specify this value, which is used to estimate the expected coverage.				
	Figure 4-6: Manually specifying the reference length for a de novo Assembly				
	Reference Length 🗌 Set Manually(Kbps):				
Expected Depth of Coverage	The range that best represents the expected depth of coverage for your sample dataset. After you click Inspect Input Files, the value for Illumina datasets, SOLiD System datasets, or Ion Torrent datasets is automatically set to the total number of bases in sample files divided by the number of bases in reference file. For identifying low frequency variations, the Expected Depth of Coverage should be set to that of the minor allele. You can modify the value if:				
	There are many reference positions that will have no coverage.				
	• There are many bases of sample file that will not match to the selected reference.				
	• The minor allele might be found at a depth of coverage lower than what was calculated.				
Condensation Type	For Illumina data, SOLiD System data, or Ion Torrent data, select one of the following:				
	Consolidation (to reduce read number)				
	Elongation (to maintain read count)				
	 Error Correction (to reduce errors without reducing read count or lengthening reads) 				
	For Roche/454 data, the only available option is Error Correction.				


Chapter 4 Sequence Condensation Tool

Setting	Description					
Paired	Available only if you select Elongation for Illumina data. Click this option to open the Merge Overlapping Paired Reads dialog box.					
	Figure 4-7: Merge Overlapping Paired Reads dialog box					
	Merge Overlapping Paired Reads					
	Image: Coverlapping Paired Reads Overlap Min Base Image: Coverlapping Paired Reads Image: Coverlapping P					
	setting an acceptable length for the merged results					
	 Merged Length [] bp to [1000] bp Merged Length [70] bp to [130] % of the longer read length 					
	You can select one or both options; however, if you select both options, then the data must meet both criteria to be included in the results.					
	Note: The recommended value for the minimum number of bases that must overlap so that paired reads are correctly merged is nine. You can select a value that is less than nine, but this means that there is less overlap that is required between the paired reads, so your results might be less reliable. You can also select a value that is greater than nine, but an increased value requires more overlap for the reads to be merged, which might result in less paired reads being merged. See "Merging Paired End Reads" on page 105.					
Save Score	Creates a .qual file that contains information about the number of reads that are used in each subgroup for condensation.					

Merging Paired End Reads

With NextGENe's Paired End Merging functionality, you can merged paired end reads by elongating the paired reads to the point that there is overlap between the two reads. The paired reads can then be joined together to form one continuous, longer read.

Figure 4-8: Merging overlapping paired end reads



The number of elongation cycles that is required depends on the read lengths and the library size. Each condensation cycle generally increase the average read length to 1.6 the original length for shorter (<=36 bp) reads and to 6 bases less than twice the original length for longer (>36 bp) reads. These values might be reduced with an average depth of coverage less than 30x. For 75 bp reads from a 200 bp library, for example, a single cycle of elongation results in the reads being elongated enough for the paired reads to overlap. For 35 bp reads from a 200 bp library, three cycles of elongation are needed. You should extend the reads until a significant portion of the paired reads (roughly 15% of the elongated read length) are expected to overlap.

Figure 4-9:	Average read	lengths after	elongation fo	r varying original re	ead lengths

Original Read Length	35 bp	50 bp	75 bp
Avg Read Length After 1 Cycle of Elongation	56 bp	88bp	138 bp
Avg Read Length After 2 Cycles of Elongation	90 bp	160 bp	1
Avg Read Length After 3 Cycles of Elongation	144 bp		

The paired reads are merged only if the overlapping regions match between the reads. Errors resulting from sequencing chemistry, basecalling, or the initial assembly by elongation will not match with the paired read, so the pair would not be merged.

Sequence Condensation Tool - Advanced Settings for Illumina Data, SOLiD System Data, or Ion Torrent Data

For the Illumina, SOLiD System, and Ion Torrent instrument types, the available settings are the same, and the default values for the advanced settings are populated based on the Read Lengths and Expected Depth of Coverage values that were set in "Sequence Condensation Tool - General Settings" on page 102. You can leave these settings as is, or you can modify the settings. At any time, you can click Default Settings to automatically reset all the values to SoftGenetics's default values.

Figure 4-10:	Condensation	Settings page,	Advanced	Settings for	[.] Illumina	data,	SOLiD
	System data, of	r Ion Torrent da	ata				

ndensation Jumber of Cycles: 1 Set Memory Ratio 1 View Condensation Results
Minimum Read Length for Condensation 25 Bases One Index/Read
✓ Range in Read to Index : 1 Bases to Length minute 6 Bases
Auto Indexing Based on Expected Coverage = 500 X(>500) Reads Required for Each Group in One Direction 5 to 60000 Reads Required for Each Group in Each Direction 2 to 60000
Bridge Reads Required for Each Subgroup: 2 and 1 % Total Reads Required for Each Subgroup: 5 and 0.2 % Recover Best Subgroup for Repeat Indexes
Forward and Reverse Balance 0.1 (0~0.5) Remove Indexes with PCR bias: Min. Ratio = 20 Min. Coverage= 100
C Fixed Shoulder Sequence Length = 12 Bases C Fixed, then Extended Shoulder Length = 12 Bases and Score <= 1.01 C Flexible Sequence Length = 11.9.7. (10.8.6) C Homopolymer Index Checking
Start Index at 2 (2 or 3) Homopolymers AT,GC,ATT, Complements Use Only 5' Bases for Consensus
✓ Remove Low Quality Ends when Score <=
Index Error Correction if Frequency <= 15 % of Majority Index
Default Settings

• Number of Cycles—The default value is 1. After one cycle, many of the instrument's base call errors are corrected, which is ideal for applications such as SNP/Indel discovery. Additional cycles help to remove some of the systematic instrument errors and low frequency variations. Also, additional cycles further elongate the reads while correcting some of the discrepant variations between the reads. Four cycles of condensation can increase many reads from 35 bps to an excess of 150 bps, which is ideal for some applications such as de novo assembly or the discovery of large indels.



If more than one condensation cycle is used, you can specify the values for the advanced settings for each cycle independently.

- Memory Ratio—Available only for 32-bit OSs. Because of memory constraints, the Condensation Tool parses large sample datasets as needed and processes each partition separately. When the Memory Ratio is set to 1.00, the software loads a pre-set number of sequence reads. If you increase the value for the memory ratio, more reads are loaded into memory, but this might result in limited computer resources and therefore, the inability to use your computer for other functions.
- View Condensation Results—Select this option to view the condensation results in the Condensation Results tool when Consolidation is the selected method. See "The NextGENe Condensation Results Tool" on page 383.
- Minimum Read Length for Condensation—Excludes sequence reads that are less than the specified value from the condensation. The minimum value allowed is 14 bp.
- Range in Read to Index [x] Bases to Length minus [y] Bases—Ignores the lower quality bases at the ends of reads during indexing. These bases are still used for the condensation but they are not included as anchor sequences. For example, if x=1 and y=3, all bases from the first base to the last three bases from the end are used for indexing. To allow indexing of all bases, set x=1 and y=0.
- Auto Indexing Based on Expected Coverage = [x]—Recommended only for high coverage datasets (average coverage> 500). Set "x" equal to the expected average coverage. This provides an alternative to individually specifying values for each of the next four coverage settings. The Condensation Tool can then use the expected average coverage to calculate appropriate coverage requirements.



The minimum allowable value for this setting is 500. With an expected coverage of less than 500x, auto-indexing is less accurate and is not recommended.

• **Reads Required for Each Group in One Direction [x] to [y]**—Prevents the indexing of fragments that might have errors, repeats and redundancies. The number of reads with a given anchor sequence in the same direction (either forward or reverse) must be within this range. An anchor sequence is added to the index table and used to form a group when the exact anchor sequence is found in a number of reads that have same direction and that is greater than or equal to the lower limit and less than or equal to the upper limit.

For example, consider a case where the lower and upper indexing limits are set to 10 and 6000 respectively. In this case, the 12 base pair anchor sequence of ACCAGAAGTTTA is added to the index table only if it is found in at least 10 forward reads or 10 reverse reads but less than 6000 sequence reads in the same direction. If this index is found in less than 10 reverse reads and less than 10 forward reads then it is considered noise and is not needed in the index table. If the sequence is found in more than 6000 reads in the same direction, then it is a fragment that is difficult to assemble (often because of a repeat) and it also is not added to index table.

- **Reads Required for Each Group in Each Direction [x] to [y]**—Specifies the number of reads that are required to match an anchor sequence in both directions for it to be included in the index table. The number of forward reads and the number of reverse reads that match the anchor sequence must be within this range. For data that is either completely one-directional or primarily one-directional. set this value to equal to -1.
- Bridge Reads Required for Each Subgroup: [x] and [y%]—"x" indicates the minimum count of bridge reads required to form a subgroup. "y" indicates the minimum percentage of reads within the subgroup that must be bridge reads. For data that is either completely one-directional or primarily one-directional, set both of these values equal to -1.

For example, consider this setting with values of 2 and 1%. For the ACCAGAAGTTTA index, 1000 reads contain this anchor sequence. Of these 1000 reads, a total of 150 reads match at least one of the shoulder sequences. Twenty reads out of these 150 reads contain the same eight nucleotides of CGGATTCC to the left of the index and the same eight nucleotides of TGCCATGC to the right side of this index. These shoulder sequences are therefore are used to form a subgroup with these 150 reads because more than two reads (20 in this example) and more than 1% (13% in this example) of the reads are bridge reads.

- Total Reads Required for Each Subgroup: [x] and [y%]—The number of reads that have identical anchor sequence and that contain similar shoulder sequences must be within the specified range to form a subgroup.
- **Recover Best SubGroup for Repeated Indices**—Only the first instance (from the 5' end) of the repeat is indexed and only the unique shoulder sequence is used for repeat indices.
- Forward and Reverse Balance—Sequencing artifacts produce significant imbalances between the number of reads in each direction. If selected, false positives due to PCR bias or other directional bias are reduced. Indices are checked for the number of forward reads and the number of reverse reads that match the anchor sequence. Indices are excluded from the index table if the ratio of the number of reads in either direction to the total number of reads in the other direction is below a set threshold. clear this option for data that is either completely one-directional or primarily one-directional.

For example, if an index contains 100 forward reads and 10 reverse reads, then the ratio of reverse reads to forward reads is 0.1 If this option is set to a value of 0.2, then this index is removed from the index table and no condensed read is produced for the index.

- Remove Indices with PCR bias: Min. Ratio = [x] Min. Coverage = [y]—Amplification bias is sequence dependent, which results in some anchor sequences containing a large number of sequence reads in disproportionate levels. If selected, reads that meet or exceed the specified threshold settings are not used for indexing.
- Fixed Shoulder Length Sequence = [x] bases—Evaluates shoulder sequences of a set length. All reads within a single group contain the identical 12 base pair index. Reads within the group can vary within the shoulder sequences. Reads that are used to create a consensus sequence must contain an identical ("x" + 12) bp sequence. For example, if this value is set to 8, then the reads used for creating a consensus sequence must contain an identical 28 base anchor—8 bases to the right of index, a 12 base index, and 8 bases to the left of index.
- Fixed, then Extended Shoulder Length = [x] Bases and Score <= [y]—This option is useful for assembling condensed reads that have been run through at least one condensation cycle. The fixed shoulder length is checked first, and then is rescanned with some variation being tolerated. If the shoulder bases are the same, then all corresponding bases between the reads are checked. A score is calculated to determine the amount of variation among the reads. A one base difference yields a score of 1 for the position if it is not at the end of a read. The score for a difference in the 1st and last 3 bases is 1/2. The score must be below the set threshold for the read to be used in the subgroup. If the score is set to 1.01 (the default value), then the tool condenses reads containing two differences at the ends and just one difference for the middle bases.
- Flexible Sequence Length = [x], [y], [z]—Sets less stringent criteria for shoulder sequence length. Specify the values from largest to smallest, for example, "10, 8, 6." Given these settings, the Condensation Tool initially attempts to find sequences with 10 bp matching shoulder sequences; however, it also looks for sequences that have 8 bp matching shoulder sequences and then finally, 6 bp matching shoulder sequences.
- **Homopolymer Index Checking**—Reduces the size of the index table that is generated for condensation. Instead of indexing every 12 bp anchor sequence, only 12 bp sequences that occur before and after homopolymers of three or more bases are used. The regions that are adjacent to homopolymers are also used for shoulder sequences instead of the regions that are directly adjacent to the anchor sequence.
- Start Index at [x] (2 or 3) Homopolymers or [] AT, GC, ATT ... Complements—Evaluates anchor sequences starting at positions where a homopolymer of two or three bases (as determined by the value set for [x]) is found. Anchor sequences will begin at the second base of the homopolymer. For instance, where a sequence of "AACTGTC..." occurs, the anchor sequence will begin as "ACTGTC..." To provide a sufficient number of anchor sequences, combinations of "GC" "CG" "AT" and TA" are also used to indicate the start of an anchor sequence. With both of these options selected, the condensation speed is increased by using an average of 1/2 as many anchor sequences. To index only homopolymers, clear the "AT, GC, ATT ...Complements option. With only the Start

Ry

Index option selected, the condensation speed is increased by using an average of 1/4th as many anchor sequences.

• Use Only 5' Bases for Consensus—Uses only the 5' bases of reads to determine the consensus base at each position.

Elongation starts from the center of the anchor and works outward.

• Remove Low Quality Ends when Score <= [x]—Assigns a quality score to each base of each read relative to the number of variations within the group of reads being condensed. For the bases on both ends of a given condensed read (bases outside of the anchor and shoulder sequences), if the score is less than the defined score, the end is regarded as low quality and is trimmed from the read starting from the low quality base.

Quality scores for each base are calculated by comparing the number of reads that match to the consensus sequence to the number of reads that differ from the consensus at the given position. Reads that are aligned to the position on the 5' end from the shoulder sequence are given a higher weight than reads that align on the 3' end from the shoulder sequence. A score of seven is assigned to each read that aligns at the position on the 5' end. A score of two is assigned to each that aligns at the position on the 3' end. The value is considered positive for all reads that match to the consensus base and negative for all reads that differ from the consensus, the score is multiplied by a penalty value of 1.7, so the final calculation is one of the following:

- Number of reads with differing base calls x 7 x 1.7
- Number of reads with differing base calls x 2 x 1.7

For example, consider a position where nine total reads are aligned. Three reads are aligned at the 5' end with a base call of "C," four reads are aligned at the 3' end with a base call of "A," and two reads are aligned at the 3' end with a matching base call of "C." The score is calculated as: $(3 \times 7) + (2 \times 2) - (4 \times 2 \times 1.7) = 12.8$, where:

- (3 x 7) represents the number of matching 5' reads times the score of 7.
- (2 x 2) represents the # of matching 3' reads times the score of 2.
- (4 x 2 x 1.7) represents the number of differing 3' reads times the score of 2 times the penalty of 1.7.

This setting can be very useful when using condensation to prepare reads for assembly by removing low quality calls at the ends of reads. It also useful for low coverage regions. When the minimum coverage of the data is around three or four reads, specify a value of two or three. For a value of three, at least two reads are required to have the same base call at the 3' end. For higher coverage data, specify a larger value. For example, if the minimum coverage is about 10 reads, and the average coverage is approximately 50 reads, specify a value of 10.

- **Require Bridge Read Covering Middle [x%]**—Requires for at least one read in the subgroup that the total length of the "bridge" region —the extension beyond the left shoulder sequence, the left shoulder sequence, the anchor sequence, the right shoulder sequence, and the extension beyond the right shoulder sequence—must be at least x% of the total read length. This setting is useful when multiple condensation cycles are used.
- Index Error Correction if Frequency <= [x%] of Majority Index—This setting is useful for transcriptome analysis or other types of analyses in which expression levels vary drastically. For very highly expressed sequences, errors are found at a high frequency and without using this setting, these errors would not be corrected and instead, could be used as separate anchor sequences. This setting allows for reads with two different index (anchor) sequences to be combined into one group. If two anchor sequences differ by only one base and have identical shoulder sequences, they are clustered into one group if the count for either of these anchor sequences is less than or equal to x% of the total reads in the resulting group The *majority index* is the index that has a greater number of reads. The *minority index* is the index that has the fewer number of reads. By "correcting" the minor index to match to the major index, the minor sequence is prevented from being used as in index.

Sequence Condensation Tool - Advanced Settings for Roche/454 Data

For the Roche/454 instrument type, the advanced settings are populated with values that SoftGenetics has determined, from experience, are appropriate for most datasets for the instrument. You can leave these settings as is, or you can modify the settings. At any time, you can click Default Settings to automatically reset all the values to SoftGenetics's default values.

Figure 4-11: Condensation Settings page, Advanced Settings for Roche/454 data

Condensation - Advanced Settings	×
Error Correction	
Options of Keyword Selection after Homopolymer Breaker	
KeyWord Length: 16 Bases	
Long Keyword >= 60 Bases (50-60 Bases, Breaks at AAT or ATT)	
$\label{eq:Frequency} \mbox{Frequency} <= \begin{tabular}{c c c c c c c c c c c c c c c c c c c $	
Combine Both Forward and Reverse	
Default Settings	
OK Cancel	

Setting	Description
Keyword Length [] Bases	The minimum length for keywords. The default value is 16 bases.
Long Keyword >= [x] Bases	When a keyword is long because of sequence region without a homopolymer (three or more identical nucleotides), then the keyword can be divided into a smaller size. If the keyword length exceeds the specified value (60 bases is the default value), then it is parsed into multiple keywords at locations with base sequences of AAT or ATT.
Frequency <= [x] Counts and <= [y%] or [z%]	Indicates the count and percentage at which a variation between reads within a single cluster is corrected. If there are less than "x" reads and less than y% of the reads show a variation, then the variation is corrected. If there are more than "x" reads that contain the variation, then the frequency of the variation must be below z% to be corrected.
Combine Both Forward and Reverse	Allows the Error Correction Tool to use reverse complement sequences to calculate variation frequencies. Selecting this option helps to distinguish true SNPs from instrument errors.

Sequence Condensation Tool Output Files

After the condensation data analysis step is complete, output files are created that provide detailed information about the analysis. The different methods each have different output files with different information that is relevant for the method. See:

- "Consolidation output files."
- "Elongation output files" on page 114.
- "Error Correction output files" on page 115.

Consolidation output files

File	Description
_Condensed_Raw.fasta	This file contains all the original reads that were used for the condensation.
_Cycle#.fasta	A _cycle#.fasta file is created for each cycle of the condensation that is carried out, where # is the cycle number. This file contains the consensus reads that were produced by the condensation cycle.
_OrgSampleID.txt	This file saves the original sample IDs so that NextGENe can reference them for further analysis, such as sequence alignment.
_Parameters.txt	This file contains information about the settings that were used for the project. If condensation was carried out as a preliminary step and then alignment or assembly was carried out as part of the same project, then a _Parameters.txt file is created that contains the settings for all the project steps.
_StatInfo.txt	 This file provides various statistics about the condensation process. The number of sequences that matched to indices The number of condensed reads that was produced The average condensed read length The average coverage within each condensed read The username for the user who ran the analysis if User Management is turned on
_Uncondensed_Raw.fasta	This file contains all the reads that were not used for condensation.
TempViewDir.giv	You can use this file to graphically view the Consolidation results in the NextGENe Condensation Results tool. See "The NextGENe Condensation Results Filter Tool" on page 381. Note: This file is created only if "View Condensation Results" is
	selected.

Chapter 4 Sequence Condensation Tool

When Consolidation is the selected condensation method, each consensus read is assigned a name that provides several key pieces of information about the read:

- Each name begins with the ">" character to indicate the beginning of the read name.
- A index number for the a 12 bp anchor sequence to which the sequence is matched.
- The 12 bp anchor sequence.



Reads that match to the reverse complement for the reference show do not show this 12 bp anchor sequence. Instead, the reverse complement sequence is shown.

- A number that indicates the anchor sequence's starting location in the consensus sequence.
- The left shoulder sequence.
- The right shoulder sequence.
- The number of forward reads that were used to generate the consensus sequence.
- The number of reverse reads that were used to generate the consensus sequence.

For example, consider a read named as shown below:

>67059_TCCTGACTCCAC_19_GACGGATG_CCACACCC_42_67<

This read was generated from the 67059th index which contains the anchor sequence "TCCTGACTCCAC." The anchor sequence begins at position 19 of the consensus read, with the sequence "GACGGATG" on its left and the sequence "CCACACCC" on its right. 42 forward and 67 reverse reads were used to generate the consensus sequence.

Elongation output files

File	Description
_Cycle#.fasta	A _cycle#.fasta file is created for each cycle of the condensation that is carried out, where # is the cycle number. This file contains the consensus reads that were produced by the condensation cycle.
_Parameters.txt	This file contains information about the settings that were used for the project. If condensation was carried out as a preliminary step and then alignment or assembly was carried out as part of the same project, then a _Parameters.txt file is created that contains the settings for all the project steps.
_StatInfo.txt	 This file provides various statistics about the condensation process. The number of sequences that matched to indices The number of condensed reads that was produced The average condensed read length The average coverage within each condensed read The username for the user who ran the analysis if User Management is turned on

Error Correction output files

File	Description
*_ErrorCorrected.fasta	This file contains all the error corrected reads. You can use this file as the sample file for all future projects and therefore, you do not have to use the Error Correction method again.
_Parameters.txt	This file contains information about the settings that were used for the project. If condensation was carried out as a preliminary step and then alignment or assembly was carried out as part of the same project, then a _Parameters.txt file is created that contains the settings for all the project steps.
_StatInfo.txt	 This file provides various statistics about the error correction process. The number of sequences that matched to indices The number of condensed reads that was produced The average condensed read length The average coverage within each condensed read The username for the user who ran the analysis if User Management is turned on

Chapter 4 Sequence Condensation Tool

Chapter 5 Sequence Assembly Tool

Many applications require short reads to be assembled into large contigs. You use NextGENe's Sequence Assembly tool to assemble the reads that are generated by the Roche/454, Illumina, SOLiD System, and Ion Torrent instruments into larger contigs. When available, you can use paired end information. You can add the base/color-called reads from any of these instruments directly into NextGENe for assembly, or you can use the Sequence Condensation tool to polish and correct these reads prior to assembly.

This chapter covers the following topics:

- "Sequence Assembly Tool Settings" on page 119.
- "Sequence Assembly Output Files" on page 127.

Chapter 5 Sequence Assembly Tool

Sequence Assembly Tool Settings

All assembly projects use the same General Assembly settings. The Final Assembly methods that are available on the Assembly Settings page are based on the selected instrument type and the selected Condensation method (Consolidation, Elongation, or Error Correction). When you select an assembly method, the corresponding settings are automatically populated with values that SoftGenetics has determined, from experience, are appropriate for the selected method. You can leave these settings as-is, or you can modify the settings. At any time, you can click Default Settings to automatically reset all the values to SoftGenetics's default values.

Instrument Type	Final Assembly Methods that are Available
Roche/454	• Greedy
	PE Assembly
	Skeleton Assembly
	Floton/Floton-PE
Illumina	
Condensation (Elongation)	 De Bruijn (paired end options available if two sample files loaded)
	Maximum Overlap
	PE Assembly
Condensation (Error Correction)	 De Bruijn (paired end options available if two sample files loaded)
	PE Assembly
Condensation (Consolidation)	De Bruijn (paired end options not available)Maximum Overlap
Condensation deselected	 De Bruijn (paired end options available if two sample files loaded) PE Assembly
SOLiD System	
Condensation (Elongation or Error Correction) or Condensation deselected	 De Bruijn (paired end options available if two sample files loaded)
Condensation (Consolidation)	De Bruijn (paired end options not available)
ION TORRENT	
Condensation (Elongation or Error Correction) or Condensation deselected	 De Bruijn (paired end options available if two sample files loaded)
	PE Assembly
	Floton/Floton-PE
Condensation (Consolidation)	De Bruijn (paired end options not available)

Chapter 5 Sequence Assembly Tool

See:

- "General Assembly settings" below.
- "De Bruijn assembly method for Illumina, SOLiD System, and Ion Torrent data" below.
- "Maximum Overlap assembly method for Illumina data" on page 121.
- "Greedy assembly method for Roche/454 data" on page 121.
- "Skeleton assembly method for Roche/454 data" on page 122.
- "PE assembly method for Roche/454, Illumina, and Ion Torrent data" on page 123.
- "Floton/Floton-PE assembly method for Roche/454 and Ion Torrent data" on page 124.

General Assembly settings

Setting	Description
View Assembly Results in NextGENe Viewer window	Creates a project (.pjt) file that shows how the reads aligned to the assembled results —where each read aligns and where the reads are mismatched. Select this option to view the assembly results immediately after your data analysis is complete in the NextGENe Viewer window.
	Note: The Ace file is the file that contains the displayed results. To ensure that this Ace file can be displayed for the project, if View Assembly Results in NextGENe Viewer window is selected, then the "Save Ace File" option is also selected, but is unavailable.
Save the Original Sequences with Assembled Ones	Select this option for applications that must have original coverage information retained. If this option is selected, then an AssembledContigsWithOrg.fasta output file is created that stores both the original sequence information and the assembled sequence information, including information about which reads were used in the assembly of which contigs. See "Sequence Assembly Output Files" on page 127.
	Note: This option is not available for the De Bruijn and PE Assembly methods. If this option is selected for other assembly methods, the processing time is increased.
Save Ace File	Creates an ACE (.ace) file that shows how the reads aligned to the assembled results—where each read aligns and where the reads are mismatched. NextGENe uses the information in this file to create the .pjt file. In addition, other programs can use this ACE file directly.

De Bruijn assembly method for Illumina, SOLiD System, and Ion Torrent data

The De Bruijn assembly method for Illumina, SOLiD System, and Ion Torrent data uses short words instead of entire reads as indices to develop the De Bruijn graph, which reduces redundancy. The software scans the reads for the first occurrence of each short word and records the location of the short word in the read. After the location of each short word in the reads is recorded, each read is represented by the short words that it contains and by its overlaps with other reads to create an index table. Reads are then mapped as a path along the graph with nodes representing overlaps and arcs between nodes representing links.

Setting	Description
Index Size	The length of the sequence (short word) that is used in the index table for assembly. The value must be an odd integer in the 17 - 99 range. Shorter reads require a smaller index size. For example, reads of 36 bp might work well with an index size = 21.
	Note: The smaller the index size, the more computer memory is required to process the index.
Paired Reads Data	- Available for datasets that were generated by paired reads.
Library Size	• The size of the fragment that was generated for sequencing from both ends.
Expected Coverage	 The average depth of coverage in reads at any single position within the reference.

Maximum Overlap assembly method for Illumina data

The Maximum Overlap assembly method is an alternative method of assembly for Illumina data that is less memory intensive than the De Bruijn assembly method. In this assembly method, which is suitable after multiple cycles of condensation, redundant/overlapping reads are merged to elongate condensed reads to form long contigs.

Setting	Description
Minimum Read Length = [] Bases	Sequence reads that contain less than this number of bases are not used to generate the final assembly.
Read Count Required for Indexing >= [x] and <= [y]	The number of reads that contain a given anchor sequence must fall within this range for the sequence to be used for indexing.
Minimum Length = 1/2 Avg Original Read Length	With this option selected, the shortest contig that is produced is one half the length of the average original read length. For example, if the average length of the original reads is 36 bases, then the shortest contig that is produced is 18 bases.
Minimum Contig Length = [] bases	After assembly, contigs that contain less than this number of bases are excluded from the Assembled Sequences output file.

Greedy assembly method for Roche/454 data

The Greedy assembly method looks for the maximum overlap between reads and extends the overlaps to form large contigs. The Greedy assembly method is recommended for Roche/454 reads or any other long reads datasets with an average read length that is greater than or equal to 70 bp.

Skeleton assembly method for Roche/454 data

The Skeleton assembly method uses *seed keys*, which are sequences between homopolymers (three or more identical nucleotides), to look for overlap between reads. Although the average distance between homopolymers is 16 bp, much longer stretches without homopolymers can occur. (A read with a length of 256bp contains an average of 16 keywords.) When this is the case, seed keys are created between "AAT" or "TAA" sequences. By comparing reads with homopolymer sequences or AAT or TAA sequences instead of comparing at every base position, processing time is significantly decreased. The Skeleton assembly method is recommended for Roche/454 reads or any other long reads datasets with an average read length that is greater than or equal to 70 bp.

Setting	Description
Seed Key Length >= [x] Bases, <= [y] Bases	Specifies the length range for seed key sequences. If the number of bases between homopolymers is greater than "y," then seed keys are created between "AAT" or "TAA" sequences.
Seed Key Coverage >= [x], <= [y]	The number of reads that match a seed key must fall within this range to be used in the assembly.
Auto Estimate	Select this option to have the software estimate the seed key coverage values.
	Note: If this option is selected, then the two options above are unavailable. Instead, NextGENe automatically calculates these values.
Assembled Contig Length to Output >= [x] Bases	Specifies the minimum contig length that is to be included in the Assembled Sequences output file. Any contigs that contain fewer than this number of bases are saved in a shortContigs.fasta file.

PE assembly method for Roche/454, Illumina, and Ion Torrent data

The PE Assembly method is a novel paired end assembly algorithm developed by SoftGenetics. This assembly method is designed to tolerate repeat regions smaller than the paired end library size to produce accurate assembly results. The PE assembly method uses a traditional scaffolding assembly algorithm. Short "words" within reads are used to find overlaps to form the scaffold. This generates initial assemblies that stop at repetitive regions. These initial assemblies are referred to as *scaffold contigs*. (NextGENe places these contigs in the ScaffoldContigs.fasta file. You can use this file to manually select which scaffold contigs are to be linked together. (See "The NextGENe Long PE Assembly Mapping Tool" on page 389.) When paired reads are used, the paired information is used to continue the assemblies past the repetitive regions to make larger contigs that otherwise could not be assembled simply by scaffolding. Although you can use the PE assembly method for the assembly of single sequence read data, it is most effective for paired reads with relatively small library sizes, such as 200 bp library paired end Illumina reads.

Setting	Description
Paired End Data	Select this option if you are assembling paired end data.
Library Size	 The size of the fragment that is being sequenced.
 Long Library Size (> 1000 Bases) 	 If the library is greater than 1000 bases, then in addition to specifying the library size, you must also select this option.
Section Size	Available only if Long Library is selected. Scaffold contigs are broken into sections when they are being assembled so that the distance between the contigs can be estimated. For the majority of datasets, the default value of 400 is the recommended value.
Minimum Scaffold Length	Available only if Long Library is selected. Any scaffold contigs that are shorter than the specified Minimum Scaffold Length are discarded and are not are used in the generation of the final contigs.
Word Length	The word length that is used for scaffolding. This value is determined by the average depth of coverage for the data. The lower the average depth of coverage for the data, the shorter this value should be. Conversely, the higher the average depth of coverage for the data, the longer this value should be. (Longer word lengths result in greater noise reduction.) If coverage falls within the range of 20-30x, the recommended word length is 23. If coverage is approximately 50x, the recommended word length is 29. The maximum recommended value for word length is 31.
High Coverage Limited: Max Coverage = [x]	The maximum coverage that is to be used for assembly. For sequences with higher coverage, reads up to the maximum coverage are used. Additional reads with the sequence are ignored, which increases processing speed.
Final Contig Merging	Merges any overlapping contigs that were found after scaffolding and linking with the paired reads are complete.

Chapter 5 Sequence Assembly Tool

Setting	Description
Reduce Memory Usage	When this option is selected, only the 5' end of the read is used to create "words" for indexing (to determine overlaps). The number of bases used to index is determined according to the following:
	(0.5+ (20/L))(L), where L = the average read length.
	Note: The memory that is conserved by this method is more significant for longer reads. For 36 bp reads, there is no difference in the memory that is used.


Floton/Floton-PE assembly method for Roche/454 and Ion Torrent data

The Floton assembly method developed by SoftGenetics reduces the number of homopolymer errors, which is a common problem in flow-based sequencing technology. The Floton assembly method converts the sequence into its original flows, which consist of the nucleotide and the number of consecutive calls for the nucleotide.



The Floton-PE method is identical to the Floton assembly method, but it is used solely for paired end data.

Figure 5-1: Conversion of base calls into flow calls



By converting the sequence data into this format, the homopolymer indels that were difficult to assemble become basically SNPs (in the base count), which allows for the correction of most homopolymer errors.

In the Floton assembly method, reads are indexed with several flowmers. This information is used during the first two steps of the three step assembly process:

- 1. Condensation—Reads that share flowmer indexes are compared and used to generate high-quality consensus contigs. The same read can be used in multiple condensation contigs.
- 2. Combination—An iterative process checks for condensation contigs that contain the same reads for the purpose of discovering and merging overlaps.
- 3. Overlap Merging—The combination contigs are combined into the final assembly contigs.

Setting	Description
Settings	
	 Select the assembly type that applies to your data: Small Genome (< 10MB) Large Genome Sequence Repeats PCR/Haplo/HLA Typing Metagenomics Others
Coverage Normalized to [30] X	Normalizes coverage for the assembly. This decreases processing time by ignoring reads where coverage is above the set threshold. The default value is 30.
Pair Normalized to [20]X	Available only for the Floton-PE assembly method. Automatically implemented if Coverage Normalized is selected. The coverage of paired reads is normalized to the value that you specify.
	ge Normalized, then you must select one of the following methods, which ads are kept and which reads are discarded.
 Method 1 (Selected) Method 2 	 This method checks keywords (sequences between homopolymers) in the reads and preferentially keeps reads where one or more of the keywords has low coverage.
(Random)	Note: Method 1 increases processing time.
	 This method randomly selects which reads are kept and which reads are discarded.
	output files are specific to the Floton/Floton-PE assembly method. To view a list that are produced for any assembly method, see "Sequence Assembly Output e 127.
Output Condensation	Creates the *_CondensedSequences.fasta file, which is the output from the Condensation step. This file lists the extended sequence for each original read with the original data title and in the original data order.
Output Combination	Creates the *CombinedSequencesfasta file, which contains the results for the Combination step.
Length Cut off <= [] x Avg Read Len or [300] bp	Rejects a contig that has length (number of base pairs) that is less than or equal to the indicated threshold. You can specify the threshold in one of two ways:A multiple of the average read length.
	A specific number of base pairs. The default value is 300 bps.

Chapter 5 Sequence Assembly Tool

Setting	Description
Advanced	
Automatic	Select this option to have NextGENe automatically determine the appropriate values for the Index Length, Index Count, and Remove Low Frequency options based on the loaded data. If you do not select Automatic, then you can manually select the values for these options.
 Index: Length [16] Flows 	 Select a value to create an index of the indicated length that ends in a homopolymer sequence. The default value is 16 bp.
 Index Count [4] Per Read 	 Select a value to create the indicated number of primary indices per read. The default value is four primary indices per read.
	The index number can be either one, or an even value (2, 4, and so on.) NextGENe prioritizes the indices based on such factors as the homopolymer length. For example, if the index number is set to four, then the two indices that have the highest priority in the first half of the read and the two indices that have the highest priority in the second half of the read are selected as the indices. If the index number is set to one, then the index with the highest priority is selected as the index, regardless of which half of the read that it falls in.
	n a higher average coverage per read, a smaller number of indices is d. Conversely, for reads with a longer average read length, a larger number of commended.
Remove Low Frequency [] or []%	Rejects the entire contig if the coverage is less than or equal to the indicated threshold or trims the end of the contig if the coverage of the ending bases is less than or equal to the set percentage of the maximum coverage for the contig.
Error Tolerate []% and Ignore [] bp	Combine two contigs only if the percent difference between the two contigs is less than or equal to the indicated threshold, and when combining, ignore the differences in the indicated number of base pairs at the end of each contig.

Sequence Assembly Output Files

After the assembly data analysis step is complete for any type of assembly method, the following output files are created that provide detailed information about the analysis.

File	Description
_assembledsequences.fasta	This file contains all the assembled reads in .fasta format. This file can be used as sample input for alignment projects or as a reference.
_assembledsequences.cfasta	In addition to the _assembledsequences.fasta file, this file is produced for SOLiD System data. This file contains the assembled reads in color space format. This file can also be used as sample input for alignment projects.
AssembledContigsWithOrg.fasta	Created only if Save the Original Sequences with Assembled Ones is selected for the General Assembly options. See "General Assembly settings" on page 120.
shortcontigs.fasta	If you use the Skeleton Assembly method or Maximum Overlap method, then you must specify the minimum contig length that is to be included in the Assembled Sequences output file. Any contigs that contain fewer than this number of bases are saved in this .fasta file.
_Parameters.txt	This file contains information about the settings that were used for the project. If condensation was carried out as a preliminary step and then assembly was carried out as part of the same project, then a _Parameters.txt file is created that contains the settings for all the project steps.
_StatInfo.txt	 This file provides basic information and various statistics about the assembly process. Basic information: The general steps that were used Process times Sample file names and output file names Statistical information: The assembled sequence count The average length of the assembled sequences The username for the user who ran the analysis if User Management is turned on.
_Uncondensed_Raw.fasta	This file contains all the reads that were not used for assembly.

Chapter 5 Sequence Assembly Tool

Chapter 6 Sequence Alignment Tool

The NextGENe Sequence Alignment tool matches short sequence reads to a reference sequence. The reference sequence can be a small genome or genomic region (250 Mbp or less) or it can be a whole large genome reference such as the human, mouse, or rat genome. The NextGENe application also has the NextGENe Viewer, which is a viewing and editing tool that you can use to view the results of the Sequence Alignment tool and produce a variety of interactive reports that summarize the sequence alignment information.

This chapter covers the following topics:

- "NextGENe Sequence Alignment Algorithms" on page 131.
- "Sequence Alignment Tool Settings" on page 133.
- "NextGENe Viewer" on page 140.
- "Paired Reads Alignment" on page 156.
- "Transcriptome Alignment Project with Alternative Splicing" on page 168.
- "STR (Short Tandem Repeats) Analysis Project" on page 180.
- "Mitochondrial Amplicon Analysis Project" on page 189.
- "HLA Project" on page 195.
- "Sequence Alignment Project Output Files" on page 208.
- "Sequence Alignment Project Mutation Report" on page 210.
- "Sequence Alignment Project Reports" on page 246.
- "NextGENe Viewer Tools" on page 278.
- "NextGENe Viewer Comparison Reports and Tools" on page 291.

Chapter 6 Sequence Alignment Tool

NextGENe Sequence Alignment Algorithms

The NextGENe Sequence Alignment tool matches short sequence reads to a reference sequence. For all application types other than *de novo* Assembly, a reference is required for aligning the reads of the data file that is being analyzed against a known genome. If you are aligning the data against a small genome (one that is less than or equal to 250 Mbp), then you must align data against a reference that is either in .fasta format or GenBank (gbk or gb) format. If you are aligning the data against a large genome (one that is greater than 250 Mbp, such as the whole human genome), then you must align the data against a preloaded reference that SoftGenetics supplies or a custom preloaded reference that was built using the NextGENe Build Preloaded Reference tool.



For SOLiD data, the alignment is done in color-space.



For detailed information about the Build Preloaded Reference tool, see the Reference & Track Manager Tool User's Manual or Online Help.

Genomic regions or genomes smaller than 250 Mbp

For genomic regions or genomes smaller than 250 Mbp, NextGENe uses an alignment method that is similar to BLAT methodology to align sequence reads to the reference. The reference file is first divided into an index table. Every 12 bases of each sequence read is aligned to this table. The positions of alignment between the reads and the reference are determined and the alignment is evaluated linearly. If they are in a line, the sample sequence can be aligned to the reference target positions. (Jumps might exist in the line because of true or false positive indels.) Reads can be matched to a single position, or they can be matched to multiple positions. If a read matches exactly at more than one position, it can be aligned at each exact match position when "Allow Ambiguous" is selected. (See "Allow Ambiguous Mapping" on page 134.) If this option is set equal to one, the read is aligned to the first exact match position from the beginning of the reference. If this option is set equal to zero, all reads that match perfectly at more than one location are discarded

The Allow Ambiguous setting is not applicable for reads that include mismatches. Instead, when reads match to more than one position with the same number of mismatches, the *Uniqueness score* is used to determine the best position to which to align the read. The uniqueness score is calculated according to the following, where "n" is the number of hits on the reference:

$$1 \div (\sqrt{n})$$

The region with the greatest Uniqueness score is selected to align the read.

Preloaded Reference Alignment

For aligning reads to a preloaded reference such as the human, mouse, or rat genome, NextGENe uses a Preloaded Index Alignment algorithm. This algorithm employs a suffix array that is represented by the Burrows-Wheeler Transform (BWT). A rank algorithm allows the software to traverse the suffix array to find the best matching location for each read. In addition to the BWT, the software maintains genome positions at every four base pairs within the genome, which allows the software to monitor these locations while traversing the reference genome.

Dollar sign indicate	es end of sequence	
Rotate sequences:	Sort Rotations	Last Column of Sorted
gattaca\$	\$gattaca	а
\$gattaca	a\$gattac	с
a\$gattac	aca\$gatt	t
ca\$gatta	attaca\$g	g
aca\$gatt	ca\$gatta	а
taca\$gat	gattaca\$	\$
ttaca\$ga	taca\$gat	t
attaca\$g	ttaca\$ga	а

Figure 6-1: Example of the Burrows-Wheeler Transform algorithm

NextGENe first attempts to match the entire read exactly to the reference. Reads can be matched to a single position, or they can be matched to multiple positions. To align reads that match exactly at more than one position, set the Allowable Ambiguous Alignments setting to a value that is greater than one, with 50 being the recommended value. (See "Allowable Ambiguous Alignments" on page 135.) If this option is set to a value of one, the read is aligned to the first exact match position from the beginning of the reference. If this option is set to a value of zero, then all reads that match perfectly at more than one location are discarded.

For reads that cannot be matched exactly, NextGENe tries to match the entire read with an increasing number of mismatches, starting at one mismatch and continuing up to the maximum number of allowable mismatches, as set by you. (See "Allowable Mismatched Bases []" on page 135.) For reads that can still not be matched, seeds that are smaller than the read lengths are used to identify the best matching position within the genome. After finding the best match, a dedicated NextGENe algorithm expands the alignment to align the entire read which, in turn, allows the individual reads to be aligned with indels and mismatches.

Sequence Alignment Tool Settings

The Alignment Settings page is available by doing one of the following:

- Clicking Alignment in the Project Wizard.
- Clicking Process on the NextGENe viewer main menu. (See "NextGENe Viewer main menu" on page 142.)
- Clicking the Alignment Settings icon number of the NextGENe viewer toolbar. (See "NextGENe Viewer toolbar" on page 147.)

The alignment settings that are available on the Alignment Settings page for any application type *other than* Transcriptome with alternative splicing, STR analysis, or HLA depend on the type of reference file (.fasta, GenBank, or preloaded) that was loaded for the project. See:

- "Alignment settings-fasta or GenBank reference file" on page 134.
- "Alignment settings—Preloaded reference" on page 135.
- "BAM Sample Files settings" on page 136.
- "Sample Trim settings" on page 136.
- "Mutation Filter settings" on page 137.
- "File Type settings" on page 138.
- "Other settings" on page 138.



For a detailed discussion of the settings for a transcriptome alignment project with alternative splicing, see "Transcriptome Alignment Project with Alternative Splicing" on page 168. For a detailed discussion of the settings for an STR analysis project, see "STR (Short Tandem Repeats) Analysis Project" on page 180. For a detailed discussion of the settings for an HLA project, see "HLA Project" on page 195.

Alignment settings—.fasta or GenBank reference file

The following settings are available for .fasta sample files and BAM files with the Realignment option selected. If you have loaded aligned BAM sample files without the Realignment option selected, then see "BAM Sample Files settings" on page 136.

Setting	Description
Matching Requirement: Base Number >= [x] and Base percentage >= [y]	 "x" indicates the minimum number of bases in each read that must match the reference sequence for the read to align with a specific position in the reference sequence. "y" indicates the minimum percentage of each sequence read that must match the reference sequence for the read to align with a specific position in the reference sequence. Note: Both conditions must be met for the read to be aligned to the position.
Allow Ambiguous Mapping	Aligns the read to each exact match position if a read matches exactly at more than one position in the reference. If this option is not selected, the read is aligned to the first exact match position from the start of the reference.
Remove Ambiguously Mapped Reads	Removes reads that match exactly to more than one position in the reference from the analysis.
Detect Large Indels	After an initial alignment is carried out, a consensus sequence is created and if an indel is found that occurs in at least 5% of the reads, this indel in reflected in the consensus sequence. The reads are then aligned again to this consensus sequence.
	Note: This option helps to align reads that include indels towards the end of the read, which in turn, allows allow for correctly calling the variant in the Mutation report. Processing time increases if this option is selected.
Rigorous Alignment	When this option is selected, after the matching region is determined for a read based on the matched bases and the uniqueness score, the alignment of individual bases is then checked to determine the alignment with the least mismatches. Consider the following simple example:
	AAAAAAAAAGCTCGT
	AAAAAAAAACGT - without rigorous alignment
	AAAAAAAAAA CGT - with rigorous alignment
	Note: This option also helps to align reads that include indels.
Read length over reference length <u>></u> [80%]	Displayed only for STR analysis and selected by default for STR analysis. The read must cover at least the indicate percentage of the segment to which it is aligned, or it is not assigned to an allele. See "STR (Short Tandem Repeats) Analysis Project" on page 180.
	Note: This setting ensures that the read covers an entire repeat region.

Alignment settings—Preloaded reference



The following settings are available for .fasta sample files and BAM files with the Realignment option selected. If you have loaded aligned BAM sample files without the Realignment option selected, then see "BAM Sample Files settings" on page 136.

Setting	Description
Reads:	
Allowable Mismatched Bases []	 If a read does not align exactly to the reference, then the entire read can still be aligned to the reference if the number of mismatched bases does not exceed the indicated threshold. If the read cannot be aligned with this number of mismatches, it might still be possible to align the read using seed sequences.
Allowable Ambiguous Alignments	 Applies to reads that match perfectly to the reference sequence or to reads that have a number of mismatches less than the threshold for Allowable Mismatched Bases. For perfectly matched read, or a read that has a number of mismatches, if multiple matching locations are found, the read is aligned to the reference sequence up to the specified number of ambiguous alignments that are allowed. If this option is set to "1," the read is aligned to the first matching position from the start of the reference. If this option is set to "0," then a read that matches at multiple locations is not aligned to the reference.
Seed [x] Bases, Move Step [y] Bases	"x" is the length of the seed that is used to determine the matching positions in the reference genome. "y" is the number bases between seed start positions.
Inspect Input Files	Click this option to have NextGENe automatically set the values for Allowable Mismatched Bases, Seed Bases/Move Step Bases, and Allowable Alignments.
	Note: If multiple data files are being analyzed, each value is the total for all files.
Allowable Alignments []	If a seed matches more than this number of positions in the reference genome, then the seed is ignored.
Overall Matching Base Percentage >= [85]	The percentage of the read that must match to the reference genome for the read to be aligned to the reference. Default value is 85.
Detect Large Indels	After an initial alignment is carried out, a consensus sequence is created and if an indel is found that occurs in at least 5% of the reads, this indel in reflected in the consensus sequence. The reads are then aligned again to this consensus sequence.
	Note: This option helps to align reads that include indels towards the end of the read, which in turn, allows allow for correctly calling the variant in the Mutation report. Processing time increases if this option is selected.

BAM Sample Files settings



The following settings are for aligned BAM sample files when the Realignment option is <u>not</u> selected.

Setting	Description
Mapping Quality >=	The Map Quality for a read must exceed this threshold for the read to map to a given location. The read can map to as many locations as where the Map Quality is met.
Remove Ambiguous Alignments	Removes all reads that match exactly to more than one position in the reference from the analysis unless one or both of the following two options are selected:
 If Mapping Quality is <= [] 	 Removes reads that match exactly to more than position only if the mapping quality is less than or equal to the indicated threshold.
Except for the Highest Map Quality Alignment	 Removes reads that match exactly to more than one position except for the alignment that has the highest map quality.
Remove Paired Reads that are not Properly Paired	Removes reads that are flagged as not properly paired. The definition of "properly paired" varies among the alignment program that you used, but typically means that the both reads aligned in the correct orientation and within the expected library size.
Match Reference	Click this option to match the reference that was used to create the BAM file with the reference that was loaded during the Load Data step for the project. See "To load the reference files" on page 56.

Sample Trim settings

Setting	Description
Select Sequence Range From [x] Bases to [y] Bases	Certain base pair ranges in the sequence reads can be masked. Select this option to ensure that only this specified range of base pairs is loaded for alignment and compared to the reference.
Hide Unmatched Ends	Hides the ends of reads that do not match to the reference, which can reduce the false positive detection rate. NextGENe hides the unmatched ends by checking for two mismatches in the last eight base pairs, and then trimming to the mismatched base. It repeats this process until eight base pairs are found without two mismatched ends.

Mutation Filter settings



Homopolymers are defined as the reference is > 2 bases and the reads are > 1 base. This means that CC>C is a homopolymer deletion and C>CC is not a homopolymer insertion.

Setting	Description
Use original	Applicable only when aligning condensed reads. If this option is selected, then the mutation percentage refers to the original read numbers and not the condensed read numbers. A variation that is detected must exceed the specified percentage of original reads for it to be reported as a variant. Reads that align to the position that is at the end of the read (outside of the anchor and shoulder sequences) are not included in the count of aligned reads.
	Note: This option is useful for eliminating false positives.
Except for homozygous	Selected by default. The coverage requirement is ignored for variants that are homozygous.
Mutation percentage <	For the indicated variation type (SNP, Indel, or Homopolymer Indel), a variation between the aligned reads and the reference sequence at a given position of the reference must occur at a frequency that exceeds this value, or a variant is not called at the position.
SNP allele count \leq	For the indicated variation type (SNP, Indel, or Homopolymer Indel), the total number of reads with the variant allele must exceed this value, or a variant is not called at the position.
Total coverage count ≤	For the indicated variation type (SNP, Indel, or Homopolymer Indel), the total number of reads at a given position must exceed this value, or a variant is not called at the position.
must be met for a	e mutation percentage, the SNP allele count, <i>and</i> the total coverage count n indicated variation type at a given position to be reported as a variant. If t met, then the variation is filtered from the analysis and it is highlighted in nent viewer.
Perform in-read phasing	Selected by default. Strings of variants that are within a user-defined proximity (0 -3 bp) and are on the same reads are merged into a single indel call.
Max Gap between two variants	The maximum number of bp allowed between variants on the same strand to be merged into a single indel call (phased). If the number of bp exceeds this threshold, then the variants are not phased.
Phaseable reads percentage	The minimum percentage of reads in the phased region that must have at least one of the phaseable variants for the phasing to include the variant position.

File Type settings

Setting	Description
Load Assembled Results File	The Assembly tool creates the assembledsequences.fasta file, which is a file that contains information about each read that was used to create a given assembled contig. You can load this file into the Sequence Alignment tool for a more accurate representation of coverage.
	Note: For SOLiD System data, you can load the assembledsequences.csfasta file.
Load SAGE Expression Data	If a SAGE library is loaded as a reference file and the expression levels of each tag are needed, then select this option and set the values for Extract Bases From and New Sequence Coverage accordingly.
	Note: The alignment to the tag library is carried out only in the forward direction. No reverse complementation is implemented.
Extract Bases From: [x] Bases to: [y] Bases	 The sample reads might contain more bases per read than the expression library. Specify the first base position and the last base position of the tag in the sample reads.
New Sequence Coverage Minimum []	• Novel sequences that are found in the data and that are not contained in the library can be added to the end of the reference file to provide coverage for the sequences. Novel tags must be found in the data at a rate that is above this minimum threshold or they are not added as a new gene.
Load Paired Reads	Select this option to align paired end/mate pair data sets.
Library Size	The length of the DNA fragment that is used for sequencing pairs.
454 Sequences	• Enter the known sequence separating pairs for Roche/454 paired end analyses in this field.

Other settings

Setting	Description
Save Matched Reads	Select this option to create the <sample file="" name="">_matchedfasta file, which contains all the reads that aligned to the reference.</sample>
Highlight Anchor Sequence	Applicable only when aligning condensed reads. All the anchor sequences that were used for condensation are displayed in Bold type in the Sequence Alignment window.
Ambiguous Gain/Loss	If this option is selected, NextGENe calculates the Ambiguous Gain penalty and the Ambiguous Loss penalty for each variant call. (See "Ambiguous Gain penalty/Ambiguous Loss penalty" on page 227.) Note: If this option is selected, processing time is increased.

Chapter 6 Sequence Alignment Tool

Setting	Description	
Detect Structural Variations Mismatch: [x] Length or [y] Bases	If this option is selected, NextGENe detects locations of possible structural rearrangements and automatically generates pseudo paired reads for each sample read by using the 3' end of the read "as is" and reversing the 5' end of the read. For a region to reported as a structural variation, there must be at least one read aligned to the region with ([x] \times read length) number of mismatched bases or [y] number of mismatched bases	
	Note: For reads with a length less than 76 bp, condensation is recommended to lengthen the reads prior to generating the pseudo paired reads.	

NextGENe Viewer

You use the NextGENe Viewer to view and edit the results of alignment projects. When you align a single project in NextGENe, the project is *automatically* opened in the default alignment view in the NextGENe Viewer. You can also save and load projects for viewing and editing at a later date.

To load a sequence alignment project in the NextGENe Viewer

When you view a project in the NextGENe Viewer that uses a preloaded reference, you can use something other than the gene name to identify the genes. To do so, you must create a a Alternate Gene Information text file. This file is a tab-delimited text file, with the first column containing the gene name that is used in NextGENe and the second column containing the alternate gene identifier.



For assistance with setting up this Alternate Gene Information file, contact SoftGenetics at tech_support@softgenetics.com.

- 1. Do one of the following to open the NextGENe Viewer:
 - On the NextGENe main menu, click File > Open NextGENe viewer.
 - On the NextGENe toolbar, click the NextGENe Viewer icon 帐.
- 2. On the NextGENe Viewer main menu, click File > Load Project.

The Load Project dialog box opens.

Figure 6-2: Load Project dialog box

Load Project	×
Project Name	
Load Alternate Gene Information (optional)	<u>A</u>
	<u>C</u> ancel

- 3. Next to the Project Name field, click the Load File icon 😰 to browse to and select the alignment project file (Aligned Sequence Project (*.Pjt)) that you want to load.
- 4. Optionally, if you are using a preloaded reference, and you want to use something other than the gene name to identify the genes, select Load Alternate Gene Information, and

then click the Load File icon \swarrow to browse to and select the text file that contains this alternate gene information.

5. Click OK.



If the project that you are loading does not contain reference information (for example, the copy was copied from another computer and the reference information for the project was simply linked to it), then a message opens prompting you to select the appropriate reference. Click OK to close the message, and then follow the prompts to select the reference.

The Load Project dialog box closes. The loaded project opens in the default alignment view in the NextGENe Viewer. See "NextGENe Viewer layout and navigation" below.



Be patient. Depending on the size of the project, this step can take several minutes to complete.

NextGENe Viewer layout and navigation

Figure 6-3: NextGENe Viewer with opened project



The NextGENe Viewer has seven major components:

- The title bar.
- The main menu.
- The toolbar.
- The Tracks Display.
- The Whole Genome viewer.
- The Alignment viewer.
- The Status bar.

NextGENe Viewer title bar

The NextGENe Viewer title bar displays the name and full directory path for the alignment project file that is being analyzed.

Figure 6-4: NextGENe Viewer Window title bar

NextGENe Viewer [Administrator] - C:\Users\Spectrum Writing\Spectrum Writing Info\Active Client Work\SoftGenetics\Downloads\E_R1_converted_Output\E_R1_converted_Output.pjt

NextGENe Viewer main menu

The NextGENe Viewer main menu is set up in a standard Windows menu format with menu commands grouped into menus (File, Process, Paired View, Report, Search, Tool, Mutation Report, and Help) across the menu bar. Some of these menu commands are available in other areas of the application.

Figure 6-5: Main menu

File Process Paired View Reports Search Tools Comparisons Help

Menu Option	Description
File	 Load Project - For loading an alignment project for analysis.
	 Save Project - Saving the currently loaded alignment project.
	• Save Optional Reference Info—If your Process Options are set to link the reference annotation information to a project instead of exporting it to the project output folder (see "Specifying NextGENe Process Options" on page 81), you can use this option to save the information (Annotation.gbk and dbsnp.txt) to the output folder. See "Save Optional Reference Info" on page 144.
	Note : This option is useful in the event that a project needs to be copied to another computer, and you must ensure that all the project output information is copied.
	• Export
	 Bed file—Creates a BED file for a specified input sequence range. See "Exported BED file" on page 144.
	 Gap.fasta—Available only for very small projects (reference < 10Mbp). See "Exported Gap.fasta file" on page 144.
	 SAM/BAM Output—To export the NextGENe project file to a format (SAM or BAM) that other alignment viewers can use. See "SAM/BAM Output" on page 144.
	 Export Project—Saves the entire project folder to a location of your choice, for example, a network folder. See "Export Project" on page 146.
	 Show Open Reports—Brings any minimized alignment report to the front of the application display again.

Menu Option	Description
Process	 Alignment Settings—Opens the Alignment Settings dialog box on which you can view the settings for the currently loaded alignment project.
	 Database Settings—Opens the Database Setting dialog box which you can use to view and if necessary, modify the current settings for your mySQL database.
	 Query Reference Tracks—Applicable only for Preloaded Reference projects and human GenBank files with NC-accession numbers. To use the Query Reference Tracks option, you must first use the Reference & Track Manager tool to download and import a database as a <i>track</i> into NextGENe. (You can then use the Query Reference Tracks option to load data from the track for the project that is currently opened in the viewer.
	Note: Any new Preloaded Reference projects that you create after you use the Reference & Track Manager tool automatically load the track information, <i>if the Default Query option for the track is set to</i> Yes. You do not need to use the Query Reference Tracks option. For detailed information about loading track data for previously run projects, see the <i>Reference & Track Manager Tool User's Manual</i> or Online Help.
	Note:
	Pathway Studio Settings—Elsevier R & D Solutions Pathway Studio® uses a knowledge base of biological relationships culled from millions of articles and abstracts as well as clinical trials to enable the analysis and visualization of disease mechanisms, gene expression and proteomics and metabolomics data by researchers. A separate subscription to Pathway Studio is required to access Pathway Studio from NextGENe. If you intend to use this integration function, then you must select the appropriate access option to Pathway Studio. Three options are available and your subscription determines your selection:
	Pathway Studio Mammalian, ChemEffect, DiseaseFX
	Pathway Studio Mammalian
	Pathway Studio Plant
Paired View	Available when analyzing paired read (paired end/mate paired) data. See "Paired Reads Alignment" on page 156.
Reports	Available reports for an alignment project. See "Sequence Alignment Project Reports" on page 246.
Search	• Search the Alignment viewer. See "Alignment viewer" on page 150.
	 Next Mutation - With the cursor placed in the Alignment Viewer pane, moves forward to the next variant call in the pane.
	 Previous Mutation - With the cursor placed in the Alignment Viewer pane, moves back to the previous variant call in the pane.
Tools	See "NextGENe Viewer Tools" on page 278.
Comparisons	Contains options for various comparison tools and reports. See
	"Expression Comparison report" on page 291.
	"Variant Comparison tool" on page 295.
	"Somatic Mutation Comparison tool" on page 310.
	"CNV (Copy Number Variation) tool (Dispersion and HMM)" on page 317.
	 "CNV (Copy Number Variation) tool (SNP-based Normalization with Smoothing)" on page 330.

Save Optional Reference Info

If your Process Options are set to link the reference annotation information to a project instead of exporting it to the project output folder (see "Specifying NextGENe Process Options" on page 81), you can use this option to save the information (Annotation.gbk and dbsnp.txt) to the output folder.

1. Click File > Save Optional Reference Info.

A message opens indicating the file size and asking you if you are sure that you want to save the files.

2. Click OK in the message.

The message closes. The Annotation.gbk and dbsnp.txt files are saved in the <Project Name>.files folder.

Exported BED file

In the NextGENe Viewer, to create a BED file for a specified input sequence range, click select File > Export > BED. A BED file contains a line for each aligned read with the format shown in Figure 6-6 below.

Figure 6-6: Format of exported BED file

Chromosome Chromosome Position Start Chromosome Position End Read Name Score Direction

where:

- Score—The percentage of the read that matched the reference sample (1000 = 100%, 750 = 75%, and so on.)
- Direction—(+) for forward reads and (-) for reverse reads.



You can upload this file into specific Genome viewers. Contact SoftGenetics for assistance.

Exported Gap.fasta file

In the NextGENe viewer, the File > Export > Gap.fasta file option is available only for very small projects (reference less than 10Mbp). A .fasta file is created which shows the region of the reference file to which each read is aligned. The file lists the following information:

- The entire reference sequence.
- Each aligned read, beginning with the first aligned read.
- The read name is shown in the header line. The sequence lines include "*", "-", "_" or ".") to indicate empty base positions of the reference, followed by the sequence of the read. For example, a read that aligns to the 2nd base of the reference is shown as "*ACTG. "

SAM/BAM Output

When you export NextGENe sequence alignment project files to a SAM or BAM format, the standard index file, index.bai, that other alignment viewers require is also exported.

1. Click File > Export > SAM/BAM Output.

The SAM/BAM Output dialog box opens.

Figure 6-7: SAM/BAM Output dialog box

r sam	I BAM	Select Chr	omosomes
Filter by ROI Instance	-	NC IBave	
Add Bemave	Add	Eemove	
:\Users\Spectrum Writing\Spectrum Writing	ng Info\Active Client Work	\SoftGenetics\WIP\	Ni Se

- 2. Select the appropriate export format and specify the location for the exported file.
- 3. Optionally, to indicate which regions to include/exclude for the BAM or SAM file, select Filter by ROI, and then to:
 - Indicate the regions that are to be included in the BAM or SAM file, click Add for the Inclusion pane, and then select the appropriate BED file.
 - Indicate the regions that are to be excluded from the BAM or SAM file, click Add for the Exclusion pane, and then select the appropriate BED file.
- 4. Optionally, click Select Chromosome.

The Select Chromosome dialog box opens.

Figure 6-8: Select Chromosome dialog box

*	Chromosome	Length		I▼ All
✔ 1	1	226212984		
2	2	464111204		₩ Unlocalize
₹ 3	3	659415287		
4	4	847354998		✓ Unplaced
✓ 5	5	1025201451		1. Oublacea
6	6	1194301005		
7	7	1349703088		
8	8	1493033824		
9	9	1614023510		
10	10	1745761522		
11	11	1877007669	10	
✓ 12	12	2007311203		
13	13	2103058041		
14	14	2191348626		
15	15	2273274887		
16	16	2352265126		
17	17	2431882959		
18	18	2506543376		
✓ 19	19	2562580885		
20	20	2622086138		
21	21	2657537829		
22	22	2692596479		
23	х	2845174401	+	

Chapter 6 Sequence Alignment Tool

- 5. Specify the chromosomes to include in/exclude from the export file (by default, all chromosomes are included), and then click OK. You can:
 - Select/deselect an individual chromosome.
 - Select/deselect All chromosomes in a single step.
 - Select/deselect all Unlocalized (sequences) in a single step, which are contigs that are known to be part of a particular chromosome, but the locations within the chromosome are not known.
 - Select/deselect all Unplaced (sequences) in a single step, which are contigs for which the specific locations, including the chromosome, are not known.
- 6. Click OK.

The Select Chromosomes dialog box closes. You return to the SAM/BAM Output dialog box.

7. Click OK.

The dialog box closes. The export is carried out.


Export Project

You use the Export Project option to export and save the entire project folder to a location of your choice, for example, a network folder.

1. Click File > Export > Project.

The Export Project dialog box opens. The project name is selected in the Filename field.

Figure 6-9: Export Project dialog box



- 2. Optionally, change the name of the project.
- 3. Select the location in which to save the project, and then click Save.

NextGENe Viewer toolbar

The NextGENe Viewer toolbar provides quick access to a variety of viewer functions.

Figure 6-10: NextGENe Viewer toolbar buttons

lcon	Function
2	Load Project icon - Opens the Load Project dialog box, in which you can select a project to load in to the NextGENe Viewer.
	Save Project icon - Saves the project that is currently opened in the NextGENe Viewer.
Mutation Call 🗨	Region Selection dropdown list—Used in conjunction with the Previous icon and the Next icon. Available values are: Mutation Call, Covered Region, ROI, CDS, mRNA, Gene, and Chromosome.
(=	Previous icon - With the cursor placed in the Alignment Viewer pane, moves back to the previous region/location as defined in the Region Selection dropdown list.
⇒	Next icon - With the cursor placed in the Alignment Viewer pane, moves forward to the next region/location as defined in the Region Selection dropdown list.
E	 Switch Report Layout icon - A dropdown list that displays options for specifying the location for showing a selected report (to the right or at the bottom of the NextGENe Viewer), or showing only the selected report (the Alignment Viewer is hidden), or hiding a selected report. The icon display is dynamically updated based on the selected report display option. Note: If you elect to show only a selected report, then to show the Alignment Viewer again, you must directly click the Switch Report Layout icon. You can then select from an option on the dropdown
MUT 👻	list for the icon to indicate where the report is to be displayed. Report Selection icon - A dropdown list that toggles the report that is displayed in the viewer between available reports based on the selected application type. The Mutation report is always an option. The Summary report is available for any application type.
ß	Report Settings icon - Opens the Settings dialog box for the selected report.
	 Track Settings icon - Click to open a list from which you can select the appropriate tracks option: Variation Tracks Settings - Opens the Variation Tracks Settings dialog box. The Variation Tracks Settings dialog box displays the available tracks settings for the Mutation report based on the variation databases that were imported for the project. See "Variation Tracks Settings dialog box." on page 232. Gene Tracks Settings - Opens the Gene Tracks Settings dialog box. The Gene Tracks Settings dialog box displays the available gene tracks settings for the Mutation report based on the gene tracks for the project. See "Gene Tracks Settings dialog box" on page 240.

Chapter 6 Sequence Alignment Tool

lcon	Function
⊕ `	Zoom in icon - Reduces the viewing area of the Whole Genome viewer pane.
e,	Zoom out icon - Enlarges the viewing area of the Whole Genome viewer pane.
₽ ₩ 8 ÷	Font Size icon - You can manually enter a value, or you can use the Up/ Down arrows to change the font size for the entire NextGENe Viewer display (gene name, all labels, the base symbols in the Alignment view, numbering, and so on).
± ;;;	Zoom Bar - You can click the Zoom In (+) icon and/or the Zoom Out (-) icon, or use the slider function on the Zoom Bar to zoom in or zoom out the display of the Alignment viewer.
	Note: You can zoom out to a greater degree in the Alignment viewer using the Zoom Bar than if you use the manual zoom out function. See "Alignment viewer navigation" on page 151.

Tracks Display

If you have imported data from variant databases into NextGENe, then the NextGENe Viewer window has a Tracks Display section. This section displays a pane for each track that has been queried for the project. Tic marks indicate positions in each track for which there is information. If Set Amplicon BED File was selected in the Load Data step of the Project Wizard for the loaded project, then the amplicon ROIs are displayed as a solid pink link in the ROI pane for the section.

Figure 6-11: NextGENe Viewer window, Tracks Display



Tic marks indicate position with information in the track. Different positions in different tracks have different information, such as the rs# for a dbSNP variant.

Figure 6-12: NextGENe Viewer window, Tracks Display for project with an Amplicon BED file




Whole Genome viewer

The Whole Genome viewer, which is the upper pane of the NextGENe Viewer, shows the global view of the alignment project. The following information is displayed for the entire reference genome in this pane:

- Segment breakpoints (red vertical bars) and the biological information for each breakpoint.
- The coverage information (gray shading).
- Variant calls (purple and/or blue tick marks).
- Gene locations (blue arrows)
- CDS and mRNA locations (gold and green arrows, respectively).
- The current position of the reads in the Alignment viewer (blue cross).

Figure 6-13: Whole Genome viewer






For detailed information about segment breakpoints, see "Segment Breakpoints" on page 155.

Chapter 6 Sequence Alignment Tool

You can easily navigate the Whole Genome viewer using some of the toolbar icons (see "NextGENe Viewer toolbar" on page 147), or you can use your mouse and some keyboard hotkeys.

Navigation	Action
Zoom In	Hold down the left mouse button and draw a box from the upper left hand corner of the pane towards the lower right hand corner. A box is formed around the area that being reduced for viewing.
Zoom Out	Hold down the left mouse button and draw a box from the lower right hand corner of the pane towards the upper left hand corner.
	Note: The magnification for zooming out is always 100%.
Scroll	After zooming in on a region, click and drag the right mouse button in any area of the pane to move the reference view horizontally.
Display Information	Place the cursor in the pane and then click and hold the [Ctrl] key to display information for the segment/gene where the cursor is located. See Figure 6-14 below.
Copy sequence or image	Press and hold the [Shift] key and the [Ctrl] key and then click and hold the left mouse button and draw a box around the region of the display (sequence or image) that you want to copy. The selected region is filled with black. Right-click and select Copy Sequence or Copy As Picture to copy the sequence or image to your clipboard. Use standard keyboard commands or menu commands to paste the copied sequence or image into an application.

Figure 6-14: Whole Genome Viewer display information




208K 416K 624K 832K 1040K 1248K 1456K 1664K 1872K 2080K 2288K 2496K 2704K 2912K 3120K 3328K 3536K 3744K 3952K 4160K 4

Alignment viewer

The Alignment viewer, which is the lower pane in the NextGENe Viewer, displays a view of all the reads as they align to the reference sequence. See Figure 6-15 on page 151.



The NextGENe Viewer window can load a maximum of 100 million variant calls. If a project contains more than 100 million variant calls, a Mutation Score is calculated (MutationRatio*log(coverage)) and only the 100 million variants with the greatest scores are loaded in the window.



Any discrepancies that exist between the reference sequence and the sample sequence are highlighted as follows:


- Variations that occur below the variant calling settings defined in the Project Wizard (which are often the result of instrument error) or variants that are filtered out based on the Mutation Report Filter settings (see "Mutation Report settings" on page 213) are highlighted in gray.
- Variant calls are highlighted in blue for novel variants and in purple for reported variants.

You have multiple ways of navigating the Alignment viewer and you also have options for working with and modifying the displayed information.

Alignment viewer navigation

You have multiple ways of navigating the Alignment viewer.

• On the NextGENe Viewer main menu, click Search to open the Search dialog box, where you can indicate how you want to search the displayed alignment—by Sequence, by Position (chromosome, chromosome position (for example, 1, 20000)) or by Gene Name. You can also click Option to search by a reverse complement sequence.



Search		×
Find Diptions	C Search by Position	 Search by Gene Name
so bearing bequeries		
ЕРНВ6	▼ Option	<u>P</u> revious <u>N</u> ext

Chapter 6 Sequence Alignment Tool


• You can easily navigate the Alignment viewer using some of the toolbar icons (see "NextGENe Viewer toolbar" on page 147) or your mouse and some keyboard hotkeys.

Navigation	Action
Zoom In	Hold down the left mouse button and draw a box from the upper left hand corner of the pane towards the lower right hand corner. A box is formed around the area that being reduced for viewing.
Zoom Out	Hold down the left mouse button and draw a box from the lower right hand corner of the pane towards the upper left hand corner.
	Note: The magnification for zooming out is always 100%.
Display sequence read Information	Place the cursor in the pane and then click and hold the [Ctrl] key to display the name and directional orientation of each sequence read.
Display variant information	Place the cursor on a variant to display information about the variant (position, coverage, and so on).
Copy sequence or image	Press and hold the [Shift] key and the [Ctrl] key and then click and hold the left mouse button and draw a box around the region of the display (sequence or image) that you want to copy. The selected region is filled with black. Right-click and select Copy Sequence or Copy As Picture to copy the sequence or image to your clipboard. Use standard keyboard commands or menu commands to paste the copied sequence or image into an application.
Mutation Calls	Place the cursor in the pane, click and hold the [Ctrl] key and then press:
	F to move forward to the next variant call.
	B to move back to the previous variant call.
Mutation report	Double-click a variant in the Alignment Viewer to go to the position in the Mutation report. See "Sequence Alignment Project Mutation Report" on page 210.

Figure 6-17: Sequence read information

Pile-Up	c c	T T	G G	A A	T T	T T	A A	A A	A A	A A	A	>KHKE)T:015	91:010 ⁻	19>
	С	Т	G	Α	Т	Т	Α	Α	Α	Α	Ă	А	Α	Α	Α


Figure 6-18: Variant information



Alignment viewer functions

Right-click in the Alignment viewer to open a context menu that contains a list of options for working with and modifying the information in the viewer.

Figure 6-19: Alignment viewer context menu



Option	Comment
Add Mutation	Click this option to open the Add New Mutation dialog box and specify a variant call for a position.
	Figure 6-20: Add New Mutation dialog box
	Add New Mutation
	Mutation Position
	Coverage 5 Gbk Base T
	A(%) 0.00 C(%) 0.00 T(%) 0.00
	G(%) 0.00 Ins(%) 0.00 Del(%) 0.00
	Insertion Base(s)
	Comments
	Note: To view a manually added variant in the Mutation report, you must select "Added manually" on the Filters tab on the Mutation Report Settings dialog box. The Comment column displays "Added Manually" for the variant. See "Filter tab, Annotation sub-tab" on page 223.
Delete Mutation	Click this option to remove a variant call for a position. Although the position is no longer called a variant, the sequence of the reads is not changed.
	Note: To view a deleted variant in the Mutation report, you must select "Deleted" on the Filters tab on the Mutation Report. Settings dialog box. The deleted variants are highlighted in gray and the Comments column displays "Deleted" for each variant. See "Filter tab, Annotation sub-tab" on page 223.


Chapter 6 Sequence Alignment Tool

Option	Comment
Undo Deletion	Undoes a selected manual deletion. The position is again called a variant.
Confirm Mutation	Click this option to select variants in which you have a high confidence.
	Note: To view a confirmed variant in the Mutation report, you must select "Confirmed" on the Filters tab on the Mutation Report Settings dialog box. The confirmed variants are displayed in black text in the Mutation report and the Comments column displays "Checked" for each variant. See "Filter tab, Annotation sub-tab" on page 223.
Undo Confirmation	Undoes the manual confirmation of a selected variant.
Undo	Undo the <i>last</i> edit action that was carried out for a selected variant.
View Edit History	Available only if User Management is turned (see "Configuring User Management" on page 31) and only after at least one edit action (for example, Deletion) has been carried out for the variant call. Opens the Edit History dialog box, which displays all the edit operations that have been carried by all users for the selected variant. See "Viewing the Edit history for a variant" on page 213.
	Consensus Sequence function from the Mutation report menu, the ns affect how the consensus sequence is output.See "Save consensus 2.
Automatic Add Consensus Break Point	Click this option to automatically add consensus sequence breakpoints at positions where there is no coverage.
Add Consensus Break Point	Click this option to manually add a consensus breakpoint at a selected position.
Delete Consensus Break Point	Click this option to remove a consensus breakpoint at a selected position.
Go to Position in Mutation Report	Click this option to go to the position in the Mutation report. See "Sequence Alignment Project Mutation Report" on page 210.
Tracks	Displays the available tracks (panes) in the NextGENe Viewer window. Click on a track (pane) as needed to toggle its display on and off.
	Note: Tracks is also available as a context menu option for the Position pane, the Translation pane, and the Tracks Display section.

Segment Breakpoints

When you align a sample file to a reference sequence that contains discontinuous segments, such as transcripts or assembled contigs, the breakpoints between segments are indicated by a vertical red line in the Whole Genome viewer and in the Alignment viewer. Because the sequence from the end of one to segment to the beginning of the other is not continuous, NextGENe highlights portions of the reads that align across the segment breakpoint. Typically, one end of the read matches to the end of one of the segments and the other end of the read is then mapped to the following segment, usually with low matching. The portion of the read that matches poorly is shown in lowercase with a gray background.

Figure 6-21: Reads aligned at segment breakpoints



Status bar

The Status bar is displayed in the bottom right corner of the NextGENe Viewer window.

Figure 6-22: NextGENe Viewer window, Project Information Summary bar

From left to right, the Status bar displays the following information:

- The reference to which the samples were aligned.
- The size (bp) of the reference.
- The total number of reads and the Average Coverage for the reads.
- The username for the currently logged in user.

Paired Reads Alignment

NextGENe can align paired end/mate paired data to a reference genome. When you load paired read sample files, NextGENe can identify the pairs only if one character, the *designating character*, is different between the two files, for example, 1/2 or F/R. For SOLiD system data, the designating character can also be 3/5. When "Load Paired Reads" is selected on the Alignment Settings page (see "Load Paired Reads" on page 138), NextGENe first attempts to align the reads where the *gap distance* (the distance between the two ends of the read in bps) falls within the *expected gap distance* (Library size - (2 x Read Length)). If the pairs cannot be aligned within the expected gap distance, NextGENe then aligns the reads to the best matching position. When aligning paired end/mate paired data, five results are possible (with the first four listed below being the most common):

- Both reads can be aligned to the reference and are oriented in opposite directions.
- Both reads can be aligned to the reference and are oriented in the same directions.
- One read in the pair can be aligned to the reference but the other read does not.
- Neither read can be aligned to the reference.
- Additionally, paired end/mate paired end samples often include some unpaired reads that could be matched or unmatched to the reference.

NextGENe considers each of these possibilities and provides statistics for each when aligning paired end/mate paired data.

If NextGENe still cannot recognize the pairs, try isolating the designating character with an underscore, for example, $_1$ and $_2$.

After you complete an alignment project for paired end/mate paired data, in addition to the standard alignment reports (see "Sequence Alignment Project Reports" on page 246), you can also generate specialized Paired reports that list all the pairs that align to the reference with a gap distance that is outside of the expected gap distance as determined by the Sequence Alignment settings. You can also generate a Paired Reads Gap Distribution report and a Paired Reads Statistics report and you can export specific information for your paired read data, such as which reads in the pair were not matched, to a fasta file. All these reports ands functions are available from the Paired View menu on the NextGENe Viewer main menu. See:

- "Paired Reads Gap Distribution report" on page 157.
- "Paired Reads Statistics report" on page 158.
- "Paired Reads Statistics report" on page 158.
- "Opposite Direction Paired Reads report" on page 159.
- "Same Direction Paired Reads report" on page 161.
- "Single Reads report" on page 163.

- "Paired Reads Graph report" on page 165.
- "Export SV Reads function" on page 167.




For detailed information about the other alignment project reports that are available for paired end/mate paired data, see "Sequence Alignment Project Mutation Report" on page 210 and "Sequence Alignment Project Reports" on page 246.

Paired Reads Gap Distribution report

Figure 6-23: Paired Reads Gap Distribution report

The Paired Reads Gap Distribution report shows the number of pairs with continuous gap sizes (every possible gap size, up to the maximum number of bps in the reference sample).

N Paired Reads Gap Distribution



The report displays two charts. The top chart shows the gap sizes for pairs that are oriented in opposite directions (blue bars). The bottom chart shows the gap sizes for pairs that are oriented in the same direction (green bars).

Paired Reads Statistics report

The Paired Reads Statistics report details various statistics about the paired end/mate paired data including the matched read count and matched pairs with a gap distance in the expected range.

Figure 6-24: Paired Reads Statistics report example

Total Reads Count	16089799
Unpaired Reads Count	1770755
Matched Reads Count	9788494
Matched Paired Reads Count	5328584
Matched Paired Reads within Expected Gap Distance Count	4857542
Matched Unpaired Reads Count	1298465
Paired Reads with Only one Read Matched Count	3161445
Paired Reads Matched with Same Direction Count	336890

Value	Description
Total Reads Count	The total number of reads in the sample files.
Unpaired Reads Count	The total number of reads in the sample files that do not have a mate.
Matched Reads Count	The total number of reads in the sample files that matched to the reference file, including both paired reads and single reads.
Matched Paired Reads Count	The total number of paired reads in the sample files with both reads matched to the reference file. (Does not include single reads.)
Matched Paired Reads within Expected Gap Distance Count	The total number of paired reads in the sample files that matched to the reference file at a distance from which their mate matched that was within the expected gap distance.
Matched Unpaired Reads Count	The total number of unpaired reads in the sample files that matched to the reference file.
Paired Reads with Only One Read Matched Count	The total number of paired reads in the sample files with only one read matched to the reference file. (The mate did not match to the reference file.)
Paired Reads Matched with the Same Direction Count	The total number of paired reads in the sample files with both reads matched to the reference file in the same direction—i.e., both are forward reads or both are reverse reads.

Opposite Direction Paired Reads report

The Opposite Direction Paired Reads report lists all the pairs that aligned to the reference genome in opposite directions and that have a gap distance that is outside of the expected range. After you select the Opposite Direction Paired Reads report option, a Filter Settings dialog box opens.

Figure 6-25:	Filter settings dialog box for specifying the range for the Opposite Direction
	Paired Reads report

Input Region Manually Start 1	Entire Reference Range
Input Points of Insterest Text	File(*.txt)
Input Points of Insterest BED	File(*.bed)

You must specify the range for which to generate the report in this dialog box.

Setting	Description
Input Region ManuallyEntire Reference Range	You must specify the starting position and the ending position, or you can select Entire Reference Range to include the entire reference range in the output.
Comma-delimited text file	There are no special requirements for uploading a comma-delimited text file. If the input text file is a comma-delimited text file, it must contain one of the following lists:
	 A list of specific reference locations (position number) separated by commas
	 A list of reference ranges (start position number - end position number) separated by commas
BED file	A BED file is a tab-delimited text file. You can upload a BED file only if the reference sequence contains chromosome information, which means that the reference sequence must be either a preloaded reference that NextGENe supplies, or a GenBank reference file that contains chromosome information. Each row in the file contains a region of the reference that is to be used for the report, and at a minimum, the file must contain the following information:
	Field #1 - Chromosome number for the region
	Field #2 - Chromosome start position
	Field #3 - Chromosome end position
	Note: Field #4, which is used for the Comment column, is optional.

Because the pairs being shown are oriented in the opposite direction, the pairs are represented with a blue bar.




Figure 6-26: Opposite Direction Paired Reads report example

The report is interactive:

- To show only the paired reads view (the histogram), click the Show Paired Reads View icon.
- To show only the paired reads report (the table), click the Show Paired Reads Report icon
- To sort the report results, double-click any column heading.
- To view a position or region in the Alignment viewer, double-click any value in any column.
- To save the report to a text file, on the report toolbar, click the Save Report icon **I**. A default name and location are provided for the file, but you can change both of these values.

Same Direction Paired Reads report

The Same Direction Paired report lists all the pairs that aligned to the reference genome in the same direction and that have a gap distance that is outside of the expected range. After you select the Same Direction Paired Reads report option, a Filter Settings dialog box opens.

Figure 6-27: Filter settings dialog box for specifying the range for the Opposite Direction Paired Reads report

Input Region Manually	Entire Reference Bange
Start 1	End 2000
Input Points of Insterest Text	File(*.txt)
Input Points of Insterest BED	
	1 =

You must specify the range for which to generate the report in this dialog box.

Setting	Description
Input Region ManuallyEntire Reference Range	You must specify the starting position and the ending position, or you can select Entire Reference Range to include the entire reference range in the output.
Comma-delimited text file	There are no special requirements for uploading a comma-delimited text file. If the input text file is a comma-delimited text file, it must contain one of the following lists:
	 A list of specific reference locations (position number) separated by commas
	 A list of reference ranges (start position number - end position number) separated by commas
BED file	A BED file is a tab-delimited text file. You can upload a BED file only if the reference sequence contains chromosome information, which means that the reference sequence must be either a preloaded reference that NextGENe supplies, or a GenBank reference file that contains chromosome information. Each row in the file contains a region of the reference that is to be used for the report, and at a minimum, the file must contain the following information:
	Field #1 - Chromosome number for the region
	Field #2 - Chromosome start position
	Field #3 - Chromosome end position
	Note: Field #4, which is used for the Comment column, is optional.

Because the pairs being shown are oriented in the same direction, the pairs are represented with a green bar.




Figure 6-28: Same Direction Paired Reads report example

The report is interactive:

- To show only the paired reads view (the histogram), click the Show Paired Reads View icon. ♣.
- To show only the paired reads report (the table), click the Show Paired Reads Report icon
- To sort the report results, double-click any column heading.
- To view a position or region in the Alignment viewer, double-click any value in any column.
- To save the report to a text file, on the report toolbar, click the Save Report icon **I**. A default name and location are provided for the file, but you can change both of these values.

Single Reads report

The Single Reads paired is generated for all single aligned reads. This report provides the name and the position of all reads that aligned to the reference genome without a mate. After you select the Single Reads report option, a Filter Settings dialog box opens.

Figure 6-29: Filter settings dialog box for specifying the range for the Opposite Direction Paired Reads report

ings	
Input Region Manually	Entire Reference Range
Start 1	End 2000
Input Points of Insterest Text I	File(*.txt)
Input Points of Insterest BED	
input onto or motorest pres-	
]6

You must specify the range for which to generate the report in this dialog box.

Setting	Description
Input Region ManuallyEntire Reference Range	You must specify the starting position and the ending position, or you can select Entire Reference Range to include the entire reference range in the output.
Comma-delimited text file	There are no special requirements for uploading a comma-delimited text file. If the input text file is a comma-delimited text file, it must contain one of the following lists:
	 A list of specific reference locations (position number) separated by commas
	 A list of reference ranges (start position number - end position number) separated by commas
BED file	A BED file is a tab-delimited text file. You can upload a BED file only if the reference sequence contains chromosome information, which means that the reference sequence must be either a preloaded reference that NextGENe supplies, or a GenBank reference file that contains chromosome information. Each row in the file contains a region of the reference that is to be used for the report, and at a minimum, the file must contain the following information:
	Field #1 - Chromosome number for the region
	Field #2 - Chromosome start position
	Field #3 - Chromosome end position
	Note: Field #4, which is used for the Comment column, is optional.

1				
dex	Read Name	Read Start	Ref Title	Section Pos
	>7_i4UvTfNCwN1/1	4998	NT_113796	0
	>3_Z4YsTfNCwN1/2	6489	NT_113796	0
	>7_G5lfkSOCwN1/2	6506	NT_113796	0
	>5_nRplffNCwN1/1	8552	NT_113796	0
	>3_LypjeSOCwN1/1	8659	NT_113796	0
	>7_wyPKAfNCwN1/1	9487	NT_113796	0
	>7_8b7HtSOCwN1/1	9499	NT_113796	0
	>5_oD5iBfNCwN1/1	9511	NT_113796	0
	>7_hl5NRSOCwN1/1	9544	NT_113796	0
	>1_TUYzRSOCwN1/2	9554	NT_113796	0
	>3_ekrmCfNCwN1/2	9558	NT_113796	0
	>5_4Un5mSOCwN1/2	9601	NT_113796	0
	>5_jHuCnSOCwN1/2	9656	NT_113796	0
	>7_qP8AYfNCwN1/2	9661	NT_113796	0
	>7_k8XmOfNCwN1/1	10187	NT_113796	0
	>1_u4MpYSOCwN1/2	10654	NT_113796	0
	>7_77c5TSOCwN1/2	10780	NT_113796	0
	>1_Y7LVISOCwN1/1	10843	NT_113796	0
	>1_Y7LVISOCwN1/2	10941	NT_113796	0
	>1 LtmWEfNCwN1/1	11134	NT 113796	n

Figure 6-30: Single Reads report example


The report is interactive:

- To sort the report results, double-click any column heading.
- To view a position or region in the Alignment viewer, double-click any value in any column.
- To save the report to a text file, on the report toolbar, click the Save Report icon **I**. A default name and location are provided for the file, but you can change both of these values.

Paired Reads Graph report

The Paired Reads Graph report graphically displays where the mates aligned for paired reads at a given reference position. The report also graphically displays the number of reads for which the mate did not align to the reference sequence in either direction.





From left to right, the graphs that are displayed on the report are the following:

- Reverse Dir—The Reverse Dir graph shows where both reads be aligned to the reference sequence in opposite directions.
- Same Dir—The Same Dir graph shows where both reads aligned to the reference sequence in the same direction.
- Single—The Single graph shows the number of reads that aligned to the reference sequence at a given position without a mate.

The data points in the Reverse Dir graph and in the Same Dir graph are color-coded (as indicated in the Legend below the graphs). The color code indicates the number of reads that aligned to the reference sequence and that had mates that aligned at the same position in either the opposite direction (the Reverse Dir graph) or in the same direction (the Same Dir graph). For example, in Figure 6-31 above, a red data point indicates that aligned at the same position reads aligned to the reference sequence at the indicated position and their mates aligned at the same position in the opposite direction.

Chapter 6 Sequence Alignment Tool

The report is interactive. You can use the buttons on the report toolbar, or you can manually carry out some of the same actions.



The three graphs in the report are linked. Whenever you carry out one action for a graph (for example, zooming in on a region of a graph), then the same action is carried out for the other two graphs.

Figure 6-32: Paired Reads Graph report toolbar

R	19	+	+	ŧ	+		
---	----	---	---	---	---	--	--

Button	Function
Q	Zoom In button—Zoom in on a graph view. You can also hold down the left mouse button and draw a box from the upper left hand corner of any region in the graph towards the lower right hand corner. A box is formed around the area that being reduced for viewing. After you zoom in on a position in a graph, you can use the Move icons to navigate the display.
9	Zoom out button—Zoom out the graph view. You can also hold down the left mouse button and draw a box from the lower right hand corner of any region in the graph towards the upper left hand corner.
	Note: The magnification for zooming out is always 100%.
*	Move Right button—Move the graphic display to the right.
+	Move Left button—Move the graphic display to the left.
1	Move Up icon—Move the graphic display up.
¥	Move Down button—Move the graphic display down.
	Show/Hide button—Toggles the legend display (on or off) at the bottom of the report.
2	 Refresh button—Reset the report display to the display that is indicated by the range. Note: You change the range of reads that are displayed in the graphs in the Set Read Count Range area. The default value is 0 to the maximum value for the read count range for the given dataset.

Export SV Reads function

The Export SV reads function can be used to export reads that could represent structural variations in your data. Fasta files are saved with reads that fit the following criteria:

- The paired reads where either one or both reads were not aligned.
- The paired reads where both paired reads were aligned, but the distance between the paired reads was not in the expected range of Library Size Range.

One fasta file is produced for each paired read file—projectname_SV_1.fasta and projectname_SV_2.fasta. You can save the files to a location of your choosing, and you can also change the names of the files.

Transcriptome Alignment Project with Alternative Splicing

You select the Transcriptome application type and Alternative splicing if you are aligning transcriptome (RNA-Seq) data and the transcriptome project must contain alternative splicing information. When Alternative splicing is selected, NextGENe uses a proprietary four step alignment algorithm to ensure that reads that span exon junctions can be aligned, and then after alignment, transcripts are called. The settings that are available for a transcriptome project with alternative splicing are very different from the alignment settings for all other application types. If you open a project file for a Transcriptome project with Alternative splicing, then the NextGENe Viewer has visualization options that are application-specific. A Transcript report, which is an application-specific report, is also available. You can also identify the genes that are differentially expressed in transcriptome (RNA-Seq) data, and then upload the report results to Pathway Studio for visualization of the differential expression analysis values as well as biological pathway information.

Transcriptome with Alternative splicing alignment algorithm

- The first step is a basic alignment of the whole genome. An attempt is first made to align entire reads to the reference sequence without any mismatches. Short seed sequences within the reads are then used to align the reads to the reference sequence.
- The second step is alignment to exon junctions using a reference sequence of exon-exon junctions that was created using annotated genes. Any reads that could not be aligned to the genomic reference sequence are aligned to this reference sequence of exon-exon junctions. The positions are translated back to genomic reference positions. Reads are more completely aligned, especially those reads in regions that are near the end of exons.
- The third step is detecting and linking exons. Potential exon regions are recorded. A link is recorded if two exons are at least partially covered by the same read. Several filtering steps are carried out to remove false positives.
- The fourth step is an alignment to the detected transcripts. A reference sequence of mRNA transcripts (a reference without intron sequences) is generated based on the link information. The original reads are aligned to this reference and the coordinates are translated back to genomic positions.

After alignment is completed, regions (covered or annotated) and links are called and then compared to known transcripts so that the regions and links be classified.

Transcriptome project with Alternative splicing alignment settings



The Transcriptome application type with Alternative splicing requires a preloaded reference that is created from an annotated GenBank file or that is supplied by SoftGenetics. Contact tech_support@softgenetics.com for assistance.

The settings that are available for a Transcriptome alignment project with Alternative splicing are very different from the alignment settings for all other application types.

Analysis Options

Setting	Description
Auto Detect PE Library Size	Available only if Paired Reads is selected. Select this option if you do not want to manually specify the library size. Instead, NextGENe automatically determines the library size.
Paired Reads	Select this option if you are analyzing paired reads.
	Note: Processing paired read data for transcriptome analysis requires at least 24GB of RAM, and takes significant processing time. If your system does not have sufficient RAM, or paired end information is not critical for your project, you can clear this option to process the data as single reads.
Library Size: Min [] Max []	Available only if Paired Reads is selected and Auto Detect PE Library Size is not selected. You must manually enter the size of the DNA fragment that is being used for sequencing.
Match Reference	Applicable only if BAM sample files were loaded. Click this option to match the reference that was used to create the BAM file with the reference that was loaded during the Load Data step for the project. See "To load the reference files" on page 56.

• Parameters for Alternative Splicing Analysis

Setting	Description				
Seed Length	The size of the seeds that should be used for the first step of the Transcriptome Alignment algorithm.				
Move Step	The distance in base pairs between the starting points for each seed.				
 Min Coverage in Annotated Region Minimum Coverage 	Set the value to the coverage depth that is expected for the data. If the experimental coverage for the region meets or exceeds this threshold, then an exon is called in this region.				
in Unannotated Regions	Note: A higher minimum coverage value results in faster data processing, and more specific, but less sensitive, results.				
Allowable Ambiguous Number	The maximum number of allowed matches for each seed. For example, you have a seed that matches to 100 positions in the reference sequence and the Allowable Ambiguous Number is set to 20, then only the first 20 matches are considered for analysis. Note: The allowed range is 10-50.				
Remove Non-Linked	Remove any exons that do not have a link.				
Exons	Note: Removing these exons reduces the noise in the analysis.				

Chapter 6 Sequence Alignment Tool

Setting	Description				
Single-Strand Sequencing	Select this option if single strand sequencing was carried out on the samples. Forward and reverse coverage information is also used to separate overlapping transcripts.				
Ignore Fusions Between Similar Genes	Select this option to improve the accurate detection of fusion genes. Eliminates fusion calls between genes with similar names, for example, ABCD1 and ABCD2.				
Rigorous Fusion Detection	Select the option to improve the accurate detection of fusion genes.				
Ambiguous Alignment for Similar Genes	By default, NextGENe checks for similarity between transcript calls. After the initial alignment, it checks for transcripts that are 95% similar in their calls, and then after the final alignment, it checks for transcripts that are 80% similar in their calls. NextGENe removes the called transcripts that meet or exceed these similarity thresholds. Select this option to disable this check and keep all called transcripts, regardless of similarity.				
	Note: In most cases, if you select this option, then the processing time and the number of called transcripts are increased, but the number of mapped reads is not significantly increased.				

• Parameters for New Gene Detection

Setting	Description
Exon Size Min [] Max []	The range in bps for a region to be called an exon.
Average Coverage	The expected coverage for calling an exon, which is carried out in the second alignment step. This value is used is similarly to the alternative splicing's average coverage option of the first alignment step.
	Note: The value that you enter here is not an absolute threshold. It is used simply as an approximation when calling an exon.
Intron Size Min [] Max []	The expected range in bps for introns (the regions between called exons).
Donor-Acceptor	Defines the beginning and ending base pairs for identifying a region that can be called as an exon.

• Parameters for Hash-Table Alignment

Setting	Description					
Matching Requirement: Base Number >= [x] and Base percentage >= [y]	"x" indicates the minimum number of bases in each read that must match the reference sequence for the read to align with a specific position in the reference sequence. "y" indicates the minimum percentage of each sequence read that must match the reference sequence for the read to align with a specific position in the reference sequence.					
	Note: Both conditions must be met for the read to be aligned to the position.					
Allow Ambiguous Mapping	Aligns the read to each exact match position if a read matches exactly at more than one position in the reference. If this option is not selected, the read is aligned to the first exact match position from the start of the reference.					

Setting	Description
Remove Ambiguously Mapped Reads	Removes reads that match exactly to more than one position in the reference from the analysis.


• Parameters for Mutation Detection

Setting	Description			
Mutation Percentage <= []	A variation between the aligned reads and the reference sequence at a given position of the reference must occur at a frequency that exceeds this value or the variant is not reported.			
SNP Allele <= []	If more than the specified number of reads has the SNP allele, then the variant at a given position is reported			
Total Coverage <= []	The total number of reads at a given position must exceed this coverage threshold for a variant to be called at the position.			
Except for Homozygous Selected by default. The coverage requirement is ignored for variants that are homozygous.				
Note: The values for the mutation percentage, the coverage threshold, and the SNP allele must be must be met for a variant at a given position to be reported. If any criterion is not met, the variant is filtered from the analysis and highlighted in gray in the Alignment viewer.				

Transcriptome project with Alternative splicing view

After you open a Transcriptome alignment project with Alternative splicing in the NextGENe viewer, the TSC Show Transcript Report option is available on the Report Selection icon. Select this option to open the Transcript report and to display the project in the *transcriptome project view*. From top to bottom, the transcriptome project view has the following visualization options that are specific for a transcriptome project—Global coverage, Localized coverage, Identified transcripts with exon links, and Annotation. Forward coverage is always shown in blue and reverse coverage is always shown in red in the Localized Coverage pane.

Figure 6-33: Transcriptome project view (Transcript report hidden)



For detailed information about the Transcript report, see "Transcript report" on page 173.

Links in the project view are color-coded to indicate the different types of links.


Link Color	Description						
Purple	Purple A link that matches the annotation for the gene. (Annotated link).						
Blue	A link that is not represented by any annotation for the gene. (Novel link).						
Black	A link that represents a gene fusion. (Fusion link).						

Regions in the project view are also color-coded to indicate the different types of regions.

Region	Description
Purple	An exon that matches the annotation for the gene. (Annotated region).
Blue	An exon that is not represented by any annotation for the gene. (Novel region).
Red	Insertion and intron retention.
Pink	An exon that is found in the annotation for the gene, but was not found in the data. (Exon skipping).
Orange	A start or end to an exon that differs from the annotation for the gene. (Alternative splice site).
Gray	An alternative start for the first exon for the gene or an alternative end for the last exon for the gene. (Alternative transcript start/stop).

If you zoom in on a local region for a Transcriptome project, the nucleotide sequence and the amino acid sequence for the detected transcripts are displayed in blue. The annotated transcripts are displayed in green below the nucleotide and amino acid sequences. The Y axis indicates the localized coverage. You can manually adjust the scale for the axis.

Figure 6-34: Zooming in on a local region for a transcriptome project



Transcript report

By default, when the Transcript report first opens in the NextGENe viewer, it is displayed on the right side of the opened NextGENe viewer. You can click the Switch Report Layout icon is on the NextGENe Viewer toolbar to indicate the location for showing the report (to the right or at the bottom of the NextGENe Viewer), or showing only the report (the Alignment Viewer is hidden), or hiding the report. You can do the following for any variant in this report:

- You can double-click any variant entry in this report to update the display in the NextGENe viewer accordingly.
- If you have a subscription to Pathway Studio, then you can right-click a variant in the report, and on the context menu that opens, select View in Pathway Studio to import the gene for the variant into Pathway Studio and visualize the biological pathway information for the gene.



Before you can use the Transcript report in conjunction with Pathway Studio, your Pathway Studio access option must be set for the NextGENe Viewer. See "Process" in "NextGENe Viewer main menu" on page 142.

Figure 6-35: Transcript report

Index	Chr	Start	End	Lengt	Gene	Exon(s)	Link N	PE Lir	Avg C	<-Cov	->Cov	Туре	Isoform	Protein
923	1	9,599,544	9,599,806	263	SLC25A33	1	NA	NA	31	NA	NA	Alt Splice Site	NM_032315.2	NP_115691.1
924	1	9,599,806	9,613,684	13879	SLC25A33	1;2	91	2	NA	31	121	Known Link	NM_032315.2	NP_115691.1
925	1	9,613,684	9,613,863	180	SLC25A33	2	NA	NA	121	NA	NA	Exon	NM_032315.2	NP_115691.1
926	1	9,613,863	9,627,342	13480	SLC25A33	2;3	146	62	NA	121	122	Known Link	NM_032315.2	NP_115691.1
927	1	9,627,342	9,627,419	78	SLC25A33	3	NA	NA	122	NA	NA	Exon	NM_032315.2	NP_115691.1
928	1	9,627,419	9,630,316	2898	SLC25A33	3;4	123	0	NA	122	111	Known Link	NM_032315.2	NP_115691.1
929	1	9,630,316	9,630,416	101	SLC25A33	4	NA	NA	111	NA	NA	Exon	NM_032315.2	NP_115691.1
930	1	9,630,416	9,633,404	2989	SLC25A33	4;5	78	0	NA	111	203	Known Link	NM_032315.2	NP_115691.1
931	1	9,633,404	9,633,470	67	SLC25A33	5	NA	NA	203	NA	NA	Exon	NM_032315.2	NP_115691.1
932	1	9,633,470	9,640,012	6543	SLC25A33	5;6	201	0	NA	203	180	Known Link	NM_032315.2	NP_115691.1
933	1	9,640,012	9,640,292	281	SLC25A33	6	NA	NA	180	NA	NA	Exon	NM_032315.2	NP_115691.1
934	1	9,640,292	9,642,357	2066	SLC25A33	6;7	100	44	NA	180	207	Known Link	NM_032315.2	NP_115691.1
935	1	9,642,357	9,642,831	475	SLC25A33	7	NA	NA	207	NA	NA	Exon	NM_032315.2	NP_115691.1
	-	0.010.004	0.010.071	100	01.005.400	•	N.1.3	K.1.4	1.01	K1.4	K 1 A	ALCONTRA CONT	NILL COOST D	NID ARCOOKE

Field	Description						
Each entry (record) in the Transcript report represents a region or a link. Purple text indicates an annotated record and blue text indicates a novel record.							
Index	The numerical value that NextGENe assigns to the record.						
Chr	The name of the chromosome where the record occurs.						
Start	The base number that indicates where the record starts.						
End	The base number that indicates where the record ends.						
Length	The length (in base pairs) for the region, or the length between the two ends of a link. N/A is displayed for fusion links.						
Gene	The name of the gene where the record is found.						
Exon(s)	One exon number is displayed in this column if the record is a region. Two exon numbers are displayed in this column if the record is a link. N/A is displayed in this column if there is not an annotated exon for the record.						

Chapter 6 Sequence Alignment Tool

Field	Description			
Link Number	Applicable only for link records. The number of reads that covered the link. Displays N/A for region records.			
PE Link Number	Applicable only for link records in paired end data. The number of pairs where one read maps to either end of the link. Displays N/A for region records and non-paired end data.			
Avg Coverage	Applicable only for region records. The average coverage of the region. N/A is displayed for link records.			
<-Coverage ->Coverage	Applicable only for link records. Average coverage of the regions that are linked. N/A is displayed for region records.			
Туре	The type of region or link.			
Isoform	The NCBI accession number for the mRNA isoform.			
Protein	The NCBI accession number for the protein.			
Contig The contig (region of the reference) where the record is found.				
Note: You can click any NCBI accession number to go to the NCBI website				

You can click the Report Settings icon is on the NextGENe Viewer toolbar to open the Transcript Report Settings dialog box and specify what information is to be displayed in the report.

Transcript report settings

The Region Type options on the Filters tab of the Transcript Report Settings dialog box are different for an index that was not created from GenBank files (Figure 6-36 below) versus an index that was created from a GenBank file (Figure 6-36 on page 174).

Figure 6-36:	Transcript Report	Settings dialog	box, Filters tab	(non-GenBank index)
--------------	-------------------	-----------------	------------------	---------------------

🔰 Transcript Report Settings	
Filters Columns	
Record Type	
Link Type	Region Type
Vovel	🔽 Annotated RNA
🔽 Known	Unannotated
🔽 Fusion	✓ Intron Retention
	✓ Insertion
	🔽 Exon Skipping
	✓ Alt Splice
	✓ Alt Transcript Start/Stop
Filters	
Min Number of Novel Link	Min Coverage of Unannotated
	_ 1
Min Number of Fusion	Min Coverage of Intron Retention
Min PE Number of Fusion	
	Min Coverage of Insertion
Min Coverage of Alt Splic	e Min Coverage of Alt Start/Stop
Save Set	tings Load Settings Default <u>DK</u> Cancel

Figure 6-37:	Transcript Report Settings dialog box, Filter	rs tab (GenBank index)

Region Type	
🔽 mRNA	🔽 Unannotated
🔽 rRNA	Intron Retention
🔽 tRNA	🔽 Insertion
🔽 ncRNA	🔽 Exon Skipping
🔽 misc_RNA	🔽 Alt Splice
🔽 LTR	🔽 Alt Transcript Start/Stop
Pseudogene	

Setting	Description		
Record Type			
Link Type	Show the indicated link type.		
Sequence Type	Show the indicated sequence type.		
Filters			
	in the report only if the link number (the number of reads that overlap the link) reshold or display the region record in the report only if the number of reads		

that cover the region meets the indicate threshold.

Figure 6-38: Trans	cript Report Settings	dialog box,	Columns tab
--------------------	-----------------------	-------------	-------------

Transcript Report Se	ttings		0
Filters Columns			
🗭 Index			
🔽 Chr	🔽 Start	🔽 End	🔽 Length
🔽 Gene	🔽 Exon(s)		
🔽 Link Number	🔽 PE Link Number		
🔽 Avg Coverage	🔽 <-Coverage	₩ ->Coverage	
🔽 Type	🔽 Isoform	🔽 Protein	
S	ave Settings Load Settin	ngs Default	OK <u>C</u> ancel

You specify which columns are to be displayed in the Transcript report. By default, all columns are selected.



You can use the Save Settings function to save the selected report settings to a Settings file (.ini file), and you can use the Load Settings function to load this Settings file for use in another project report.

Differential gene expression analysis of transcriptome data

Differential gene expression generates extraordinarily complex networks of gene and protein interactions. To understand the molecular mechanisms of health and disease, these networks must be identified and understood. You can use the Expression Comparison report to identify the genes that are differentially expressed in transcriptome (RNA-Seq) data, and then upload the report results to Pathway Studio for visualization of the differential expression analysis values as well as biological pathway information. Elsevier R & D Solutions Pathway Studio uses a knowledge base of biological relationships culled from millions of articles and abstracts as well as clinical trials to enable the analysis and visualization of disease mechanisms, gene expression and proteomics and metabolomics data by researchers. A separate subscription to Pathway Studio is required to access Pathway Studio from NextGENe.



Before you can use the Expression Comparison report in conjunction with Pathway Studio, your Pathway Studio access option must be set for the NextGENe Viewer. See "Process" in "NextGENe Viewer main menu" on page 142.



For instructions about carrying out a detailed differential expression pathway analysis in Pathway Studio, see the SoftGenetics application note "Integrating NextGENe Software with Pathway Studio for Differential Gene Expression and Biological Pathway Analysis at http://softgenetics.com/PDF/PathwayStudioAppNote.pdf.

1. On the NextGENe Viewer's Comparisons menu, click Expression Comparison Report.

The Expression Comparison Report Settings dialog box opens. The General tab is the only tab.

Figure 6-39: Expression Comparison Report Settings dialog box, General tab

Expressio	on Comparison Report	Settings		×
General	Summer Report			
Regio	ns			
ΘL	Jse Segments as Defined	in Reference Files		
(• Gene	⊂ mBNA	C CDS	
0	🔿 Continuous mRNA	C Continuous CDS		
(O ROI			
O S	iet Incremental Segment L	ength 10000	Bases	
O Ir	nput Region of Interest (*.	bed)		
				Set
Limits				
	Limit to First 200	bp		
	Limit to Last 200	bp		
	<u>Save Settings</u>	ad Settings		<u>C</u> ancel

Option	Description
Use segments as	Gene - Report coverage levels for each gene.
defined in the reference files.	 mRNA - Report coverage levels for each mRNA region. (Coding and non-coding exons.)
	CDS - Report coverage levels for each coding region.
	 Continuous mRNA - Report coverage levels for the entire mRNA for a gene, one region per gene.
	 Continuous CDS - Report coverage levels for the entire coding region for a gene, one region per gene.
	 ROI - Report coverage levels based on Regions of Interest that are defined in a GenBank reference file.
	Note: For information about defining Regions of Interest in a GenBank reference file, see "Advanced GBK Editor tool" on page 280
Set incremental segment length	Specify the segment length.
Input region of	You can upload a Region of Interest file in a BED format.
interest (*.bed)	Note: For information about the required format for the BED file, see "BED file" on page 463.

2. Indicate how to define the segments that are to be analyzed and reported on by the tool.

3. Optionally, select one or both Limit options and if needed, modify the default limits (200 bp) for reporting the coverage for only the first or last "x" number of bases of the selected segment type.




Optionally, at this point, you can click Save Settings to save the settings for this report in a Settings file (.ini file), which can be used to generate the Expression Comparison report for another project based on the settings in the file.

4. Click OK to open the Load Project Files dialog box.

Figure 6-40: Load Project Files dialog box

Load Project Files	×
Reference File:	
	<u>S</u> et
Sample File(s):	
	Add
	<u>R</u> emove
	<u>C</u> ancel

5. Click Set to browse to and upload the reference project file (the control sample file).




6. Click Add to browse to and select an alignment project file that is to be included in the comparison. Repeat this step until you have added all the necessary project files.



You can load a maximum of ten projects.

7. Click OK to close the Load Project Files dialog box and generate the report.





- 8. The report is interactive. Optionally, you can do any or all the following:
 - Change the report view. The report can display either the "Min Coverage," "Max Coverage," (the default value), the "Average Coverage," "Minimum Forward Read Coverage," "Minimum Reverse Read Coverage," "Read Counts," "Forward Read Counts," "RPKM," "RPK," or "FPKM" for each region. To change the view, on the report menu, click View, and on the View menu, select a different viewing option.



FPKM is available only if paired end data was analyzed for the projects.

Save the report. To save the report to a text (*.txt) file, on the report menu, click File
 > Save, or on the report toolbar, click the Save Report icon . A default name and location are provided for the file but you can change both of these values. The saved

report is a table that lists the gene name and description for each region as well as the actual expression values for each region for every loaded project. The differential expression values of Ratio, log2Ratio, z-value, and p-value are also calculated and displayed for each gene in the report.

- Change the view based on original reads. For projects that used condensation, the views are based on the condensed reads. To change the view so that is based on the original reads, click Display Original Information at the top of the report.
- Modify the report settings. To modify the report settings, on the report menu, click Settings > Settings to open the Expression Report Settings dialog box and modify the report settings as needed. The report display is dynamically updated after you save the modifications.
- 9. On the report main menu, click File > Upload gene list to Pathway Studio.

The Sample Setting dialog box opens. The names of the projects that were loaded as the sample projects are displayed appropriately in each Sample name field.

Figure 6-42: Sample Setting dialog box

Nane	UNIT_Durput	Product	NextGERe			
Orgenization	Sofigenetics	Orparvitm	Haman			
Property description	F	(Optional)				
Property source	-	(Optional)				
Sample Sample name	UHR_Durput	Class name	Insirv	Value	control	_
Semple name	HBR_Dutput	Clast name	[th:sin	Velue	cai#	_
Differential expression						
DE1 Name	HBR_Output vs UHR_Output					
Sample pet l	HBR_DupA	Sample set2	UHR_0up4			

10. Enter the appropriate sample settings for your analysis, and then click OK.

The Sample Setting dialog box closes. Differential expression values of Ratio, log2Ratio Fold Change, z-value, and p-value are uploaded to Pathway Studio. You are re-directed to the login page for Pathway Studio.

11. Log in to Pathway Studio.

The Expression Comparison data is imported into Pathway Studio. You can now carry out a detailed differential expression pathway analysis for the sample projects.


STR (Short Tandem Repeats) Analysis Project


You select STR analysis if you are aligning data from STR sequencing to a reference file that contains reference STR alleles. If you select STR analysis as the application type, then you must create a custom reference file in .fasta format for the analysis. A specific alignment setting is required for STR analysis. If you open a project file for an STR analysis project in the NextGENe viewer, an STR report, which is an application-specific report, is available. The report has visualization options that are specific for STR analysis. An STR Reads Histogram report, which is a report that details all the read information for all the alleles that were identified for a selected locus across all loci in the project, is also available.

STR analysis custom .fasta reference file

You must use a text editor to create a custom reference file in .fasta format to carry out STR analysis. One reference .fasta file is required per locus, with one allele per .fasta line in the file. The file name must be the same as the name of the locus, for example, D18S51.fasta. In each .fasta file, each allele is identified by its name in the title line above the allele sequence line. The allele sequence line contains three parts:

- The pre-repeat flanking sequence.
- The allele repeat sequence.
- The post-repeat flanking sequence.





Typically, the flanking sequences are identical for all the alleles for the locus but the repeat sequence region is specific for each allele. Also, typically, there is a difference in the length within the reference region for each allele, but there might be other differences as well such as a SNP within the region for one of the alleles.

STR project alignment settings

In addition to the default sequence alignment project settings, a specific alignment setting— *Read length over reference length*—is required for STR analysis.

Setting	Description
Read length over reference length <u>></u> [80%]	Selected by default. The read must cover at least the indicated percentage of the segment to which it is aligned, or it is not assigned to an allele.
	Note: This setting ensures that the read covers an entire repeat region.



Variants that do not pass the Mutation Filter thresholds are assumed to be sequencing errors and they are ignored when assigning reads to alleles. See "Mutation Filter settings" on page 137.

STR project report

After you open an STR analysis project in the NextGENe viewer, the STR Show STR Report option is displayed on the Report Selection icon. Select this option to open the STR report in addition to the Alignment view. The report has two sections. The top section is the *Locus report*, which shows the different loci that were analyzed along with associated information for each locus. The bottom section is the *Allele report*, which displays a row for each allele, by name, that was identified in the sample for a selected locus. The information is relative to the order of the alleles listed in the Allele Name column in the Locus report. Double-click any entry in the Locus report to update the display in the NextGENe viewer and the Allele report accordingly. You can also double-click any allele in the Allele report to change the focus of the display to the selected allele.

Seq 🔟	AP 🛠 💻		_	-	FA 8	∃* ₩	11111111111111	<u></u> =		
ndex	Locus	Locus Coverage	Locus Percenta	Allele N	umber	Allele Name		Allele Frequency	*	
	Amelogenin	1335	8.544%	2		Amelogenin_X,	Amelogenin_Y	52.95%, 47.04%		
	CSF1P0	1772	11.34%	2		CSF1P0_7.0, C	SF1P0_16.0	52.99%, 47.00%		
	D13\$317	374	2.393%	1		D135317_13.0		100%		
	D16S539	1594	10.20%	2		D16S539_12.0,	D16S539_9.0	54.95%, 45.04%	-	Locus repo
	D18551	739	4.729%	2		D18551_10.0, D	018551_9.0	92.01%, 7.983%		
	D21S11	1782	11.40%	2		D21S11_29.0, D	21511_28.0	91.97%, 8.024%		
	D3S1358	1100	7.04%	2		D3S1358_17.0,	D3S1358_15.0	59%, 41%		
	D55818	1035	r r74%	2		D55818 10.0 F	156818 12.0	RN% 4N%	+	
ndex	Sequence	Matched Allele N	lame Status	Start	End	Frequency	Total Reads	Forward Reads	Rev	
	CCCTGGGCTCTG	i Amelogenin_X	Matched	t	106	52,95%	707	342	365	Allele
5	CCCTGGGCTCTG	Amelogenin Y	Matched	109	220	47.04%	628	297	331	report

Figure 6-44: STR report

Column	Description
Locus report	
Locus	The name of the locus that was analyzed. Any loci that failed any of the Filter settings for the report, are grouped into a row with Unknown displayed in this column. See "STR Report Settings dialog box" on page 186.
Locus Coverage	The total number of reads that were aligned to the locus.
Locus Percentage	Locus coverage/Total number of aligned reads.
Allele Number	The total number of alleles that were identified for the locus.
Allele Name	The names of the individual alleles that were identified for the locus. If the locus is Unknown, then N/A is displayed in this column.
Allele Frequency	The number of reads that were assigned to each allele out of the number of reads that were assigned to all accepted alleles for the locus. (Shown as a percentage.) The information is relative to the order of the alleles listed in the Allele Name column. Note: Depending on the Filter settings that were specified for the
	report, these values might not be the same as the Frequency values in the Allele report. See "STR Report Settings dialog box" on page 186.
Allele Total Coverage	The total number of reads that are assigned to each allele. The information is relative to the order of the alleles listed in the Allele Name column.
Allele Percent Matched	The percentage of the sequence for the sample allele that matches the sequence for the reference allele. The information is relative to the order of the alleles listed in the Allele Name column.If the match is 100%, then the allele is considered to be a Matched allele.
	 If the match is less than 100%, then the allele is considered to be a Possible allele.
Allele report	
Sequence/Length	The default value is sequence, which shows the sequence for the sample allele. You can change the report settings to show the length, which is the length of the sample allele in base pairs based on the consensus length of all the reads that were assigned to the allele. See "STR Report Settings dialog box" on page 186.
Matched Allele Name	The reference allele name for the allele to which the sample data is matched. Based on the allele name that was defined in the custom FASTA reference file.
Status	 If the sample allele sequence matched 100% to the reference allele sequence, then Matched is displayed for the status.
	 If the sample allele sequence matched less than 100% to the reference allele sequence, then Possible is displayed for the status.
	 If the allele's locus is Unknown, then N/A is displayed for the status.
Start	The start position of the allele within the reference.

Column	Description
End	The end position of the allele within the reference.
Frequency	The number of reads that were assigned to the allele out of the total number of reads that were aligned to the locus. (Shown as a percentage.)
	Note: Depending on the Filter settings that were specified for the report, these values might not be the same as the Allele Frequency values in the Locus report. See "STR Report Settings dialog box" on page 186.
Total Reads	The total number of reads that aligned to the allele.
Forward Reads	The number of reads that were assigned to the allele that were forward reads.
Reverse Reads	The number of reads that were assigned to the allele that were reverse reads.
Differences	The number of bases in the sample allele sequence that do not match the reference allele sequence.
	• For matched alleles, the difference = 0.
	 For possible alleles, the difference > 0.

By default, when the STR report first opens in the NextGENe viewer, it is displayed on the right side of the opened viewer, and the focus in the Alignment viewer is set to the first locus in the list of analyzed loci. A blue cross centered in the Alignment viewer indicates the position of the locus. The Allele report details the alleles that were identified for this first locus. You can click the Switch Report Layout icon in the NextGENe Viewer toolbar to indicate the location for showing the report (to the right or at the bottom of the NextGENe Viewer), or showing only the report (the Alignment Viewer is hidden), or hiding the report.

The STR report is interactive. You can:

- Double-click on any locus to change the focus in the Alignment view to that of the selected locus. The Allele report display is updated accordingly.
- Double-click on any allele to change the focus in the Alignment viewer to that of the selected allele. A blue cross is displayed in the Alignment viewer to indicate the position of the selected allele on the locus.

Other options are available on the report toolbar. See "STR report toolbar" on page 184.

STR report toolbar


lcon	Action
Seq	Show Allele Sequence Report/Show Allele Length Report - Click this icon to toggle the display for the Allele report between the Allele Sequence report (Sequence column) and the Allele Length in base pairs (Length column).
	Note: You can also change the Report type in the STR Report Settings dialog box to toggle the display. See "STR Report Settings dialog box" on page 186.
ki.	STR Reads Histograms icon - Click this icon to open the STR Reads Histogram report, which details the read counts for all the alleles that were identified for a given locus. See "STR Reads Histogram report" on page 184.
AP	Allow Possible Alleles/Check Matched Alleles Only icon - Click this icon to toggle between reporting both Matched alleles and Possible alleles in the Allele report, or reporting only Matched alleles.
	Note: You can also use the Allow possible allele matches filter setting on the STR Report Settings dialog box to toggle the reporting options. See "STR Report Settings dialog box" on page 186.
Ż	STR Report Settings icon—Click this icon to open the STR Report Settings dialog box and specify the information that is to be displayed in the report. See "STR Report Settings dialog box" on page 186.
=	Show/Hide Locus Report icon - Click this icon to toggle the display of the Locus report in the NextGENe viewer.
=	Show/Hide Allele report icon - Click this icon to toggle the display of the Allele report (Sequence or Length) in the NextGENe viewer.
	Save STR Reports icon—Click this icon to open the Save Report as Text File dialog box, and save the STR Locus report and the Allele report as individual text (*.txt) files. By default, the report name is the project name appended with STR and the report is saved in the same location as the project output files, but you can change one or both of these values.
	Note: Before you save the report, make sure that the correct Allele report (Sequence or Length) is displayed in the viewer.

STR Reads Histogram report

On the STR report toolbar, click the STR Reads Histogram icon **b** to open the STR Reads Histogram report. This report details the coverage distribution for all the alleles that were identified for a locus across all the loci in the project.

- The number of forward reads and the number of reverse reads for matched alleles, with the forward reads represented in dark blue and the reverse reads represented in red. The reverse coverage is stacked on top of the forward coverage.
- The number of forward reads and the number of reverse reads for possible alleles, with the forward reads represented in light blue and the reverse reads represented in pink. The reverse coverage is stacked on top of the forward coverage.

See Figure 6-45 on page 185.






The report is interactive. You can click one of the following to save the report as either a PDF or PNG file, respectively.

- File > Save as PDF
- File > Save as PNG

You must specify the name and location for the saved report.

STR Report Settings dialog box

On the report toolbar, click the STR Report Settings icon 3 to open the STR Report Settings dialog box and indicate the information that is to be displayed in the report. By default, all columns for the Locus report and the Allele report are selected for display. Also by default, the Allele Sequence report is displayed.



ocus report display settings		Allele sequence report display setting:
₩ Locus		Sequence
✓ Locus Coverage	V Matched Allele Name	
🔽 Locus Percentage		🔽 Status
		🔽 Start
Allele Number		🔽 End
🔽 Allele Name		Frequency
Allele Frequency		🔽 Total Reads
Allele Total Coverage		Forward Reads
Allele Percent Matched		Reverse Reads
ilter settings		I Differences
Allow possible allele matches		Report type
Maximum differences	3	Allele sequence report
Minimum forward/reverse balance		
Minimum count	10	
Minimum frequency	5 %	
Save Settings Load	d Settings	Default OK Canc



Optionally, you can also do either one or both of the following:

- Click Load Settings and browse to and select a Settings file (.ini file) to generate the STR report based on the saved settings in the file.
- Click Save Settings to save your settings for the report in a Settings file (.ini file). You can use this saved Settings file to generate the STR report for another project based on the settings in the file.

Setting	Setting Description					
Locus report display settings						
Locus	The name of the locus that was analyzed.					
Locus Coverage	The total number of reads that were aligned to the locus.					
Locus Percentage	Locus coverage/Total number of aligned reads.					
Allele Number	The total number of alleles that were identified for the locus.					
Allele Name	The names of the individual alleles that were identified for the locus. If the locus is Unknown, then N/A is displayed in this column.					
Allele Frequency	The number of reads that were assigned to each allele out of the number of reads that were assigned to all accepted alleles for the locus. (Shown as a percentage.) The information is relative to the order of the alleles listed in the Allele Name column.					

Setting	Description
Allele Total Coverage	The total number of reads that are assigned to each allele. The information is relative to the order of the alleles listed in the Allele Name column.
Allele Percent Matched	The percentage of the sequence for the sample allele that matches the sequence for the reference allele. The information is relative to the order of the alleles listed in the Allele Name column.
	 If the match is 100%, then the allele is considered to be a Matched allele.
	 If the match is less than 100%, then the allele is considered to be a Possible allele.
Allele sequence report	t display settings
Sequence/Length	The default value is Sequence, which shows the sequence for the sample allele. If you select Allele length report for the report type, then report display is changed to show the length, which is the length of the sample allele in base pairs based on the consensus length of all the reads that were assigned to the allele. See "Report type" on page 188.
	Note: You can also click the Show Allele Sequence/Show Allele Length Report icon to toggle the display of the Allele report. See "STR report toolbar" on page 184.
Matched Allele Name	The name of the sample allele that was matched to the reference allele. Based on the allele name that was defined in the custom FASTA reference file.
Status	The status for the allele—Matched, Possible, or Unknown.
Start	The start position of the allele within the reference.
End	The end position of the allele within the reference.
Frequency	The number of reads that were assigned to the allele out of the total number of reads that were aligned to the locus. (Shown as a percentage.)
Total Reads	The total number of reads that aligned to the allele.
Forward Reads	The number of reads that were assigned to the allele that were forward reads.
Reverse Reads	The number of reads that were assigned to the allele that were reverse reads.
Differences	The number of bases in the sample allele sequence that do not match the reference allele sequence.
Filter settings	
Allow possible allele matches	If selected, report both matched and possible alleles, which contain one or more mismatches. If not selected (the default value), then report only matched alleles.
	Note: You can also click the Allow Possible Alleles/Check Matched Alleles Only icon on the report toolbar to toggle between reporting both Matched alleles and Possible alleles in the STR report, or reporting only Matched alleles. See "STR report toolbar" on page 184.

Setting	Description				
Maximum differences	Available only if Allow possible allele matches is selected. If the number of differences between the sample allele sequence and the reference allele sequence exceeds the indicated value, then the allele is classified as Unknown.				
Minimum forward/ reverse balance	Indicates the balance for the #F/#R reads for the allele and vise-versa. For example, if set to 5%, then if there were 100 reverse reads for the allele, there must at least 5 forward reads for the allele, otherwise, the allele would be classified as Unknown. The default value is zero, which means that there is no requirement for the Forward/Reverse balance.				
	Note: Adjusting this setting can help reduce the rate of false positives.				
Minimum count	The minimum number of reads that are required for an allele, otherwise, the allele is classified as Unknown.				
Minimum frequency	The minimum value (expressed as a percentage) for the ratio of the number of reads for the allele to the total number of reads for the locus. If the frequency for the allele is does not meet or exceed this threshold, then the allele is classified as Unknown.				
Report type					
Allele sequence report	Selected by default. Display the allele sequence (Sequence column) in the Allele report.				
Allele length report	Display the allele length (Length column) in the Allele report.				
Note: You can also click display of the Alle	the Show Allele Sequence Report icon on the report toolbar to toggle the le report.				

Mitochondrial Amplicon Analysis Project


You select Mitochondrial amplicon as the application type if you are identifying alleles for specific amplicons in mitochondrial sequencing data. A Mitochondrial amplicon analysis project has application-specific data requirements. If you open a project file for a Mitochondrial amplicon analysis project in the NextGENe viewer, a Mitochondrial amplicon report, which is an application-specific report, is available. The report has visualization options that are specific for Mitochondrial amplicon analysis. A Reads Summary Alignment view, which is a view that details all the read information for all the alleles that were identified for a selected amplicon across all amplicons in the project, is also available.


Mitochondrial amplicon analysis data requirements

The Mitochondrial amplicon application type requires the mitochondrial Genbank reference file. You must also load a BED file that details the amplicon locations. See "To set ROI regions from a BED or GBK file" on page 58.

Mitochondrial Amplicon report

After you open a Mitochondrial amplicon analysis project in the NextGENe viewer, an MT Show Mitochondrial Amplicon Report option is displayed on the Report Selection icon. Select this option to open the Mitochondrial Amplicon report in addition to the Alignment view. The report has two sections. The top section is the *Amplicon report*, which shows the different amplicons that were analyzed along with associated information for each amplicon. The bottom section is the *Allele report*, which displays a row for each allele, by name, that was identified in the sample for a selected amplicon. Double-click any entry in the Amplicon report to update the display in the NextGENe viewer and the Allele report accordingly. You can also double-click any allele in the Allele report to change the focus of the display to the selected allele.





Field	Description
Amplicon report	
Amplicon	The name of the amplicon that was analyzed. Any amplicons that failed any of the Filter settings for the report are grouped into a row with Unknown displayed in this column. See "Mitochondrial Amplicon report" on page 189.
Amplicon Coverage	The total number of reads that were aligned to the amplicon.
Amplicon Percentage	Amplicon coverage/Total number of aligned reads.
Allele Number	The total number of alleles that were identified for the amplicon.
Allele Frequency	The number of reads that were assigned to each allele out of the number of reads that were assigned to all accepted alleles for the amplicon. (Shown as a percentage.)
	Note: Depending on the Filter settings that were specified for the report, these values might not be the same as the Frequency values in the Allele report. See "Mitochondrial Amplicon report" on page 189.
Allele Total Coverage	The total number of reads that are assigned to each allele.
Allele report	
Sequence	The sequence for the sample allele.
Start	The start position of the allele within the reference.
End	The end position of the allele within the reference.
Frequency	The number of reads that were assigned to the allele out of the total number of reads that were aligned to the amplicon. (Shown as a percentage.)
	Note: Depending on the Filter settings that were specified for the report, these values might not be the same as the Allele Frequency values in the Amplicon report. See "Mitochondrial Amplicon Report settings dialog box" on page 192.
Total Reads	The total number of reads that aligned to the allele.
Forward Reads	The number of reads that were assigned to the allele that were forward reads.
Reverse Reads	The number of reads that were assigned to the allele that were reverse reads.
Differences	The number of bases in the sample allele sequence that do not match the reference allele sequence.

By default, when the Mitochondrial Amplicon report first opens in the NextGENe viewer, it is displayed on the right side of the opened viewer, and the focus in the Alignment viewer is set to the first amplicon in the list of analyzed amplicons. A blue cross centered in the Alignment viewer indicates the position of the amplicon. The Allele report details the alleles that were identified for this first amplicon. You can click the Switch Report Layout icon on the NextGENe Viewer toolbar to indicate to indicate the location for showing the report (to the right or at the bottom of the NextGENe Viewer), or showing only the report (the Alignment Viewer is hidden), or hiding the report. The Mitochondrial Amplicon report is interactive. You can:

- Double-click on any amplicon to change the focus in the Alignment view to that of the selected amplicon. The Allele report display is updated accordingly.
- Double-click on any allele to change the focus in the Alignment viewer to that of the selected allele. A blue cross is displayed in the Alignment viewer to indicate the position of the selected allele on the locus.

Other options are available on the report toolbar. See "Mitochondrial Amplicon report toolbar" below.

lcon	Action
<i>m</i>	Display Reads Summary Alignment icon - Click this icon to open the Reads Summary Alignment view, which shows the differences in the alignment of the consensus sequences for all called alleles to the reference sequence for the selected amplicon. See "Reads Summary Alignment view" below.
×	Mitochondrial Amplicon Report Settings icon—Click this icon to open the Mitochondrial Amplicon Report Settings dialog box and specify the information that is to be displayed in the report. See "Mitochondrial Amplicon Report settings dialog box" on page 192.
=	Show/Hide Amplicon Report icon - Click this icon to toggle the display of the Mitochondrial Amplicon report in the NextGENe viewer.
=	Show/Hide Allele Report icon - Click this icon to toggle the display of the Allele report in the NextGENe viewer.
	Save Mitochondrial Amplicon Reports icon—Click this icon to open the Save Report as Text File dialog box, and save the Mitochondrial Amplicon report as a text (*.txt) file. By default, the report name is the project name appended with Mitochondrial and the report is saved in the same location as the project, but you can change one or both of these values.

Mitochondrial Amplicon report toolbar

Reads Summary Alignment view

On the report toolbar, click the Reads Summary Alignment icon to open the Reads Summary Alignment report, which shows the differences in the alignment of the consensus sequences for all called alleles to the reference sequence for the selected amplicon. An insertion is displayed in green, a deletion is displayed in red, and the different nucleotide is displayed for SNPs. (See Figure 6-48 on page 192.) The view is interactive:

- Change the display At the top of the view window, click the Next Amplicon and Previous Amplicon icons
 to move through each amplicon.
- Zoom In Hold down the left mouse button and draw a box from the upper left hand corner of any region in a graph towards the lower right hand corner. A box is formed around the area that being reduced for viewing.

• Zoom Out - Hold down the left mouse button and draw a box from the lower right hand corner of any region in the graph towards the upper left hand corner.




Figure 6-48: Reads Summary Alignment view

Reads	Summar	y Alignment (Ampl	icon02)							
44			-					_		
		M:16,000 16,020		M;16,100 6,080	M:16,150 16,140	M:16,200 16,200	M;16,250 16,280	M:16,300 16:320	M:16,350	M:16
						-e		e e e		-
5	=					-64		е е		

Mitochondrial Amplicon Report settings dialog box

On the report toolbar, click the Mitochondrial Amplicon Report Settings icon $\stackrel{\bullet}{\not\sim}$ to open the Mitochondrial Amplicon Report Settings dialog box and indicate the information that is to be displayed in the report. By default, all columns for the Mitochondrial Amplicon report and the Allele report are selected for display. Options that are unavailable (grayed-out) are applicable only for the STR analysis report.

Figure 6-49: Mitochondrial Amplicon Report Settings dialog box

implicon report display settings			Allele report display settings
Amplicon			Sequence
Amplicon Coverage			🔽 Maustred Allete Name
Amplicon Percentage			F Statue
			I Start
Allele Number			🔽 End
F Allele Name			Frequency
Allele Frequency			🔽 Total Reads
🔽 Allele Total Coverage			Forward Reads
T Allele Reicent Matched			Reverse Reads
		_	I Differences
ilter settings			
👿 Allów possible allele matarie:	-	_	
Maximum differences	20		
Minimum forward/reverse balance		%	
Minimum count	10	_	
Minimum frequency	5	%	



Optionally, you can also do either one or both of the following:

- Click Load Settings and browse to and select a Settings file (.ini file) to generate the Mitochondrial Amplicon report based on the saved settings in the file.
- Click Save Settings to save your settings for the report in a Settings file (.ini file). You can use this saved Settings file to generate the Mitochondrial Amplicon report for another project based on the settings in the file.

Setting	Description
Amplicon report displa	ay settings
Amplicon	The name of the amplicon that was analyzed.
Amplicon Coverage	The total number of reads that were aligned to the amplicon.
Amplicon Percentage	Amplicon coverage/Total number of aligned reads.
Allele Number	The total number of alleles that were identified for the amplicon.
Allele Frequency The number of reads that were assigned to each allele out of the n of reads that were assigned to all accepted alleles for the amplicor (Shown as a percentage.)	
Allele Total Coverage	The total number of reads that are assigned to each allele.
Allele report display se	ettings
Sequence/Length	The sequence for the sample allele.
Start	The start position of the allele within the reference.
End	The end position of the allele within the reference.
Frequency	The number of reads that were assigned to the allele out of the total number of reads that were aligned to the amplicon. (Shown as a percentage.)
Total Reads	The total number of reads that aligned to the allele.
Forward Reads	The number of reads that were assigned to the allele that were forward reads.
Reverse Reads	The number of reads that were assigned to the allele that were reverse reads.
Differences	The number of bases in the sample allele sequence that do not match the reference allele sequence.
Filter settings	
Maximum differences	If the number of differences between the sample allele sequence and the reference allele sequence exceeds the indicated value, then the allele is classified as Incomplete.
Minimum forward/ reverse balance	Indicates the balance for the #F/#R reads for the allele and vise-versa. For example, if set to 5%, then if there were 100 reverse reads for the allele, there must at least 5 forward reads for the allele, otherwise, the allele would be classified as Incomplete. The default value is zero, which means that there is no requirement for the Forward/Reverse balance.
	Note: Adjusting this setting can help reduce the rate of false positives.
Minimum count	The minimum number of reads that are required for an allele, otherwise, the allele is classified as Incomplete.

Setting	Description
Minimum frequency	The minimum value (expressed as a percentage) for the ratio of the number of reads for the allele to the total number of reads for the locus. If the frequency for the allele is does not meet or exceed this threshold, then the allele is classified as Incomplete.

HLA Project

You select the HLA application type to analyze Human Leukocyte Antigen (HLA) data or major histocompatibility complex (MHC) data from other organisms. You can also use the application type to review Sanger sequencing data that has been previously analyzed in Mutation Surveyor. An HLA analysis project has application-specific data requirements and alignment settings. When you open an HLA project file in the NextGENe viewer, the HLA report, which is an application-specific report is displayed. The viewer also has visualization options that are application-specific.

HLA analysis data requirements and project settings

An HLA analysis project has the following application-specific project requirements and settings:

- Load Data requirements:
 - Loading reference files The required reference files are the GenBank files for the HLA genes that are being targeted in the project. You can load multiple reference GenBank files for HLA genes.
 - Loading Sanger sequencing data If you are loading Sanger sequencing data that has been analyzed in Mutation Surveyor, then you must select Load MS HLA Mutation Report.

	Load data	Show Project Log>>	If you are loading Sanger sequencing
Step	E	t to fasta:	data that has been analyzed in Mutatio Surveyor, then you
Application	Sample files:	Load	must select Load MS HLA Mutation
		Remove	Report.
Load Dáta		RemoveAll	
Condensation	Reference files:		
	C:\Data\Demo_Data\HLA\Omixon\References\HLA-A_NC.gb C:\Data\Demo_Data\HLA\Omixon\References\HLA-B_NC_RC.gb	Load	
	C:(Data)Demo_Data)HLA)Omixon(References)HLA-C_NC_RC.gb C:(Data)Demo_Data)HLA)Omixon(References)HLA-DPA1_NC_RC.gb C:(Data)Demo_Data)HLA)Omixon(References)HLA-DPB1_NC_gb	Preloaded	
Resembly	C:\Data\Demo_Data\HLA\Omixon\References\HLA-DPB2_NC.gb C:\Data\Demo_Data\HLA\Omixon\References\HLA-DRB1_NC_RC.gb	Remove	
		RemoveAll	

Figure 6-50: HLA analysis, Load Data requirements

The required reference files are the GenBank files for the HLA genes that are being targeted in the project. You can load multiple reference GenBank files for HLA genes.

• Alignment settings:

Figure 6-51: HLA analysis, Alignment Settings

ect Wizard - Alig	nment	
		Show Project Log>>
Step	Load dictionary(*,fasta) or load NCBI XML(dbMHC_allelev(n.n).xml)	_
Application		Load
		Remov
Load Data		
	Coverage threshold	
Condensation	Minimum coverage 3	
	Percent coverage 50.0	
Assembly	Minimum read length 100	
	${\textstyle \textstyle $	
Alignment	Mutation filter	
Post Processing	✓ Check reads balance when mutation percentage < 20%	
	Default Settings Save Settings	Load Settings
	<< Back Next >> Cancel	Finish

Setting	Description
Load dictionary or load NCBI XML	You must load one of the following three dictionary files, where XML is the preferred format.
	Human - NCBI XML file for alleles.
	You can download an NCBI XML for human alleles from the ncbi database—ftp://ftp.ncbi.nlm.nih.gov/pub/mhc/alleles/.
	Non-human primate - EBI XML or FASTA file for alleles.
	You can download an XML or FASTA file for non-human primate alleles from the MHC/NHP database—ftp://fftp.ebi.ac.uk/pub/ databases/ipd/mhc/nhp/.
	HLA Dictionary .fasta file.
	You can download the HLA dictionary sequences from the IMGT/ HLA database—http://www.ebi.ac.uk/imgt/hla/.
Coverage Threshold - The cover	erage requirements to call alleles that are present in the sample data.
Minimum Coverage	The minimum number of reads that must cover an allele.
Percent coverage	The percentage of the gene that must be covered by reads for the allele to be called in the gene. You should set this value based on the region that is being targeted. For example, if you are targeting just exons, then this value should be less than 50%. (An acceptable value is 10%.) If you are targeting the whole gene, then this value should be greater than 50%. (An acceptable value is 90%.)
Minimum read length	Any read that does not meet or exceed the indicated threshold is not used for calling alleles.

Setting	Description
Align each sample file to only reference file	Select this option if you load a separate sample file for each gene that is being targeted.
Mutation filter	
Check reads balance when mutation percentage < 20%.	Selected by default. If the frequency of a variant is less than 20%, then the Read Balance is checked. If the reads for the variant are not balanced, then the variant is ignored and it is not used for allele calling.

HLA project report

After you open an HLA analysis project, the HLA Show HLA Report option is displayed on the Report Selection icon. Select this option to open the HLA-specific reports and display the project in the *HLA project view*. From top to bottom, the report has the following three sections: the HLA Summary report, the Allele Matching report, and the Allele Coverage report. (For a description of these report sections, see the table on the following page.)

Figure 6-52: HLA report

Index	Locus	Allele 1		Allele 2		Score		Coverage	Poor Co	vered Position	Mismatch	es Mismatche	s i Mismatch	ies i Syr	anym	
1	HLA-A	HLA-A A*01:0	1:01	HLA-A ATE	8.01:01	6.00,33.0	00	24172:2514	935,9		4,11	0,0	4:11	0,0		
2	· · · · · · · · · · · · · · · · · · ·		A-B_B*08:01:01		HLA-8_8-44.03:01		ŋ.	55309:3465	-		30	0,0	3:1	0:0		HLA
3	HLA-C	HLA-C_C'04.0	11:01	>HLA-C_C*C	7.01.01	1.00,0.00	0	99098,9182	7 33,9		1,0	0,0	1.0	0,0		Summ
4	HLA-DPB1	HLA-DFB1_D	PB1*138:01	>HLA-DPB1	_DPB1?68;01	125.70;8	19,70	10,3	468,261		17:13	17:13	0;0	2:1		
5	HLA-DRB1	HLA-DRB1_D	RB1*03.01:08	>HLA-DRB1	DRB1*07:01:01	121,90;1	31.90	103159;127	9 382,297		10,14	10:14	0,0	4,5	2.12	report
															×.	
	HLA-B_B100	3:01:01				A	liele2>1	HLA-B_B*44:03:	01		_			_		
ndex	2.1		Observed Ali Al	ele Balanci Direc	tional B Mutation Call A	_		Reference P(Pr	×	Observed A	Allele Bal	and Directions	BIMutation	CallAm	ing As	Allele
	-						-							-		Matchin
	9707		<u>G</u> 1	D	a,619+1226)	1		9707 C		ā	Ū	Na				report
2	9952	C	G 0.:	333 0.	c 620 1966>											•
¢ _							10									
Allele	HLA-B_B-08	3:01:01	-		-	A	liele2.>I	HLA-B_B*44:03:	01							
ndex	Reference	Position Gene	Coverage	Reference B	Zygosity All#F.#R	1 × In	dex	Reference Posi	tion Gen	e Cov	erage R	eference B-Z)	voosily A	(#E.#B)	1	Allele
	9701	HLA-B	4	1ã	Heterozygour 0;0	- 1	-	9701	HLA	8 1	G	H	omozygous 0	D		Covera
2	9702	HLA-B	4	A	Homozygous 0,4	2		9965	HLA	8 1	A	He	omozygous O	,t		report
3	9703	HLA-B	3	A	Homozygous 0:3	3		9956	HLA	8 1	G	H	omozygous 0	0		report
4	9704	HLA-B	3	Ť	Homozygous 0.0	4	111	9957	HLA	8 1	A	H	omozygous 0	1		
5	9705	HLA-B	3	6	Homozygous 0,0	5		9958	HLA-	8 1	A	H	enozygous 0	at .		
5	9706	HLA-B	3	G	Homozygous 0;0	6		9959	HLA	8 1	G	. He	eterozygour0	ø		
7	9707	HLA-B	3	C.	Homozygous 0:0	7		9960	HLA	8 1	T	He	omozygous 0	0		
3	9708	HLA-B	3	A	Homozygous 0,3	8	11	9961	HLA	8 2	C	н	eterozygou:0	,a		
9	9709	HLA-B	.3	T	Homozygous 0;0	9		9962	HLA	8 2	c	H	omozygous 0	a		
10	9710	HLA-B	3	Ġ	Homozygous 0,0	10	α	9963	HLA	8 2	C	He	eterozygcus0	a		
11	9711	HLA-B	3	A	Homozypous 0:3	11	1	10889	HLÁ	8 5	A	Ĥ	omozygous 0	5		
12	9712	HLA-B	.3	G	Homozygaus 0:0	12	2	10984	HLA	Ð 10	A	He	omozygous 0	10		
13	9713	HLA-B	3	T	Homozygaus 0,0	13	3	11327	HLA	8 10	G	н	omozygous Ö	,o		
14	9714	HLA-B	3	T	Homozypous 0:0	14	4	11328	HLA	в 9	G	He	omozygous 0	.0		
15	9715	HLA-B	3	1	Homozygous 0.0	15	5	11329	HLA	8 8	C	He	omozygous 0	.Q		
16	9716	HLA-B	3	T	Homozygous 0,0	16	6	11330	HLA	8 8	A	H	omazygous ()	8		
17	9717	HLA-B	3	c	Homozygous 0;0	17	7	11331	HLA	8 8	G	H	omozygous 0	o		
18	9718	HLA/B	3	C	Homozygoue 0.0	18	8	11332	HLA	8 B	A	He	omozygous 0	D		
19	9719	HLA-B	3	T	Homozygous 0:0	15	g	11323	HLA	8 8	6	. Ri	0 suogyseme	0		
20	9720	HLA-B	.3	6	Homozygous 0,0	20	0	11334	HLA	8 8	G	H	omozygous 0	,i		
21	9721	HLA-B	3	A	Homozygous 0;3	+ 21		11335	HLA	8 8	G		omozygous ()		-	
8						1.4									· · · ·	

Report Section	Description
HLA Summary	The HLA Summary report displays all the called alleles for the sample data as well as summary information for the alleles. If the sample is called as homozygous for the locus, then a pound sign (#) is displayed for the second allele. Double-click any entry in the HLA Summary report to update the display in the HLA project view and the two allele reports accordingly.
Allele Matching report	The Allele Matching report shows the mismatches for the consensus sequence for the sample data compared to the dictionary sequence for the gene and allele pair that is selected in the HLA Summary report. Double-click any position in the report to change the focus of the HLA project view to the selected position.
Allele Coverage report	The Allele Coverage report shows the low coverage positions (as defined in the Filter options in the report) for the gene and allele pair that is selected in the HLA Summary report. The report also show additional information about the alleles such as zygosity. Double-click any position in the report to change the focus of the HLA project view to the selected position.

The HLA report toolbar is interactive. The information that is displayed in the report sections as well as some of the information that is displayed in the panes of the HLA project view is determined by the settings that you have selected for the report. See "HLA report toolbar" below and "HLA Report Settings dialog box" on page 199.

HLA report toolbar

Five icons are displayed in the HLA Summary report toolbar.

lcon	Action
	Show/Hide HLA Summary report icon - Click this icon to toggle the display of the HLA Summary report in the NextGENe viewer.
=	Show/Hide Allele Matching report icon - Click this icon to toggle the display of the Allele Matching report in the NextGENe viewer.
	Show/Hide Allele Coverage report icon - Click this icon to toggle the display of the Allele Coverage report in the NextGENe viewer.
X	HLA Summary Report Settings icon - Click this icon to open the HLA Report Settings dialog box and specify the information that is to be displayed in the report. See "HLA Report Settings dialog box" on page 199.
	Save HLA Reports icon—Click this icon to open the Save Report as Text File dialog box, and save the HLA report as a text (*.txt) file. By default, the report name is the project name appended with HLA_Report and the report is saved in the same location as the project, but you can change one or both of these values.

HLA Report Settings dialog box

On the report toolbar, click the HLA Report Settings icon 🧩 to open the HLA Report Settings dialog box and indicate the information that is to be displayed in each of the report sections as well as information that is displayed in some panes of the HLA project view. You can also elect to save the different report sections as a text file. See:

- "HLA (Summary Report) Settings tab" below.
- "Allele Matching Report Settings tab" on page 201.
- "Allele Coverage Report Settings tab" on page 203.
- "Output Settings tab" on page 204.

Figure 6-53: HLA Report Settings dialog box, HLA Settings tab

ummary display			
🔽 Sample	₩ 0	Coverage	Mismatches
V Locus	₩ F	oor Covered Position	I▼ Mismatches In EDS
i⊽ Allele 1	₩ 4	minio Acid Change	Mismatches in Non-Coding Regions
Allele 2	₩ 9	iubstitutions	I▼ Synonymous Mismatches in CDS
Score	V 1	ndels	Vinmatched Reads Count
2 group result 3 group result 4 group result		⊂ 2 allele ⊂ 3 allele ⊙ All alle	



Optionally, you can also do either one or both of the following:

- Click Load Settings and browse to and select a Settings file (.ini file) to generate the HLA report based on the saved settings in the file.
- Click Save Settings to save your settings for the report in a Settings file (.ini file). You can use this saved Settings file to generate the HLA report for another project based on the settings in the file.

HLA (Summary Report) Settings tab

Setting	Description			
Summary display				
Sample	The sample ID.			
Locus	The HLA locus on which the alleles are located.			

Setting	Description
Allele 1	HLA alleles for the reported genotype.
Allele 2	Note: The values that you have specified for the Type Precision determine the naming scheme that is displayed for the alleles. See Type Precision.
Score	The likelihood that the genotype for the two alleles is the correct genotype.
	Note: The closer that the score is to zero, the greater the likelihood that the genotype is the correct one.
Coverage	The number of reads that mapped to the locus.
Poor Covered Position	Number of poor covered positions for the allele based on the Allele Coverage report filter settings. See "Allele Coverage Report Settings tab" on page 203.
Amino Acid Change	The number of mismatches in that are located in the coding regions that result in an amino acid change.
Substitutions	The number of mismatches that are substitutions.
Indels	The number of mismatches that are indels.
Mismatches	The number of mismatches in the sample data as compared to the dictionary sequence.
Mismatches in CDS	The number of mismatches that are located in the coding regions.
Mismatches in Non-Coding Regions	The number of mismatches that are located in the non-coding regions.
Synonymous Mismatches in CDS	The number of mismatches that are located in the coding regions that do not result in an amino acid change.
Unmatched Read counts	The number of reads that align to the gene but don't match to the consensus sequences for either of the selected alleles. Displayed in the Unmatched Reads pane for the HLA project view. See "Unmatched Reads pane" on page 207.
always the Gene Name one of the following diffe	s how to display the allele names in the HLA Summary report. The name is followed by up to four separate codes, each of which are representative of rent allele characteristics/properties - Serotype, Amino Acid Differences, s, and Non-coding Differences.
Figure 6-54: Type p	recision for allele naming
	Groups 1 through 4

			Groups	1 through 4	1	
	Gene	Serotype	Amino Acid Differences		Non-coding Differences	
HL	-A-C [*]	^{<} 07	02:	01:	03	
2 group result	Show Ger	ne, Serotyp	be, and Ami	ino Acid Di	fferences.	
3 group result	Show Ger Difference	, JI	be, Amino A	Acid Differe	nces, and S	Synonymous
4 group result			be, Amino A -coding Dif		nces, Syno	nymous

Setting	Description
Allele pairs	
1 allele result	Display the sample data (top allele pair) that was the best matched to the dictionary data for the selected gene.
2 alleles result	Display the sample data (top two allele pairs) that was the best matched to the dictionary data for the selected gene.
3 alleles result	Display the sample data (top three allele pairs) that was the best matched to the dictionary data for the selected gene.
All alleles result	Display the sample data (top four allele pairs) that matched to the dictionary data for the selected gene.

Allele Matching Report Settings tab

Figure 6-55: HLA Report Settings dialog box, Allele Matching Report Settings tab

IV Reference Base IV IV Predicted Allele Base IV IV Dbserved Allele Base IV IV Allele Balance IV IV Allele Balance IV IV Directional Bias IV IV Mutation Call IV	A(#F / #R) C(#F / #R) G(#F / #R) T(#F / #R) Deletion(#F / #R) Insettion(#F / #R) Amino Acid Change	- Inse	l tion(%)	A Scare E Scare G Scare G Scare T Scare Deletion Scare Insertion Scare
IF Reference Base IF IF Predicted Allele Base IF IF Dbserved Allele Base IF IF Allele Balance IF IF Directional Bias IF IF Mutation Call IF	C(#F / #R) G(#F / #R) T(#F / #R) Deletion(#F / #R) Insertion(#F / #R)	□ C(%) □ G(%) □ T(%) □ Dele □ Inse	l tion(%)	E.Score G Score T Score Deletion Score
Image: Predicted Allele Base Image: Predicted Allele Base Image: Diserved Allele Base Image: Predicted Allele Base Image: Predicted Allele Base Image: P	G(#F/#R) T(#F/#R) Deletion(#F/#R) Insertion(#F/#R)	〒 G(%) 〒 T(%) 〒 Dele 〒 Inse	l stion(%)	☐ G Score ☐ T Score ☐ Deletion Score
IV Dbserved Allele Base IV IV Allele Balance IV IV Directional Bias IV IV Mutation Call IV	T(#F / #R) Deletion(#F / #R) Insertion(#F / #R)	T T(%) Dele Inse	tion(%)	☐ T Score ☐ Deletion Score
I⊽ Allele Balance I⊽ I⊽ Directional Bias I⊽ I⊽ Mutation Call I⊽ A	Deletion(#F / #R) Insertion(#F / #R)	∏ Dele ∏ Insei	tion(%)	C Deletion Score
I Directional Bias I I Mutation Call I	Insertion(#F / #R)	- Inse		
🗭 Mutation Call 🔽			rtion[%]	☐ Insertion Score
Mutation Call Filter options	Amino Acid Change			
Filter options				
V Display mismatches only	statistics: Allele balance 50 Directional bias 50	*	Ĩ	annolation: Substitutions Voncoding Synonymous Missense Vonsense Indels

Setting	Description
Display Options	
Reference Position	The reference position where the mismatch occurs.
Reference Nucleotide	The nucleotide in the GenBank file at the reference position.
Predicated Allele Nucleotide	The nucleotide in the dictionary file for the selected allele at the reference position.
Observed Allele Nucleotide	The nucleotide in the consensus sequence for the sample data at the reference position.
Allele Balance	The variant frequency in the sample data at the reference position.
Read Balance	The read balance for the variant. Note: This value is identical to the value that is calculated for Balance Ratios and Frequencies in the Alignment settings. See "File Type settings" on page 138.
Mutation Call	The change (variant call) that occurs at the variant position.

Setting	Description
A(#/F / #R), C(#/F / #R), G(#/F / #R), T(#/F / #R)	The actual number of reads that show the indicated base at the variant location in the forward direction and the actual number of reads that show the indicated base at the variant location in the reverse direction.
Deletion (#F / #R)	The actual number of reads that show a deletion at the variant location in the forward direction and the actual number of reads that show a deletion at the variant location in the reverse direction.
Insertion (#F / #R)	The actual number of reads that show an insertion at the variant location in the forward direction and the actual number of reads that show an insertion in the reverse direction at the variant location.
A(%), C(%), G(%), T(%)	The percentage of reads that show the indicated base at the variant location.
Deletion(%)	The percentage of reads that show a deletion at the variant location.
Insertion(%)	The percentage of reads that show an insertion at the variant location.
A Score, C Score, G Score, T Score	Essentially an allele balance score for each individual allele. It is scaled to be similar to the Overall Mutation score, but it does not contribute to the overall score.
	 If the allele F/R ratio is > 3 x the F/R ratio for all the reads at the indicated position, or is < 1/3 x the F/R ratio for all the reads at the indicated position, then the score for the allele is zero.
	 If the position has no calls that correspond to the indicated allele, then the score for the allele is again zero.
	 Otherwise, the score is calculated based on the F/R ratio for the allele and the F/R ratio for all the reads at the indicated position. The closer that these two values are, then higher the allele score. The maximum allele score for any allele is 27.
Deletion Score	For deletion alleles. See the description for A Score, C Score, G Score, T Score.
Insertion Score	For insertion alleles. See the description for A Score, C Score, G Score, T Score.
Filter Options - All options a	are selected by default.
Note: If you change any va all tabs to their defau	alue on this tab, at any time, you can click Default to return all values on It values.
Display mismatches only	Display the mismatches for the consensus sequence for the sample data compared to the dictionary sequence for the allele pair that is selected in the HLA Summary report. Clear this option to show both matches and mismatches.
Filter by statistics	
Allele Balance Read Balance	 The Allele Balance is identical to the Allele Frequency. (See "Allele Frequency" on page 193.) Display only those alleles that have an allele balance ≥ the indicated threshold. The default value is 0.5.
	 Display only those alleles that have a Read Balance ≥ the indicated threshold. The default value is 0.5.

Setting	Description
Filter by annotation	
 Substitutions Noncoding Silent (in CDS) Missense Nonsense/No-stop 	• By default, show the mismatches for the consensus sequence for the sample data compared to the dictionary sequence if the mismatch occurs for a position that is annotated as the indicated substitution type. Clear the options for the substitution types that are not to be displayed in the report.
• Indels	• By default, show the mismatches for the consensus sequence for the sample data compared to the dictionary sequence if the mismatch occurs for a position that is annotated an insertion or deletion. Clear this option if indels are not to be displayed in the report.

Allele Coverage Report Settings tab

Figure 6-56: HLA Report Settings dialog box, Allele Coverage Report Settings tab

Settings Allele Matching Report	settings j	Allele Coverage Re	pon	Settings Out	put j
Display options			_		
I Reference Position	17	A(#F / #R)	Ē	A(%)	T A Score
🔽 Gene	1	C(#F / #R)	Г	C(%)	C Score
I Coverage	V	G(#F / #R)	Ē	G(%)	IT G Score
☑ Reference Base	R	T(#F / #B)	Г	T(%)	T T Score
V Zygosity	V	Deletion(#F / #R)	Г	Deletion(%)	T Deletion Score
🐼 Mutation Call	V	Insertion(#F / #R)	Г	Insertion(%)	T Insertion Score
🐼 Amino Acid Change					
Filter options					
Coverage display threshold:	1	Zygosity:			
Min coverage:		Heterozygous th	rest	blo	
A restored a la		20 %			
		🔽 Homozygou	2		
		₩ Heterozygou	IS		
	-	1.			


Setting	Description
Display Options	
Reference Position	The reference position where the mismatch occurs.
Gene	The gene that is selected in the HLA Summary report.
Coverage	The number of reads that mapped to the locus in the sample data.
Zygosity	The zygosity of the alleles (heterozygous or homozygous) in the sample data for the selected gene.
Reference Nucleotide	The nucleotide in the GenBank file at the reference position.
Mutation Call	The change (variant call) that occurs at the variant position.
Amino Acid Change	The number of mismatches in that are located in the coding regions that result in an amino acid change.

Setting	Description
Filter Options	
Note: If you change any all tabs to their de	value on this tab, at any time, you can click Default to return all values on fault values.
Coverage Display Thres	shold
Min Coverage	The minimum coverage required for a position to be called as a low coverage position and included in the report.
Zygosity	The zygosity of the variant at the reference position.
 Heterozygous threshold 	 The requirements for a location to be considered heterozygous. More than one nucleotide must observed above the indicated threshold (the default value is 20%) for the location to be considered heterozygous.
Homozygous	 Display the variants of the indicated zygosity in the report.
Heterozygous	

Output Settings tab

By default, all three sections of the HLA report are saved as text files in the project Output folder. You must clear the options for the reports that you do not want to save.

Figure 6-57: HLA Report Settings dialog box, Allele Coverage Report Settings tab



HLA project view

After you open an HLA analysis project, a third option—HLA Show HLA Report—is available on the Mutation Report/Summary report toggle. Select this option to open the HLA report and to display the project in the *HLA project view*.




Figure 6-58: HLA project view (HLA report hidden)

From top to bottom, the HLA project view has the following visualization options for a gene and allele pair that is selected in the HLA Summary report:

- Reference/Dictionary Sequence pane. See "Reference/Dictionary Sequence pane" on page 206.
- Top Allele Pair Matches pane. See "Top Allele Pair Matches pane" on page 206.
- Consensus Sequence panes. See "Consensus Sequence panes" on page 206.
- Unmatched Reads pane. See "Unmatched Reads pane" on page 207.

Reference/Dictionary Sequence pane

The Reference/Dictionary Sequence pane displays the reference sequence and its serologic equivalents for the selected gene. Positions that are not conserved among the different alleles are highlighted in yellow. Positions that are conserved among the different alleles are not highlighted. IUPAC lettering is used for the variable positions.

Figure 6-59: Reference/Dictionary Sequence pane



Top Allele Pair Matches pane

The Top Allele Pair Matches pane displays the sample data (allele pair) that was the best matched to the dictionary data for the selected gene. The pane shows the name and the dictionary sequence for each allele in the pair. The number of allele pairs that are displayed in this pane is determined by the value (1, 2, 3, or All) that is specified for Allele pairs in the HLA Report Settings dialog box. (See "HLA Report Settings dialog box" on page 199.)

Figure 6-60: Top Allele Pair Matches pane

B*08:01:01	Ť	G	G	Ċ.	¢	c	Ť	G	A	C	¢.	Ģ	A.	Ģ	A	¢	¢	T	Ģ	G	G	Ç.	¢	Ģ	G	Ť	Ģ	A	G	T	Ģ	C	Ģ	Ģ	G	T	C	G	Ĝ
B*44:03:01	T	G	G	ç	¢	¢	T	G	a	c	ċ	Ģ	Ŗ	Ģ	A	¢	¢	1	Ģ	Ģ	G	¢	c	Ģ	G	Ĵ	G	д	Ģ	Ť	Ģ	ċ¢	Ġ	Ģ	G	Ŧ	c	G	Ģ

Consensus Sequence panes

The Consensus Sequence panes displays the consensus sequence for each allele in the gene and allele pair that is selected in the HLA Summary report. The reads for each allele that resulted in the consensus sequence are displayed below the consensus sequence.

Figure 6-61: Consensus Sequence panes

Consensus	Ľ	G	G	C A	c	С	ť	Q	A	C T	c	G	A E	G	A	C T	¢	T	0 W	G	G	C A	c	0	G	T	0	A	G	T	G	c	G	G	0	T	C	0	G
5 Allele1 10	TTTTTTTTTTT	000000000000	000000 100000	0000000000000	000000000000	0000000000000	TTTTTTTTTTT	0000000000000	AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA	0000000000000	0000000000000	000000000000	~~~~~~~~~~~	000000000000	4444444444	0000000000000	0000000000000	TTTTTTTTTTT	000000000000	0 0 0 000	0 0 000	0 0 000	0000000000000	0 00000000	0 000000000	TTTTTTTT	00000 000000	AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA	000000000000	********	0000000000000	0000000000000	0000000000000	0000000000000	000000000000		0000000000000	000000000000	00000000000
Consensus	T V	G	G	C A	¢	c	L	Ģ	A.	C T	¢.	G	AE	G	A	¢ τ	c	Ţ	G W	G	G	C A	C	G	G	Ţ	G	A	G	T	G	CG	G	G	G	T	¢	G	G
5 Allele2		000000	000000	000000	000000	000000	TTTTT	000000	AAAAA	000000	000000	000000	444444	000000	44444	000000	000000	TTTTT	000000	0 00	0 00	0 00	000000	00 0	00 0	T T T	000000	44444	000000		000000	0000000	000000	000000	000000	TTTTT	000000	000000	000000

Unmatched Reads pane

The Unmatched Reads pane displays the reads that were assigned to the selected gene, but did not match to any of the consensus sequences that are displayed in the Consensus Sequence pane.

Figure 6-62: Unmatched pane

Unmatched	00	GG	CC .	4 0		00	00	00	G A	00	Ţ	Ŧ	Ţ	ł	AA	AA	AA	00	ł	-
or and conord	1.0		.21	3 0	T.	C	C	C	A	G	Т	T	C	1	A	A	A	G	T	-
			51	9 G	T 1	C	C	C	A	G	T	T	C	τ	A	A	A	G	1	
5				3 G	T.	C	C	C	A	G	T	Т	C	T	A	A	A	G	T	
			51	3 G	C	C	C	C	A	G	Т	Т	C	T	A	A	A	G	T	
			30.5	3 G	T	C	C	C	A	G	T	T	C	τ	A	A	A	G	T	
			>	3 G	T	C	C	C	A	G	T	Т	C	T	A	A	A	G	7	
			34.3	3 G	T	C	C	C	A	G	T	Т	C	T	A	A	A	G	T	
10				3 G	1	0	C	C	A	G	T	T	C	T	A	A	A	G		
10			20	3 0	T	Ĉ.	ć	ć	A	G	T	Ť	C	T	A	A	A	G	T	
			20 A A	3 G	T	C	G	C	A	G	T	T	C	T	8	A	A	G	T	
			2.1	3 0		Č.	Č.	ċ	A	G	Ť	Ť	ċ	Ť	A	A	A	G	Ť	
			2	3 6		C.	Ċ.	C	A	G	T	Ť	C	Ť	A	A	A	G	Ť	
			2 2	3 0		ĉ	ĉ	ċ	A	G	T.	Ť	ĉ	Ť	A	A	4	G.	÷.	

Sequence Alignment Project Output Files

When you complete an alignment project (either for single sequence reads, for paired end/ mate paired data, or transcriptome data), output files are created that provide detailed information about the analysis.

File	Description
*.Pjt	This is the file that is loaded in the NextGENe Viewer when the project is complete to allow review of the analysis results.
_Parameters.txt	This file contains information about the settings that were used for the project. If condensation was carried out as preliminary step and then alignment was carried out as part of the same project, then a _Parameters.txt file is created that contains the settings for all the project steps.
_StatInfo.txt	 This file provides basic information and various statistics about the assembly process. Basic information: The general steps that were used Process times Sample file names and output file names Statistical information: The respective counts for matched and unmatched reads Average read length Coverage Total number of covered bases for the reference The username for the user who ran the analysis if User Management is turned on Note: The average coverage is calculated according to the following (which therefore excludes zero coverage regions): (No. of aligned bases)/(Total no. of covered bases)
unmatched.fasta unmatched.csfasta	This file contains all the reads that did not match to the reference file. You can use this file further analysis of your samples.
Paired Data output only	
_Arranged.fasta _Arranged.csfasta	 When carrying out a paired read analysis, NextGENe first scans the sample files to determine if the reads are arranged in the files. If the reads are arranged, then no arranged files are created; otherwise, NextGENe arranges the sample files so that the paired reads are in a similar order in both files, and then saves these arranged reads in an arranged file in either a .fasta format or a csfasta format. Going forward, you can use these arranged files for analysis. Note: The Sequence Operation Tool contains an option for arranging paired read sample files. If you use this option to arrange the reads in your sample files <i>before</i> you carry out the alignment, then NextGENe skips the step of arranging the sample files. See "The NextGENe Sequence Operation Tool" on page 366.

File	Description
MateStatus.txt	Contains information that was gathered about the paired reads during the arrangement of the reads.
unmatched_paired.fasta	Contains both unmatched reads and the pair to any unmatched reads (whether matched or unmatched) to maintain the paired read file structure.

Sequence Alignment Project Mutation Report

When you complete a sequence alignment project, (either single end sequence data, paired reads/mate paired data, or transcriptome data), the Sequence Alignment project Mutation report, or simply, the Mutation report, is *automatically generated* for an alignment project but it is *not* automatically displayed. While in the default alignment view, you must click the Switch Report Layout icon indicate the location for showing the report (to the right or at the bottom of the NextGENe Viewer), or showing only the report (the Alignment Viewer is hidden), or hiding the report.

ile Proce	ss Paire	d View Re	ports Se	earch To	ools Co	omparisor	ns Help															
; 🔲	Mutation	Call 👻	⇐ 📣	1	- 101 ·	- 🗟	ж.															
		,50K	.100	к	,150K		,200K		.250K	.300K		.350K		.400K	.43	50K	.500K		.550K	.600K		.650K
									- II				1				1			T		1
_																						
-#		ł.	188	H:		11 I	11#	t I			1 11				t t				1 I I		1 11:11	
ų in the second se	10,100K	1:10,0	50K	1:10,000		1:9,950K	1:9,9	niumi oor	1:9,850K		1:9,800K		L:9,750K	1:9,7	DOK.	1:9,650K	1.0	,600K	1:9,55	OK	L:9,500K	i.
		1:10,0	SUK	1:10,000	K .	1:9,930K	1:9,5	UUK	1:9,0000		1:9,000K		1:9,750K	1:9,7	UUK	1:9,030K	1:9	JOUUK	1:9,55		1:9,300K	
€ `	ə .	/																			Zoo	m 🕅
														USH2A								
Translati	n s	s	L	1510 P	А	L	м	т	1515 T	м	м	K	G	152 I	R	F	I	G	1525 N	G	¥	с
	c	s	L	P	A	L	м	A	т	м	м	K	G	I/1			I	G/		G	Y	s
NP db_xr	of																					
R																						
itation Ca		1.1.1	1.		1.1	1.1		1					1	1.1	Г I	1.1.1.1	1	1.1	1.1.1.1	1	1	1
	1.9.8	66,480		1-9	,866,4	70		1-9.8	66,460		1-9	,866,45	50		1:9,866	440		1-9.5	866,430		1:9,8	66 4
Reference	e CA		ТАС						CACGI	TG							ата			GGG		
Consens	IS G C	TGC	- A C	CA (G	G	A T G	GC	CACGA	TG	A T G	A A	A GAG	AACAATT C	T CA/C	A A/CATCACC	A TGA	C/Œ/G	TA/GA/CA	GGA	TGACA T	A G
Pile-		тстс				G			CACGI							AATC			_	_		_
		G C T C T C		CAC			ATGATG		С А С G Л С А С G Л										TACA			A G
	G	СТС	A A	CAO	G	G	A T G	G C	CACGA	TG	A T G	A A	A GAG	A AAT	CA	A TCATCAC	A TGA	G G	TACA	GGA	TGG. T	
	ς G C	тс	AC	CA	G	G	ATG		CACGI	LTG	ATG	AA	A GAG	AART	CCA	A TOATORC	A TGA	GG	TACA	GGA	IGO. T	A G
			_																			
ır (All		•	Gene A			•																
age 1 of 1	First<< F	Previous< 1	>Next >	>Last	to Page	1	Go															
	~	-	~	_			_		Jutation Call:					~	-				Amino Ac	-	-	_
dex	Chrom	Pos	Cove	erage Ri	er	Alt%	Overa	F	Relative To C	DS				Gene	Exon	CDS	dbS	SNP	Change	Phase ID	Phase	De
	1	9866444	62	G		91.94	11.3	C.	4555_4556in	sA				USH2A	21	20			p.G1519de			
	1	9866442	61	А		50.82	0.6	C.	4558_4559in	sCA				USH2A	21	20			p.I1520deli			
	1	9866441	61	т		42.62	0.7		4558_4559in					USH2A	21	20			p.11520deli			
	1	9866438	59	G		50.85,44	.070.0	C.	4562G>AC					USH2A	21	20			p.R1521HF			
	1	9866436	59	т		47.46	0.2	C.	4564T>AT					USH2A	21	20			p.F1522IF			
	1	9866435	57	т		45.61	0.2	C.	4564_4565in	sCA				USH2A	21	20			p.F1522de			
	1	9866434	57	С		45.61	0.2	C.	4567_4568in	sCCA				USH2A	21	20			p.F1522_l1			
	1	9866431	56	A		82.14	4.3	C.	4568_4569in	sG				USH2A	21	20			p.I1523deli			
	1	9866430		G		38.89	0.0		4570G>CG					USH2A	21	20			p.G1524R(
		0000400				07.70	0.7		4534.0.00					1001004	0.1				0150447			

Figure 6-63: Mutation Report displayed at the bottom of the NextGENe Viewer

The Mutation report lists each variant in order of their sequence position. Purple text indicates reported variants. Blue text indicates novel variants. Gray text indicates variants that were automatically or manually deleted. *By default*, the Mutation report always displays certain information for the variants that are included in the report, but you can always modify the information that is displayed. (See "Mutation Report settings" on page 213.)

The report is interactive.

- Double-click a point in the report to move the Alignment Viewer to the corresponding location where you can view the reads for the position.
- Double-click a variant call in the Alignment Viewer to move the report to the corresponding location. The entire row for the variant is highlighted in yellow in the report.

• Right-click a variant call in the report to open a context menu that provides various options for working with the selected variant. You can also click Search in this context menu to open a Search dialog box in which you can enter options for searching for specific information in the report, and if you have a subscription to Pathway Studio, an option is available for viewing the biological pathway information for the gene where the variant is located in Pathway Studio.

Figure 6-64:	Context menu for a variant call in the Mutation report
1 iguio 0 0 i.	Context mona for a vanant ban in the matation report

Search	
Delete	Ctrl+D
Undo Deletion	Ctrl+R
Confirm	Ctrl+M
Undo Confirmation	Ctrl+N
Undo	
View Edit History	
Сору	Ctrl+C
View in Pathway Studio	

Option	Comment
Search	Opens a search dialog box with the field to search determined by the column from which you selected the option. For example, if you opened the search from the Gene column, then the Search Gene dialog box opens. If you open the search from the Chr (chromosome) column, then the Search Chr dialog box opens. Regardless of the dialog box that opens, the search criteria (Options, Direction, and Scope) are always the same. You use the options on this dialog box to search the Mutation report for the first occurrence of the search string that meets all the search criteria. You use the Next button to move through all the search results. <i>Figure 6-65: Search Mutation Call dialog box</i>
	Search: Mutátion Call: Relative To CDS
	Iext to find
	Options Direction Scope © Ease sensitive © Forward © Present page only © Whole words only © Backward © All pages
	Next Cloge
Delete	Click this option to remove a variant call for a position. Although the position is no longer called a variant, the sequence of the reads is not changed. Note: To view a deleted variant in the Mutation report, you must select
	"Deleted" on the Filters tab on the Mutation Report Settings dialog box. The deleted variants are highlighted in gray and the Comments column displays "Deleted" for each variant. See "Filter tab, Annotation sub-tab" on page 223.


Option	Comment
Undo Deletion	Undoes a selected manual deletion. The position is again called a variant.
Confirm	Click this option to select variants in which you have a high degree of confidence.
	Note: To view a confirmed variant in the Mutation report, you must select "Confirmed" on the Filters tab on the Mutation Report Settings dialog box. The confirmed variants are displayed in black text in the Mutation report and the Comments column displays "Checked" for each variant. See "Filter tab, Annotation sub-tab" on page 223.
Undo Confirmation	Undoes the manual confirmation of a selected variant.
Undo	Undo the last edit action that was carried out for the variant.
View Edit History	Available only if User Management is turned (see "Configuring User Management" on page 31) and only after at least one edit action (for example, Deletion) has been carried out for the variant call. Opens the Edit History dialog box, which displays all the edit operations that have been carried by all users for the selected variant. See "Viewing the Edit history for a variant" on page 213.
Сору	Copies the selected text in the cell to your clipboard. To copy text in a range of cells, click and hold the left mouse button and drag the mouse to select the region that you want to copy. Use standard keyboard commands or menu commands to paste the copied text into an application.
	Note: You can also copy the Mutation report as an image. Press and hold the [Shift] key and the [Ctrl] key and then click and hold the left mouse button and draw a box around the region of the image that you want to copy. The selected region is filled with black. Right-click and Copy as Picture to copy the selected region as an image to your clipboard. Use standard keyboard commands or menu commands to paste the copied image into an application.
View in Pathway Studio	If you have a subscription to Pathway Studio, then select this option to import the gene where the variant is located into Pathway Studio and visualize the biological pathway information for the gene.
	Note: Before you can use the Mutation report in conjunction with Pathway Studio, your Pathway Studio access option must be set for the NextGENe Viewer. See "Process" in "NextGENe Viewer main menu" on page 142.

To save the Mutation report, on the NextGENe Viewer main menu, click Reports > Mutation Report > Save Mutation Report. A dialog box opens in which you can specify both the location and the name for the saved report. The report is saved as a tab-delimited text (*.txt) file. After you save the Mutation report, the date and time that the report was saved as well as your username are added to the audit trail for the project in the ReportEditHistory.log file. This log file is saved in an AuditTrail folder in the <Project Name>.files folder for the appropriate project; for example:

 $Illumina \\ Haloplex \\ Alignment \\ 2.4.0.1 \\ D_Output \\ D_Output.files \\ AuditTrail$

Viewing the Edit history for a variant

Any edit action (addition, deletion, or confirmation) that you carry out for a variant is reflected in the font color and the Comments column for the variant in the Mutation report. This action is also automatically added to the audit trail for the variant. To view the edit history for a variant, right-click the variant in the Alignment viewer or in the Mutation report, and on the context menu that opens, click View Edit History to open the Edit History dialog box. The lower half of the Edit History dialog box displays all the edit operations that have been carried for the selected variant. The date and time and the username for the user who carried out the edit is displayed for each edit. When you select an edit entry in the lower pane, a selected series of old and new values is displayed in the upper half of the dialog box. If the edit resulted in a change for a variant value, then the old and new values are highlighted in red.



Current / Old	Values:								
	Mutation Position	Gbk Base	Mutation Call	Insertion Base(s)	Comments	Coverage	A#F	A#R	C#F
Current Value	1996	C	c.73+26C>CG		< <deleted></deleted>	9224	1	12	1324
Did Value 1996 C		C	c.73+26C>CG			9224	1	12	1324
4 🗌					-				
Edit History L	ist								
12	lit Time	Le au		Long.	0.0		Module		Recover
	22/2015 10:51-43	AM Spec	uter trumWriting	User Administrator	Operati Delete	on	Module		Hecove
						on	muuue		necuve
						'n	mooue		TROUVE
						'n	Mudue		TRECIVE

Mutation Report settings

While in the default alignment view, three options are available for specifying the information that is to be displayed in the Mutation report.

- General settings. See "Mutation Report Settings dialog box" on page 214.
- Gene tracks settings. See "Gene Tracks Settings dialog box" on page 240.
- Variation tracks settings. See "Variation Tracks Settings dialog box" on page 232.



For information about importing variation databases and/or gene tracks into a sequence alignment project, see the Reference & Track Manager Tool User's Manual or Online Help.

Mutation Report Settings dialog box

The Mutation Report Settings dialog box contains the options for the general settings for the Mutation report. To open the Mutation Report Settings dialog box, do one of the following:

- On the NextGENe Viewer main menu, click Reports > Mutation Report > Mutation Report Settings.
- On the NextGENe Viewer toolbar, click the Report Settings icon 🔂.

The dialog box contains four primary tabs—the Display tab, the Filter tab, the Summary Report tab, and the Output tab. The Display tab is always the tab that is opened when the dialog box opens. The Display tab and Filters tab both have associated sub-tabs. You can specify the general settings for generating the Mutation report on these tabs and sub-tabs, or you can click Settings > Load from file to load any general Settings file that has been saved for a Mutation report and generate the report according to the settings in the file.

Figure 6-67: Mutation Report Settings dialog box, Display tab

isplay Filter Su	ummary Report	Output			
Annotation Statisti	ics Phasing				
Basic					
Chrom	Pos		Contig	Contig Pos	Ref Pos
Ref	Alt		🔲 Genötype	Zygosity	
Gene					
👿 Gene	Trans	Туре	Trans. Accession	Strand	
Exon	CDS		🔲 Gene Ref	🔲 Gene Alt	
Protein		Mutation	n Call	Reference	e Database ID
Protein Ac	2251210		enomic	🕑 dbS	NP
E Function	i change	B	elative to CDS elative to mRNA	Miscellan	eous
			GVS Genomic	🔲 Sho	w all transcripts
			GVS Coding	Com	ments
		-	GVS Protein		
		Fo	orensic (SWGDAM mtDN/	4)	

Tab	Description
Display	The active tab when the Mutation Report Settings dialog box first opens. The settings on the Display sub-tabs determine the numerous columns that can be displayed in the Mutation report based on the information that is required for the project and the information that is included in the reference sequence.
Filter	The settings on the Filter sub-tabs determine what kinds of variants are displayed in the report.
Summary Report	The settings on the Summary Report tab determine how the Mutation report is displayed if it is included in the Summary report. (See "Summary report" on page 246.)
Output	The settings on the Output tab determine the additional formats (SIFT and VCF) in which the Mutation report can be saved and what type of consensus sequence is to be saved.

After you specify the general settings on the various tabs for a Mutation report, you can click Settings > Save to file to save the general settings to a Settings (.ini) file. You can select this saved general Settings file for post-processing options in:

- The Project Wizard. See "To specify the post-processing options for a Sequence Alignment project" on page 64.
- The NextGENe AutoRun Tool. See Chapter 9, "The NextGENe AutoRun Tool," on page 391.
- The Summary report. See "Summary report" on page 246.




If you decide that you want to return all the settings on all the tabs to their default values in a single step, then click Settings > Default.

For a detailed discussion of the options that are available on each tab and sub-tab, see:

- "Display tab, Annotation sub-tab" on page 216.
- "Display tab, Statistics sub-tab" on page 219.
- "Display tab, Phasing sub-tab" on page 221.
- "Filter tab, Annotation sub-tab" on page 223.
- "Filter tab, Bias sub-tab" on page 225.
- "Filter tab, Score sub-tab" on page 226.
- "Filter tab, ROI sub-tab" on page 228.
- "Summary Report tab" on page 230.
- "Output tab" on page 231.

Display tab, Annotation sub-tab

Figure 6-68: Mutation Report Settings dialog box, Display tab, Annotation sub-tab





If a column is an annotation column, then the column contains information only if an annotated reference sequence (a GenBank file or a preloaded reference with annotation) is used and only within regions of the reference where a coding sequence is annotated.

Setting	Description
Basic	
Chrom	Selected by default. The name of the chromosome where the variant occurs.
Pos	Selected by default. The nucleotide position in the chromosome where the variant occurs.
Contig	Identifies the contig (segment of the reference) where the variant is located.
Contig Pos	Position on the contig (segment of the reference) where the variation occurs.
Ref	Selected by default. The reference nucleotide at the variant position.
Alt	The alternate (variant) nucleotide at the variant position.
Genotype	The genotype for the aligned reads at this position. Indicates whether the variant is homozygous or heterozygous

Setting	Description
Zygosity	The zygosity (homozygous or heterozygous) of the variant. The zygosity is based on the Mutation percentage threshold value, which is specified in the Mutation Filter settings section for an Alignment project in the Project Wizard. See "Mutation Filter settings" on page 137.) If both alleles are found above the threshold value, then the variant is considered to be heterozygous. If only one allele is found above this threshold value, then the variant is considered to be homozygous.
Ref Pos	The nucleotide position in the reference sequence based on a continuous count from the beginning to the end of the reference.
Gene	
Gene	Selected by default. The gene name if it is provided in the GenBank reference file or the preloaded reference.
Trans. Type	The transcript type defined for the transcript that is shown in the Transcript Accession column.
Trans. Accession	The transcript accession number from NCBI for the gene transcript that is used for annotating the variant.
Strand	The strand (+/-) for the gene in which the variant is located.
Exon	The exon number where the variant occurs. This number includes non-coding exons.
CDS	Selected by default. The coding exon number where the variant occurs.
Gene Ref	The reference nucleotide at the variant position relative to the gene direction. This value is the same as the Ref value for (+) strand genes and the complement of the Ref value for (-) strand genes.
Gene Alt	The alternate (variant) nucleotide at the variant position relative to the gene direction. This value is the same as the Alt value for (+) strand genes and the complement of the Alt value for (-) strand genes.
Protein	
Protein Accession	The protein accession for the gene from NCBI for the transcript that is used for annotating the variant.
Amino Acid Change	Selected by default. The change in the amino acid that is caused by the variant. An "FS" is displayed for frameshift variants (indels in the coding sequence). "In-Frame" is displayed where an entire codon, or multiple entire codons, are inserted or deleted.
Function	The functional consequence of the variant. Possible values are:
	Non-coding
	Synonymous
	Missense
	Nonsense
	• No-stop
	• In-frame
	Frameshift

Setting	Description
Mutation Call – Select this opt position. You can select multip	ion to identify the change (variant call) that occurs at the variant ole options.
Genome	 Selected by default. List variant calls without positional information.
 Relative to CDS 	• List variant calls relative to the CDS (coding sequence) position.
 Relative to mRNA 	List variant call positions relative to the mRNA sequence.
HGVS Genomic	 List variant calls using the format that is recommended by the Human Genome Variation Society relative to the genomic position of the variant.
HGVS Coding	 List variant calls using the format that is recommended by the Human Genome Variation Society relative to the coding base number position of the variant.
HGVS Protein	 List variant calls using the format that is recommended by the Human Genome Variation Society relative to the amino acid position of the variant.
 Forensic (SWGDAM mtDNA) 	 List variant calls based on the mitochondrial forensic nomenclature as recommended by the Scientific Working Group on DNA Analysis (SWGDAM)
Reference Database ID	
dbSNP	For variants that are found in the dbSNP database from NCBI, the rs accession number for the variant from the dbSNP database.
Miscellaneous	
Show all transcripts	If this option is not selected, then show the variant information only for the single preferred transcript for the gene; otherwise, show variant calls based on multiple transcripts only if:
	There are overlapping genes.
	 Different transcripts of the same gene result in different amino acid changes. For example, if a variant is in the coding region in one transcript and in an intron in a different transcript.
Comments	Variants that you have manually deleted or that the software has deleted show "Deleted" in this column. Mutations that you have added manually show "Added Manually" in this column. Mutations that you have manually confirmed show "Checked" in this column.

Display tab, Statistics sub-tab

nnotation Statistics	Phasing		
Basic			
	- x	Alt %	Verall Score
Coverage	🔲 Alt #	All &	Veral Score
Ref #(F;R)	🔲 Alt #(F;R)		
Details			
🔲 A #(F;R)	🔲 A(%)	A Score	Allele Score
C #(F;R)	🗍 C(%)	C Score	Ambiguous Gain Penalty
🔲 G #(F;R)	🔲 G(%)	G Score	Ambiguous Loss Penalty
🔲 T #(F:B)	🔲 T(%)	T Score	Balance ratio relative to counts
Del #(F;R)	🔲 Del(%)	Del Score	Balance ratio relative to percentage
🔲 Ins #(F;R)	🔲 Ins(%)	Ins Score	
Other			
Check allele co	unts for negative mu	Itations	
			Kan II lan and ince and inches
Legiculate statist	ics pased on origina	ir reads for Condensa	tion/Elongation projects
Settings			DK Cancel

Figure 6-69: Mutation Report Settings dialog box, Display tab, Statistics sub-tab

Setting	Description
Basic	
Coverage	Selected by default. The total number of reads that are aligned at the variant location.
Alt #	The total number of reads that contain the alternate (variant) nucleotide at the variant position.
Alt %	The percentage of total reads that contain the alternate (variant) nucleotide at the variant position.
Overall Score	An empirical estimation of the likelihood that a given variant call is real and not an artifact of sequencing or alignment errors. See "Overall Mutation Score" on page 446.
Ref #(F,R)	The number of reads that show the reference nucleotide in the forward direction and the number of reads that show the reference nucleotide in the reverse direction.
Alt #(F,R)	The number of reads that show the alternate (variant) nucleotide in the forward direction and the number of reads that show the alternate (variant) nucleotide in the reverse direction.
Details	
A #(F,R), C #(F,R), G #(F,R), T#(F,R)	Selected by default. The number of reads that show the indicated base at the variant location in the forward direction and the number of reads that show the indicated base at the variant location in the reverse direction.
Del #(F,R)	Selected by default. The number of reads that show a deletion at the variant location in the forward direction and the number of reads that show a deletion at the variant location in the reverse direction.


Setting	Description
Ins #(F,R)	Selected by default. The number of reads that show an insertion at the variant location in the forward direction and the number of reads that show an insertion in the reverse direction at the variant location.
A(%), C(%), G(%), T(%)	The percentage of reads that show the indicated base at the variant location.
Del(%)	The percentage of reads that show a deletion at the variant location.
Ins(%)	The percentage of reads that show an insertion at the variant location.
A Score, C Score, G Score, T Score	Essentially an allele balance score for each individual allele. It is scaled to be similar to the Overall Mutation score, but it does not contribute to the overall score.
	 If the allele F/R ratio is > 3 x the F/R ratio for all the reads at the indicated position, or is < 1/3 x the F/R ratio for all the reads at the indicated position, then the score for the allele is zero.
	• If the position has no calls that correspond to the indicated allele, then the score for the allele is again zero.
	 Otherwise, the score is calculated based on the F/R ratio for the allele and the F/R ratio for all the reads at the indicated position. The closer that these two values are, then higher the allele score. The maximum allele score for any allele is 27.
Del Score	For deletion alleles. See the description for A Score, C Score, G Score, T Score.
Ins Score	For insertion alleles. See the description for A Score, C Score, G Score, T Score.
Allele Score	For the alternate allele. See the description for A Score, C Score, G Score, T Score.
Ambiguous Gain Penalty	Display the Ambiguous Gain penalty value for the variant. See "Ambiguous Gain penalty/Ambiguous Loss penalty" on page 227.
Ambiguous Loss Penalty	Display the Ambiguous Loss penalty value for the variant. See "Ambiguous Gain penalty/Ambiguous Loss penalty" on page 227.
Balance ratio relative to	Show the smaller of the two ratios:
counts	 #F/#R–The ratio of the number (count) of forward reads with the variant to the number of reverse reads with the variant.
	 #R/#F–The ratio of the number (count) of reverse reads with the variant to the number of forward reads with the variant.
Balance ratio relative to percentage	 Show the smaller of the two ratios: %ALTF/%ALTR-The ratio of the percentage of forward reads with the alternate allele to the percentage of reverse reads with the alternate allele.
	 %ALTR/%ALTF–The ratio of the percentage of reverse reads with the alternate allele to the percentage of forward reads with the alternate allele
	Note: This value is useful for regions that have coverage in only one direction.
Note: You can set the filters b tab, Bias sub-tab" on pa	based on the balance ratios on the Filters tab, Bias sub-tab. See "Filter age 225.

Setting	Description	
Mutant Allele Frequency(%)	Selected by default. The percentage of the total aligned reads at the variant position that contain the alternate allele.	
Check Allele Counts for Negative Mutations	When negative variants are included in the report, calculate and display the allele frequencies for these positions.	
Other		
Calculate statistics based on original reads for Condensation/Elongation projects	Editable only if the loaded project used Condensation or Elongation. When selected, display statistics based on the original reads.	

Display tab, Phasing sub-tab

Phasing is an optional, post-analysis step that is applied to the initial variant call results. If you select to carry out phasing as a post-analysis step, then strings of variants that are within a user-defined proximity (0 -3 bp) and are on the *same* reads are merged into a single indel call. Any variants within a maximum of 3 bp can be phased. For example, consider Figure 6-70 below, which shows the same neighboring SNPS, but one SNP is found on the same strand and the other SNP is found on different strands.

Figure 6-70: Neighboring SNPs considered for phasing



Without phasing selected, two individual substitution calls would be made for the mutations that were found on the same strand - a substitution of a G and a substitution of a C, which results in calls that do not provide a reference to the chromosome location (the same chromosome or different chromosomes). If, however, phasing is selected, then a single indel call is made instead, with a deletion of a TG and an insertion of a GC. Two individual substitution calls are still be made for the mutations that were found on different strands.



You specify phasing options for an alignment project on the Alignment tab of the Project Setup Wizard. See "Mutation Filter settings" on page 137.

Mutation Report Settings	<u> </u>
splay Filter Summary Report Output	
nnotation Statistics Phasing	
Merge phased variants Display phase ID Display phase detail	
Setlingo	DK Dancel

Figure 6-71: Mutation Report Settings dialog box, Display tab, Phasing sub-tab

Description	
Display the single indel call that results from phased reads being merged.	
A unique, system-generated value that is assigned to each phased variant. If variants have been phased together, then a single Phase ID is reported. If variants are phased separately, then a unique ID is reported for each variant. Phase IDs start at zero (0).	
 Display the following information about the phased variants: Count: The number of different variants called in the phase region. Percentage: The number of reads/total number of reads in the phased region that have at least one of the variants that was 	

Filter tab, Annotation sub-tab

notation Bias Score ROI	
Function Coding Variants Ø Synonymous substitutions Ø Missense substitutions Ø Nonsense substitutions Ø No-stop substitutions Ø Indels Noncoding Variants Splicing Sites Inform 2 000 Exem Ø All other substitutions Ø All other Indels	Limit Regions Gene Baros 12 Altes 12 Exorn Behore 12 Altes 12 Exorn Behore 12 Altes 12 EDS Behore 30 Artes 30 Source Called by software Added manually Confirmed Deleted Negative
Zygosity Ø Homozygous Ø Heterozygous Settings	Reference Database dbSNP Reported Vurreported

Figure 6-72: Mutation Report Settings dialog box, Filter tab, Annotation sub-tab

Setting	Description
Function	
 Coding Variants Synonymous Missense Nonsense No-stop 	 By default, show substitutions of all types in the report. Clear the options for the substitution types that are not to be displayed in the report.
Indels	• By default, show insertions and/or deletions. Clear this option if indels are not to be displayed in the report.
Non-coding Variants	
Splicing Sites	• Select this option to show all variants in splicing site regions, and then specify the intron and exon values to define the splicing site region.
 All other substitutions 	• Selected by default. Show all substitutions that are located outside coding regions.
All other indels	 Selected by default. Show all indels that are located outside coding regions.
Zygosity	
Homozygous	Selected by default. Show homozygous variants in the report.
Heterozygous	Selected by default. Show heterozygous variants in the report.
Limit Regions – Select this reference file.	option to show only those variants that occur in a designated region of the
• Gene	• Show the variants that occur only in gene regions. "x" number of bases on either end of the gene region can be shown as well.

Setting	Description
• Exon	 Show the variants that occur only in mRNA regions. "x" number of bases on either end of the mRNA region can be shown as well.
• CDS	 Show variants that occur only in the coding exons. "x" number of bases on either end of the coding exon region can be shown as well.
Source	
Added automatically	 Selected by default. Include all variants that NextGENe automatically identified.
Added manually	 Selected by default. Include all variants that you manually added using the Add Mutation function in the Alignment viewer.
Confirmed	 Selected by default. Include all variants that you manually confirmed using the Confirm Mutation function in the Alignment viewer.
Deleted	 Include all variants that NextGENe automatically deleted and all variants that you deleted using the Delete Mutation function in the Alignment viewer.
Negative	 Include the locations of reported SNPs (annotated in the reference file) where the sample data does not include the variant.
Note: For the source optic	ons listed above, see "Alignment viewer functions" on page 153.
Reference Database	
dbSNP	 Reported–Show reported variations as annotated in the reference based on dbSNP.
	 Unreported–Show unreported variations as annotated in the reference based on dbSNP.

Filter tab, Bias sub-tab

Display Filter Summary Re Annotation Bias Score	and the second second	Page Nun	iber
Balance ratios and frequency <=	SNPs 0.100 80.000	Indels D.100 80.000 2	Homopolymer Indels
Balance ratio calculation Balance ratio calculation Filter 1 directional calls	Relative to per	centage	


Figure 6-73: Mutation Report Settings dialog box, Filter tab, Bias sub-tab

Setting	Description
Balance Ratios and Frequency <=	 SNPs – Eliminates variant calls that are likely false positives. If both the frequency and balance ratio values for the variant fall below the set thresholds, then the variant is filtered.
	 Indels – Eliminates variant calls that are likely false positives. If both the frequency and balance ratio values for the variant fall below the set thresholds, then the variant is filtered.
	 Homopolymer Indels – Homopolymers are defined as the reference is ≥ 2 bases and the reads are ≥ 1 base. This means that CC>C is a homopolymer deletion and C>CC is not a homopolymer insertion. If both the frequency and balance ratio values for the variant fall below the set thresholds, then the variant is filtered.

Setting	Description		
	Select which balance ratio value to use for the filtering variants. You can se for the actual filtering, but you can indicate whether to display one or n report.		
Relative to counts	Selected by default. Show the smaller of the two ratios:		
	 #F/#R-The ratio of the number (count) of forward reads with the variant to the number of reverse reads with the variant. 		
	 #R/#F–The ratio of the number (count) of reverse reads with the variant to the number of forward reads with the variant. 		
Relative to	Show the smaller of the two ratios:		
percentage	 %ALTF/%ALTR-The ratio of the percentage of forward reads with the alternate allele to the percentage of reverse reads with the alternate allele. 		
	 %ALTR/%ALTF—The ratio of the percentage of reverse reads with the alternate allele to the percentage of forward reads with the alternate allele 		
	Note: This value is useful for regions that have coverage in only one direction.		
Filter 1 directional cells	Select this option to filter out variants that have overall coverage in only one direction.		

Filter tab, Score sub-tab

Figure 6-74:	Mutation Report Settings dialog box, Filter tab, Score sub-tab
	Mutation Report Settings





A variant must exceed the threshold values for all selected scores to be included in the Mutation report. For detailed descriptions about the score values on this tab, see Appendix A, "Mutation Report Scores," on page 445.

Setting	Description			
Confidence score				
Overall score	• Show all variants where the Overall Mutation score is greater than or equal to the indicated threshold.			
Coverage score	• Show all variants where the Coverage Score is greater than or equal to the indicated threshold.			
Read balance score	 Show all variants where the Read Balance score is greater than or equal to the indicated threshold. 			
Allele balance score	 Show all variants where the Allele Balance score is greater than or equal to the indicated threshold. 			
Homopolymer Score	 Show all variants where the Homopolymer score is greater than or equal to the indicated threshold. 			
Mismatch score	• Show all variants where the Mismatch score is greater than or equal to the indicated threshold.			
Wrong allele score	 Show all variants where the Wrong Allele score is greater than or equal to the indicated threshold. 			
 Ambiguous gain penalty Ambiguous loss penalty 	Show all variants where the Ambiguous Gain penalty and/or the Ambiguous Loss penalty is less than or equal to the indicated threshold. See "Ambiguous Gain penalty/Ambiguous Loss penalty" below.			
Allele Score	Show all variants where the Allele Score for the alternate allele is greater than or equal to the indicated threshold.			
Overall score calculatio	n			
Ignore read balance score	Ignore the Read Balance score when calculating the Overall Mutation score. See "Read Balance Score" on page 448.			
Ignore allele balance score	Ignore the Allele Balance score when calculating the Overall Mutation score. See "Allele Balance Score" on page 449.			
Ignore homopolymer score	Ignore the Homopolymer score when calculating the Overall Mutation score. See "Homopolymer Score" on page 450.			
Ignore mismatch score	Ignore the Mismatch score when calculating the Overall Mutation score. See "Mismatch Score" on page 451.			
Ignore wrong Allele score	Ignore the Wrong Allele score when calculating the Overall Mutation score. See "Wrong Allele Score" on page 452.			


Ambiguous Gain penalty/Ambiguous Loss penalty

Ambiguity at the position where a variant is called can be the result of many factors, including pseudo genes and other repetitive elements, and where the variant is located—at the 5' end, at the 3' end, or in a central location. The *Ambiguous Gain penalty* and *Ambiguous Loss penalty* quantify the ambiguity relative to the region where a variant is called. To calculate these penalties, NextGENe first generates multiple, short synthetic reads for every location at which a variant was called. These synthetic reads are based on the consensus sequence for the region where the variant was called. The reads are generated in both the forward and reverse directions, and are designed so that the variant call is found in

the beginning of some the reads, at the end of some of the reads, and at several central locations on other reads. NextGENe then aligns these reads with the reference sequence, and determines the number of synthetic reads that can be aligned at each variant position in the reference sequence. The Ambiguous Gain/Loss penalties are calculated from the results of these alignments. The Ambiguous Gain penalty has no set value, (the range is 0 - n), and the Ambiguous Loss penalty has a range of (0-1). For both penalties, a value closer to zero indicates that the region where the variant was called has a more unique sequence (the expected number of multiple synthetic reads were aligned to the position). Conversely, for both penalties, a larger value indicates that the region where the variant was called is not unique. For the Ambiguous Gain penalty, a value closer to ten indicates that a greater number of reads than expected aligned to the region where the variant was called. For the Ambiguous Loss penalty, a value closer to one indicates that fewer synthetic reads than expected aligned to the region where the variant was called to the region where the variant was called to the region where the variant was called to the region where the variant was called. For the Ambiguous Loss penalty, a value closer to one indicates that fewer synthetic reads than expected aligned to the region where the variant was called.

For example, consider the scenario in which variant calls were made at Positions A, B, and C in a sample file and NextGENe generates 30 synthetic reads for each position. If after aligning the synthetic reads, NextGENe determines that 30 reads aligned at Position A, 30 reads aligned at Position B, and 30 reads aligned at Position C, then both the Ambiguous Gain and Loss penalties would have a value of zero for all positions; however, if after aligning the synthetic reads, NextGENe determines that 60 reads aligned at Position A and 15 reads aligned at Position B, then the Ambiguous Gain penalty for Position A would be 2, and the Ambiguous Loss penalty for Position B would be 0.5.

Filter tab, ROI sub-tab



ay Filter Summary Report Output otation Bias Score ROI	
Filter by ROI	Esclusion
Add <u>Bernove</u>	<u>Aid Elemove</u>

You can include or exclude variants from the Mutation report based on their locations in a Region of Interest (ROI). You must specify the ROIs in a BED file, a comma-delimited text file that specifies position or gene name, or a VCF file.



Click File Types to open the File Types dialog box which details the different formats that are required for a BED file, a text file, or a VCF format file.

Setting	Description
BED file	A BED file is a tab-delimited text file. You can upload a BED file only if the reference sequence contains chromosome information, which means that the reference sequence must be either a preloaded reference that SoftGenetics supplies, or a GenBank reference file that contains chromosome information. Each row in the file contains a region of the reference that is to be used for the Mutation report, and at a minimum, the file must contain the following information:
	Field #1 - Chromosome number for the region
	Field #2 - Chromosome start position
	Field #3 - Chromosome end position
	Note: Field #4, which is used for the Description column, is optional.
Text file	You can load a text file that is comma-delimited, semi-colon delimited, or tab-delimited. The file must contain one of the following lists:
	 TXT Region Format - Specific reference locations (position number or a range of positions (start position number - end position number)).
	TXT Gene Format - A list of reference gene names.
VCF Format	You can upload a VCF file only if the reference sequence contains chromosome information, which means that the reference sequence must be either a preloaded reference that SoftGenetics supplies, or a GenBank reference file that contains chromosome information.
	Note: See http://www.1000genomes.org for the conventions and extensions adopted by the 1000 Genomes Project for reporting variants in the most recent VCF format.

You can also select Include Negative Positions within ROI to list every position in every ROI in the report, whether or not there is a variant at the position.

Summary Report tab

 Mutation Report Settings

 Display Filter

 Summary Report

 Quarter

 Report name

 Mutation report

 Image: Display mutation report

Figure 6-76: Mutation Report Settings dialog box, Summary Report tab

You use the options on the Summary Report tab to specify how the Mutation report is to be displayed in the Summary report. You must save these settings in a Settings file (.ini file) for the Mutation report. These settings are applied to the Summary report if you select this Settings file during the setup of the Summary report. See "Summary report" on page 246.

Setting	Description
Report Name	The name that is displayed for the Mutation report when it is included in the Summary report.
Display mutation report summary	Selected by default. Display the summary information for the Mutation report in the Summary report.
Display mutation report	Selected by default. Display the Mutation report in the Summary report.

Output tab



The settings on this tab are applicable only for post-processing.

Figure 6-77: Mutation Report Settings dialog box, Output tab

Mutation Report Settings			- X		
Display Filter	Summary Report	Output			
Additional Out	outs				
	FT report CF report (filtered)				
	onsensus sequence		Ed#Settings		
🛄 Save S	NP consensus sequ	ience	Edit Settings		
Settings				DK.	Cancel

Setting	Description			
Save SIFT report	Saves the Mutation Report as a SIFT report, which can be used in the third party SIFT tool.			
Save VCF report (filtered)	 Saves the Mutation Report in a format that adheres to Variant Call Format (VCF) specifications. The report contains only those variants that passed the Mutation Report Filter settings. Note: Also available as a Mutation report function. See "Mutation Report functions" below. 			
Save consensus sequence	Saves the consensus sequence to a .fasta file. To specify the settings for the saved file, click Edit Settings. See "Save consensus sequence" on page 242.			
Save SNP consensus sequence	Saves the SNP consensus sequence to a .fasta file. To specify the settings for the saved file, click Edit Settings. See "Save SNP consensus sequence" on page 244.			

Variation Tracks Settings dialog box

The Variation Tracks Settings dialog box contains the tracks settings for the Mutation report based on the variation databases that were imported for the project. (After being imported into NextGENe, a variation database is referred to as a *track*.



For detailed information about variation databases, see the Reference & Track Manager Tool User's Manual or Online Help

You can select what information to display for the tracks and you can filter the variants in the Mutation report based on the tracks.

1. On the NextGENe Viewer toolbar, click the Tracks Settings icon , and then select Variation Tracks Settings. ■

The Variation Tracks Settings dialog box opens. The Tracks pane is the left pane of the dialog box. The pane displays all the variation databases, or *tracks*, that are available for the selected project.

Figure 6-78: Variation Tracks Settings dialog box

Project Track Amodelions ESPESSIOS/V2 Geosgian Constructions C	dbNSFP\2.0				
	Show . All	Reported Unreported		Report Display >	
	Functional Prediction Conservation Population Frequency At least Criteria Settified Clean-Filter Records with multiple values for a single score will pass filtering for that score if any one of the values passes. Setting and the values for a single score will pass filtering for that score if any one of the values passes.				
	Federation of the cases of Federation of the cases of Pederation of the cases of the cases of the cases of the cases of the cases of the cases of the cases of the cases of the Multiple of the cases of	Polyphern2 iscore based on HumDry, i.e. holv, prob The score ranges from 10 n.1. D ("Probably Danaging") is the range (0.557,11, P. Prossibly Danaging") is the range (0.4330,356);8 ("Bengin") is the range (0.0.452);	D-Probably Damaging P-Possibly Damaging B-Benigh Nic Data Score 9 0		
Save Settings > Load Settings	×		OK Cano	zel	

- 2. To remove all the current display and filter settings based on all the tracks, click Load Settings > Clear all tracks, and then click OK; otherwise, go to Step 3.
- 3. In the Tracks pane, select a track, and then do the following:
 - a. Indicate the types of variants that are to be included in the Mutation report.

Option	Description
All	By default, all variants that meet all the filtering criteria are displayed in the Mutation report, whether they are included in the selected track.
Reported	Select Reported to display only those variants that are included in the selected track

Option	Description
Unreported	Select Unreported to display only those variants that are not included in the selected track.

b. Specify the filter settings for the track.

J	նդ	

The track filter settings available depend on the tracks included for the project. Information for filtering based on some example variant tracks is presented in the following sections:

- "dbNSFP track settings" on page 234.
- "ClinVar track settings" on page 238.
- "dbscSNV track settings" on page 239.
- c. Click Report Display to open the Report Display Settings dialog box, and then do the following:
 - i Optionally, to include the group identification for the track in each column heading, for example, dbNSFP, select Display track group.
 - ii. Optionally, to include the name for the track as defined when importing the track in the Track Manager in each column heading, select Display track name.
 - iii. On each tab, select the columns that are to be included in the report, or click Select All to select all columns in a single step.



The Report Display Settings dialog box lists all the display settings (columns) that can be included in the Mutation report for the track. By default, no columns are selected. The options that are available vary based on the selected track.

Figure 6-79: Report Display Settings pane, dbNSFP track selected

Display track group	Display track name	
sectional Rediction Contens	ation Population Frequency	
1000 Geroome Phane 1 1000Gp1 AF 1000Gp1 AF 1000Gp1 EUR AF 1000Gp1 EUR AF 1000Gp1 APR AF	NHLIH GO Exone Sing Pinges ESP5200 AA AF ESP5500_EA AF	
Select All		OK Cencel

- 4. Click OK to close the Report Display Settings dialog box.
- 5. Do one of the following to save your settings and close the Variation Tracks Settings dialog box:
 - Click OK.

Going forward, the Mutation report is generated according to these saved settings until you change them.

• Save Settings > Save User Defaults, and then click OK.

The settings that you have specified for all the tracks are saved as your (the logged in user's) default settings. Going forward, any new sequence alignment project that *you* run in NextGENe uses these settings by default. If you change the settings for a project and want to generate the Mutation report based on your default settings, then you can click Load Settings > Load User Defaults to restore your default settings.

• Save Settings > Save To File, and then click OK.

The settings that you have specified for all the tracks are saved to a Settings (.ini) file. Going forward, you can click Load Settings > Load From File to load this saved Settings file and generate the Mutation report according to the settings in the file.



You can also load this saved *.ini file in Postprocessing step of the Project Wizard to automatically generate the Mutation Report based on these settings.

dbNSFP track settings

You can elect to include all variants, only the variants that are reported in dbNSFP, or only the variants that are not reported in dbNSFP. The specific tabs and the filter variables that are available depend on the specific version of the dbNSFP database that was used for the project. For some example tabs, see:

- "Functional Prediction tab" on page 235.
- "Conservation tab" on page 236.
- "Population Frequency tab" on page 237.

Functional Prediction tab

Variation Tracks Settings Project Track Annotations ESP65005/V2 v65005/V2 cbNSFP 2.0 dbNSFP\2.0 Show 💿 All 🦳 Reported Unreported Report Display > Functional Prediction Conservation Foculation Frequency E At least ClearFiler Records with multiple values for a single score will pass filtering for that score if any one of the values passes. PolyFhen2_HDW PolyFhen2_HVAFi LRT MutationTaster MutationEssessor 8(Fi FATFIMM Polyphen/2 score based on HuntDiv. i.e. hdik_prob.The score ranges from 0 b 1. D ("Pobably Damagno") is the range (0.957,1); P ("Possibly Danagino") is the range (0.453,0.956) B ("Benigo") is the range [D.0.452]: D Probably Damaging PPossible Damaging B Bonign Scole Save Settings 2 Load Settings > OK Cancel

Setting	Description
At least [] Criteria Satisfied	The default value is one. A variant must pass the filtering settings for only one of the available conservation scores to be displayed in the Mutation report. Increase this value as needed.
Filtering Settings	The score threshold, which has a default value of ≤ 0 . You can modify this value for each available functional prediction method. Optionally, you can also specify classifications for the variant, for example, D-Probably Damaging, P-Possibly Damaging, B-Benign, and/or No Data.
	Note: If you specify classifications for a variant, then the variant must meet both the score threshold <i>and</i> the classification requirements to be displayed in the Mutation report.

Figure 6-80: Variation Tracks Settings dialog box, dbNSFP selected, Functional Prediction tab

Conservation tab

Froject Track Annotations ESP6500SI-V2 S00SI-V2 G500SI-V2 BNSFP	dbNSFP\2.0			
	Show 💿 All 👘 Rep	orted 👘 Unreported		Report Display >
2.0	Functional Prediction Conservation	Population Frequency		
	🔲 At least 📋 🛨 Criteria Satisf	ed	Elear Filter	
	GERP4-NR GERP4-RS Proto 29way bagDats URT_Compa	GERP++ neutral rate	Scores (*	

Figure 6-81: Variation Tracks Settings dialog box, dbNSFP selected, Conservation tab

Setting	Description
At least [] Criteria Satisfied	The default value is one. A variant must pass the filtering settings for only one of the available conservation scores to be displayed in the Mutation report. Increase this value as needed.
Filtering Settings	The score threshold, which has a default value of ≤ 0 . You can modify this value for each available conservation method.

Population Frequency tab

Project Track Annotations SP6500SI-V2 S6500SI-V2 S6500SI-V2 S6500SI-V2	dbNSFP\2.0					
	Show @ All	Reported	Report Display			
	Functional Prediction Conserv	ation Population Frequency				
	Fite based on population frequencies Clease Filter Common variants can be fittered out by limiting the maximum frequency. Al scores and pass.					
	1000Go1_AF 1000Go1_AFL_AF 1000Go1_SELH_AF 1000Go1_ASL_AF 1000Go1_ASL_AF ESP6500_AA_AF ESP6500_EA_AF	Alternative allele frequency in Frequen the whole 100006p1 data	ey is ce 10			

Figure 6-82: Variation Tracks Settings dialog box, dbNSFP selected, Population Frequency tab

Setting	Description
Filter Based on Population Frequency Score	Select this option to filter the variants that are displayed in the Mutation report based on the filtering settings for the available population frequency values.
Filtering Settings	The score threshold, which has a default value of \leq 1. You can modify this value for each available population frequency value.

ClinVar track settings

You can elect to include all variants, only the variants that are reported in ClinVar, or only the variants that are not reported in ClinVar.

Figure 6-83: Variation Tracks Settings dialog box, ClinVar selected

▲ UT tracks ▲ douc5NV 1.0 ▲ dourp L dinvar_20160502.vcf	dbsnp\clinvar_20160502.vcf				
	Show All Reported	Report Display			
	🕼 At least 🔋 👻 Criteria Satisfied				
	Clinical Significance UNCERTAIN SIGNIFICANCE NOT PROVIDED BENIGN	OTHER LIKELY BENIGN			
	·				

Setting	Description
At least [] prediction satisfied	The default value is one. A variant must pass the filtering settings for only one of the available clinical origin or clinical significance values to be displayed in the Mutation report. Increase this value as needed.
Filtering Settings	Select the variants that are to be included in the Mutation report based on clinical origin and/or clinical significance.

dbscSNV track settings

You can elect to include all variants, only the variants that are reported in dbscSNV, or only the variants that are not reported in dbscSNV.

Figure 6-84: Variation Tracks Settings dialog box, dbscSNV selected

 ▲ I Tracks ▲ B dbscSNV ▲ B dbscSNV ▲ B dbscSNV 	dbscSNV\1.0								
	Show 💿 All	Show All Reported Ourreported Report Display.							
	📝 At least 🚺 🔻 Criter	[7] At least 0 ▼ Criteria Satisfied							
	ADA_SCORE	<u>k</u> = -	0.0						
	RF_SCORE	<= =	0.0						
	REFSEQ_REGION	exonic	🔛 intergenic	📝 intronic	morna_intronic	i splicing	upstream		UTU
	ENSEMBL_REGION	1 exonic	intergenic	intronic	nema_intronic	splicing.	🔄 upstream	1 UTR5	UT
	<	elect All	_	m			_		,

Setting	Description
At least [] Criteria Satisfied	The default value is one. A variant must pass the filtering settings for only one of the available conservation scores to be displayed in the Mutation report. Increase this value as needed.
Filtering Settings	Select the variants that are to be included in the Mutation report based on the dbscSNV scores and/or regions.

Gene Tracks Settings dialog box

The Gene Tracks Settings dialog box contains the gene tracks settings for the Mutation report based on the gene tracks that were imported for the project. To open the Gene Tracks Settings dialog box, on the NextGENe Viewer toolbar, click the Tracks Settings icon , and then select Gene Tracks Settings. By default, the gene annotations for the reference (Reference Build In Annotation) is selected. If other gene annotation tracks have been imported for the project, then these tracks are listed alphabetically by name below the Reference Build Annotation track. You can leave the Reference Build In Annotation option selected to use just this information in the project, you can select another gene annotation tracks in the project.



For detailed information about importing gene annotation tracks, see the Reference & Track Manager Tool User's Manual or Online Help

Figure 6-85: Gene Tracks Settings dialog box

Gene Tracks Settin	gs		— ×-
Choose gene track	for annotation		
Beference	Build In Annotation		
C Gff_p13			
C AI			
	<u> </u>	<u>C</u> ancel	

Mutation Report functions

A variety of functions are available for working with the information in the Mutation report. All these functions, which are available under the Reports > Mutation Report option on the NextGENe Viewer main menu, result in the generation of files or reports that contain variant information for the alignment project. You must specify a name and location for these files and reports. See:

- "Save Mutation report" on page 241.
- "Save SIFT report" on page 241.
- "Save VCF report (filtered)" on page 241.
- "Save unfiltered VCF report" on page 241.

- "Mutation Report Summary" on page 241.
- "Save consensus sequence" on page 242.
- "Save SNP consensus sequence" on page 244.
- "Fragment Output" on page 245.
- "Seek Sample Position" on page 245.

Save Mutation report

Saves the Mutation report as a text (.txt) file. The default name for the report is <Loaded Project Name>_Mutation _Report, and the default directory in which it is saved is the directory for the loaded project, but you can change one or both these values.

Save SIFT report

Click Save SIFT Report to save the Mutation report as a SIFT report, which can be used in the third party SIFT tool.

Save VCF report (filtered)

Click Save VCF Report (filtered) to save the Mutation report in a format that adheres to Variant Call Format (VCF) specifications. The report contains only those variants that passed the Mutation Report filter settings.

Save unfiltered VCF report

Click Save unfiltered VCF Report to save the Mutation report in a format that adheres to Variant Call Format (VCF) specifications. The unfiltered VCF report contains *all* called variants, including the variants that were initially filtered out based on the Mutation Report settings. "SGflt" is displayed in the FILTER column for the filtered variants.

Mutation Report Summary

Click Mutation Report Summary to open the Mutation Report Summary dialog box, which displays key summarized information for the report.

Total Mutations	21523
Number of Homozygous Mutations	3654
Number of Heterozygous Mutations	17869
Number of Substitutions	19969
Number of Insertions (Number In-Frame)	675 (162)
Number of Deletions (Number In-Frame)	879 (189)
Transition/Transversion Ratio	1.531

Figure 6-86: Mutation Report Summary dialog box

Save consensus sequence

Click Save Consensus Sequence to open the Save Consensus Sequence Options dialog box. By default, the General tab is the open tab. The tab displays the options for specifying how you want to save the consensus sequence.



Optionally, you can click Load Settings on the dialog box, and browse to and select a Settings file (.ini file) to generate the Save Consensus Sequence report based on the saved settings in the file.

Figure 6-87: Save Consensus Sequence Options dialog box, General tab

Setting		
	T Covered 1	Uncovered
Input Region Manually		
Start 1	End 1000	
C Input Points of Interest Text	t File(*.txt)	
C Input Points of Interest BED	File(*.bed)	
a		
Output Consensus Sequence		
 Relative to Mutation 	C Relative to Custom Setting	[marrows
Report Filter	Homocygor+(8/1/8-1111,8/8)	75.000
	IUFAC Heterosigote(0,03-100.0%	25.000
	Homosygere indel(20/002-1002)	30.000

Option	Description
Setting	
All	Export all bases in the consensus sequence as one segment in a .fasta file. If no reads align to a region in the reference genome, then the reference sequence is exported for the region. Covered regions are exported as defined by the Output Consensus Sequence settings below.
Covered	Export a consensus sequence that contains the consensus bases from only the covered regions of the reference sequence. Multiple consensus segments are generated and placed into a single .fasta file. Covered regions are exported as defined by the Output Consensus Sequence settings below. If no reads are aligned to a region in the reference sequence, then no consensus sequence is output for the region.
	Note: If <i>any</i> portion of a reference segment (contig) is covered, then the entire segment is considered to be covered.
Uncovered	Export a consensus sequence that contains bases from only the uncovered regions of the reference sequence. Multiple segments are generated and placed into a single .fasta file. Regions of the reference sequence to which sequence reads are aligned are not included in the output.
	Note: To be considered uncovered, the <i>entire</i> reference segment (contig) must be uncovered.

Option	Description		
Specify the coverage region for which you want to save the consensus sequence. You can select one of the following:			
 Input Region Manually 	 Input the region manually. (You must specify the starting position and the ending position.) 		
Input Points of Interest Text File (*.txt)	 There are no special requirements for uploading a comma-delimited text file. If the input text file is a comma-delimited text file, it must contain one of the following lists: Specific reference locations (position number or a range of positions (start position number - end position number)) separated by commas A list of reference gene names separated by commas 		
Input Region of Interest BED File (*.bed)	 A BED file is a tab-delimited text file. You can upload a BED file only if the reference sequence contains chromosome information, which means that the reference sequence must be either a preloaded reference that NextGENe supplies, or a GenBank reference file that contains chromosome information. Each row in the file contains a region of the reference that is to be used for the report, and at a minimum, the file must contain the following information: Field #1 - Chromosome number for the region Field #2 - Chromosome start position Field #3 - Chromosome end position 		
	Note: Field #4, which is used for the Description column, is optional.		
Output Consensus	s Sequence		
Relative to Mutation Report Filter	Replace a reference nucleotide with a variant nucleotide based on the settings that are specified in the Mutation report. See "Mutation Report settings" on page 213.		
Relative to Custom Setting	• Homozygote(0%-100.0%)—The minium percentage of reads for an allele to be considered homozygous; otherwise, the allele is considered heterozygous and the consensus sequence shows a "K" (which is the IUPAC symbol for G and T) at the location. For example, if this value is set to 80% and 85% of reads aligned at the location identified as a SNP show a "G" while 15% show a "T," the position is considered homozygous and the consensus sequence shows only a "G" at the location.		
	• IUPAC Heterozygote(0%-100.0%)—The requirements for a location to be considered heterozygous. More than one nucleotide must observed above the set percentage for the location to be considered heterozygous. For example, if this value is set to 25% and 65% of reads aligned at the location identified as a SNP show a "G" while 35% show a "T," the allele is considered to be heterozygous and the consensus sequence shows a "K" (which is the IUPAC symbol for G and T) at the location.		
	 Homozygote Indel(20.00%-100%)—The percentage of reads that are aligned at the variant location that must contain the indel for the indel to be included in the consensus sequence. 		

Save SNP consensus sequence

Click Save SNP consensus sequence to open the SNP Consensus Sequence Options dialog box. The dialog box contains options for specifying how you want to save the SNP consensus sequence.



Optionally, you can click Load Settings on the dialog box, and browse to and select a Settings file (.ini file) to generate the Save SNP Consensus Sequence report based on the saved settings in the file.

Figure 6-88: Save SNP Consensus Sequence Options dialog box, General tab

neral		
Load SNP File		_
1		-
SNP(A/A) ;(A/C)		
C Fasta(A);(M)		
Before or After SNP 50	-	
and the second sec		
Dutput Consensus Sequence Homozygote(0.0%100.0%)	75.000	~
IUPAC Heterozygote(0.0%100.0%)	25.000	- %
Homozygote Indel(20.00%100%)	30.000	~ %

Load SNP File	Select this option to load a tab-delimited text file that lists specific variant positions that are to be used for saving the SNP consensus sequence. The first line in the file is the Title line. The file has the following format, where the backslash (\) indicates a tab: Chr\tChr Position\tRef_Allele\tSample_Allele\n Example: 1\t100\tA\tG\n	
	· ·	
SNP	 Output a consensus sequence to a file that shows both alleles present at SNP positions, where, for example: 	
	 A/A indicates a homozygous change to A. 	
	 A/C indicates a heterozygous change with both A and C found at the position. 	
Fasta	Output a consensus sequence to a file that:	
	 Shows only a single allele present for a homozygous position. For example, A indicates a homozygous change to A. 	
	 Uses IUPAC characters for heterozygous positions. For example, M indicates a heterozygous change with both A and C found at the position. 	
Note: For either selection, covered regions are exported as defined by the Output Consensus Sequence settings below.		
Before or After SNP	Determines the number of bases on either side of each variant that are to be included in the SNP consensus sequence when it is generated.	

Output Consensus Sequence		
Homozygote(0 %-100.0%)	The minium percentage of reads that have an allele for the allele to be considered homozygous. For example, if this value is set to 80% and 85% of reads aligned at the location identified as a SNP show a "G" while 15% show a "T," the position is considered homozygous and the consensus sequence shows a G/G at the location if SNP is selected and only a "G" at the location if the Fasta option is selected.	
IUPAC Heterozygote(0 %-100.0%)	The requirements for a location to be considered heterozygous. More than one nucleotide must observed above the set percentage for the location to be considered heterozygous. For example, if this value is set to 25% and 65% of reads aligned at the location identified as a SNP show a "G" while 35% show a "T," the location is considered heterozygous and the consensus sequence shows a G/T at the location if the SNP is selected and only a "K" (which is the IUPAC symbol for G and T) at the location if the Fasta option is selected.	
Homozygote Indel(20.00%- 100%)	The percentage of reads that are aligned at the variant location that must contain the indel for the indel to be included in the consensus sequence.	


Fragment Output

Click Fragment Output to open the Fragment Output Options dialog box. The dialog box contains options for specifying how you want to output fragments of the reference file.

Figure 6-89: Fragment Output Options dialog box

Fragment Output Options			×
Setting Covered	Uncovered		
		<u>O</u> k	<u>C</u> ancel

- Covered—Output covered fragments to a single .fasta file.
- Uncovered—Output only uncovered fragments to a .fasta file.



Seek Sample Position

You use the Seek Sample Position function to output information about points of interest using a specific numbering scheme that you define.



Contact SoftGenetics for assistance with this function.

Sequence Alignment Project Reports

After you complete a sequence alignment project (either for single sequence reads or for paired end/mate paired data), you can manually generate a variety of reports that provide detailed information about matched/unmatched reads, coverage distribution, expression levels, and so on. All the reports (with the exception of three) are available from the Reports menu on the NextGENe Viewer main menu. See:

- "Summary report" below.
- "Matched/Unmatched report" on page 253.
- "Distribution report" on page 254.
- "Coverage Curve report" on page 258,
- "Mismatched Base Numbers report" on page 264.
- "Expression Report" on page 265.
- "Expression report for SAGE studies" on page 272.
- "Structural Variation report" on page 273.
- "Score Distribution report" on page 276.



For information about the Expression report for SAGE studies, see "Expression report for SAGE studies" on page 272. For information about the Expression Comparison report, see "NextGENe Viewer Comparison Reports and Tools" on page 291. For information about the Peak Identification report, see "Peak Identification tool" on page 285.

Summary report

The Summary report displays the Run Statistics for a sequence alignment project and up to five project reports (Mutation report, Expression report, Coverage Curve report, Structural Variation report, and/or Distribution report) in a single view. After you select Summary Report, the Summary Report Settings dialog box opens. If you have already selected post-processing report options for the project, then these report options are displayed on the dialog box; otherwise, it is blank. (See Figure 6-90 on page 247.) You can select additional reports to be included in the Summary report (you must also select a Settings file for each report), and, if applicable, you can remove reports, and then click OK to generate the report.



You can generate and save multiple versions of different reports, or multiple versions of the same report as long as each report version uses a different Settings file.



For information about selecting the Settings file for a report and/or selecting a different reports, see "To modify the Summary report view" on page 250.






Figure 6-90: Summary Report Settings dialog box

By default, when the Summary report first opens, it is displayed on the right side of the opened NextGENe viewer. You can click the Switch Report Layout icon in the NextGENe Viewer toolbar to indicate where to display the report (to the side of the viewer or below the viewer), to show only the report (the NextGENe Viewer is hidden) or you can also hide the report. While in the default alignment view, you can click the Report Selection icon icon on the NextGENe Viewer toolbar to toggle between the Summary report and the Mutation report.





From top to bottom, the *default* Summary report view displays the following:

• A Report toolbar that contains options for showing/hiding the various Summary report sections (such as showing/hiding the Header pane, showing/hiding the Run Statistics pane and so on), an option for saving the report that as a PDF, and an option for modifying the Summary report settings.

lcon	Function
H	Show/Hide Summary Report Header icon - Show/hide the Header (top) pane.
St.	Show/Hide Statistics Info icon - Show/hide the Run Statistics (second) pane.
C1	Show/Hide Coverage Curve Report1 icon - Show/hide the Coverage Curve report pane.
E1	Show/Hide Expression Report1 icon - Show/hide the Expression report pane.
S1	Show/Hide Structural Variation Report1 icon - Show/hide the Structural Variation report pane.
D1	Show/Hide Distribution Report1 icon - Show/hide the Distribution report pane.
repo	u elected to generate more than one Mutation report, Expression report, Coverage Curve ort, Structural Variation report, and/or Distribution report for the project, then the esponding number of Show/Hide icons for the reports is displayed on the Report toolbar.
£	Save as PDF icon - Save the Summary report <i>that is currently displayed</i> in the NextGENe viewer as a PDF.
	Note: After you save the Summary report, the date and time that the report was saved as well as your username are added to the audit trail for the project in the ReportEditHistory.log file. This log file is saved in an AuditTrail folder in the <project name="">.files folder for the appropriate project; for example:</project>
	Illumina\Haloplex\Alignment\2.4.0.1\D_Output\D_Output.files\AuditTrail
2	Settings icon - Opens the Summary Report Settings dialog box. You use the options on this dialog box to change the report view to better suit your working needs. See "To modify the Summary report view" on page 250.
2	Refresh icon - Refreshes the Summary report display after you have changed the Summary report settings, for example, you have added another report to the display.

• A Header toolbar that contains options for customizing the information that is displayed in the Header (top) pane of the Summary report as well as options for showing/hiding the Custom header or the Default Header.

lcon	Description
	Show/Hide Custom Header icon - A toggle that shows or hides the Custom header in the Header pane of the report. When you first open the Summary report for a sequence alignment project, by default, the Custom header is displayed in the Header pane.
	Note: The Custom header displays the default information that is defined in the DefaultHeader.ini file or custom information that you specify using the Edit Header function.
	Show/Hide Default Header icon - A toggle that shows or hides the Default header in the Header pane of the report, which includes the following information about the project— Project Name, Date Created, Date Modified, the NextGENe Version that was used to run the analysis, and the NextGENe Viewer Version that was used to review the analysis.
3	Edit Header icon - Click this icon to open the Edit Header dialog box and customize the information that is displayed in the Summary report header. See "To customize the Summary report header" on page 251.

- The Run Statistics pane, which displays the _StatInfo.txt file for the sequence alignment project in its entirety. Use the pane's scroll bar to view all the information that is displayed in the pane. (See "_StatInfo.txt" on page 208.)
- The Mutation report pane, which displays the Mutation report in its entirety for the sequence alignment project. Use the pane's scroll bar to view all the report in the pane. Use the Show/Hide icons at the top of the Mutation report pane to show/hide various sections of the report, or the report itself.
- The Coverage Curve report pane, which displays which displays the Coverage Curve report in its entirety for the sequence alignment project. Use the pane's scroll bar to view all the report in the pane. Use the Show/Hide icons at the top of the Coverage Curve report pane to show/hide various sections of the report, or the report itself.
- The Expression report pane, which displays which displays the Expression report in its entirety for the sequence alignment project. Use the pane's scroll bar to view all the report in the pane. Use the Show/Hide icons at the top of the report pane to show/hide various sections of the Expression report or the report itself. Use the Show/Hide icons at the top of the report, or the report pane to show/hide various sections of the report, or the report itself.
- The Structural Variation report pane, which displays which displays the Structural Variation report in its entirety for the sequence alignment project. Use the pane's scroll bar to view all the report in the pane. Use the Show/Hide icons at the top of the Structural Variation report pane to show/hide various sections of the report, or the report itself.
- The Distribution report pane, which displays which displays the distribution coverage information for the sequence alignment project. Use the pane's scroll bar to view all the information in the pane.



The order in which the various reports are displayed in the Summary report when the report <u>first</u> opens is determined by the order in which you selected the reports on the Summary Report Settings dialog box. Use the scroll bar on the viewer to scroll through the reports. You can rearrange the order in which the reports are displayed. See "To modify the Summary report view" below.

To modify the Summary report view

Figure 6-92:	Summary Report	Settings	dialog box
1 igui o o o <u>c</u> .	Canninary respond	ootango	analog box

Summary Report Settings		×
	Remove	Add Remove All
	<u>0</u> K	Cancel

You can do the following on the Summary Report Settings dialog box to modify the Summary report view:

- Remove reports—To remove a report from the Summary report, click Remove for the report. To remove all reports in a single step, click Remove All.
- Load a different Settings file—To load a different Settings file for a report, click Set to open the Load Settings file dialog box, and then browse to and select a different Settings file for the report.
- Change the display order of the reports—To change the order in which the various reports are displayed in the Summary report, you can change the selections on the report dropdown lists, or you can use the Up and Down options for the reports.



If you change the order by changing the selections on the report dropdown lists, you must also remember to load the correct Settings file for the reports. See Load a different settings file above.

- Add a report to the Summary report—To add a report to the Summary report, do the following:
 - i. Click Add to open a new report dropdown list on the Report Settings dialog box.
 - ii. Select the appropriate report on the dropdown list.
 - iii. Click Set to open the Load Settings file dialog box, and then browse to and select a different settings file for the report.



You can generate and save multiple versions of different reports, or multiple versions of the same report as long as each report version uses a different Settings file.

- Edit the settings file for a report—To edit the current settings file for a report, do the following:
 - i. Click Edit for the report to open the <Report> Settings dialog box, and then edit the settings for the report as needed.
 - ii. Click Save Settings to save the modified settings to a new report settings file, or overwrite the existing report settings file.
 - iii. Click Cancel to close the <Report> Settings dialog box.
 - iv. Click Set to open the Load Settings file dialog box, and then browse to and select the report settings file that you just saved.
- Define a custom report name—To define a custom name for a report that can be displayed in lieu of the default report name (for example, Project A report instead of Mutation report) in the Summary report view, do the following:
 - i. Click Edit for the report to open the <Report> Settings dialog box, and then open the Summary Report tab on the dialog box.
 - ii. In the Report Name field, enter the custom name for the report.
 - iii. Click Save Settings to save the modified settings file to a new report settings file, or overwrite the existing report settings file.
 - iv. Click Cancel to close the <Report> Settings dialog box.
 - v. Click Set to open the Load Settings file dialog box, and then browse to and select the report settings file that you just saved.

To customize the Summary report header

Two types of headers can be displayed in the Header pane for the Summary report—a Custom header and Default header. The Custom header displays default information— Software, Company, Address, Phone, Fax, Website, Email—that is defined in the DefaultHeader.inf file or custom information that you can specify using the Edit Header function. You typically customize the information that is displayed in a header to better reflect your project, your business organization, and so on. The Default header displays the following information about the project—Project Name, Date Created, Date Modified, the NextGENe Version that was used to run the analysis, and the NextGENe Viewer Version that was used to review the analysis.


1. Click the Edit Header icon.

The Edit Header dialog box opens.

Figure 6-93: Edit Header dialog box

Software	NextGENe
Company	SoftGenetics LLC
Address	100 Oakwood Ave, Suite 350, State College, PA 16803 USA
Phone	814-237-9340
ax	814-237-9343
Vebsite	http://www.softgenetics.com
Email	tech_support@softgenetics.com

- 2. Do one of the following:
 - Modify any of the default information in either column.
 - Click Load to open an Open dialog box, and browse to and select an existing custom header file to load. (A header file has a .inf extension.)



- 3. Optionally, add or delete rows of information as needed.
 - To delete a row from the header, right-click on the row, and then click Delete a Row.
 - To insert a row into the header, right-click on the row that is to be located below the inserted row, and then click Insert a Row.
 - To add a row as the last row in the header, right-click on any row, and then click Add a Row.
- 4. Do one of the following:
 - Click Save to save the header file as a custom .inf file.
 - Click OK to save the Default Header.inf file. The changes that you make will be displayed by default in every header for every Summary report that you generate.

Matched/Unmatched report

The Matched/Unmatched report displays a list of all reads that did not match to the reference. The report also shows the total number of reads that matched to the reference and the total number of reads that did not match to the reference as well as the read title and the sequence for all unmatched reads. To save the reads to a .fasta file, click the Save Report icon in the report toolbar. A default name is provided for the file, but you can change this value.

Software	NextGENe V 2.10	
Project Name	SRR018422_converted_Output.pit	
Date/Time	1/7/2011 10:52:26 AM	
	Matched:1027900	Unmatched:272958
Index	Title	Sequence
1	>SRR018422.2_FWGR3X101AEE3E_length=45	CTTGCTGACATGTATGTGAGTGATGACTGAACTTCAGGTGAACTG
2	>SRR018422.4_FWGR3X101A2NEY_length=225	TTTTTTAGTAGAAATGGGGTTTCGACTACATTGGCCAGATTAGTCTTGAACTCCTGACCTT
3	>SRR018422.5_FWGR3X101EWKYM_length=54	TTGTCCACAGGAACCATGAGGATCCAGAATTCTCGAGCTGAGACACGCAAC
4	>SRR018422.6_FWGR3X101AEYW9_length=85	CTCGAGAATTCTGGATCCTCATGCTCAGTGCTGCCAGGCCATCGATCCTATGGGCCGGTG
5	>SRR018422.7_FWGR3X101D87RW_length=57	CTCGAGATTCTGGATCCTCTGCTCACCGAGTCTTGGTAGTACTTACCGAGTC
6	>SRR018422.9_FWGR3X101B5P0U_length=65	CTCGAGATTCTGGATCCTCGTTCTCTCTCCTGCTCCACCATTGTGAAGATATGCCTGGT
7	>SRR018422.10_FWGR3X101AUHJQ_length=120	CTCGAGAATTCTGGATCCTCCACACACGCCAGTAACCTGTATGAAACGTGACAACACCTAC
8	>SRR018422.11_FWGR3X101DWQ8I_length=86	CTCGAGAATTCTGGATCCTCCATGACATACCAGAATCTCTGGGACACAGCT
9	>SRR018422.12_FWGR3X101BLSZR_length=63	CTCGAGAATTCTGGATCCTCACGGAATGGAATGGATAGG
10	>SRR018422.13_FWGR3X101AF4CA_length=89	TTATTGATTTCACCATTTAATTACATGTACTACCATGGTCAATTAA
11	>SRR018422.14_FWGR3X101BA28E_length=82	CTCGAGAATTCTGGATCCTCGACAGAGCAAGACTCCGTCTACAAAAAAA
12	>SRR018422.16_FWGR3X101BU9K3_length=73	CAATAATGAACTCACTTGACACAGATGAAATAAGTCTCCACAAGAACAATTGTCTGAGGAT
13	>SRR018422.17_FWGR3X101AKKU1_length=87	CTCGAGAATTCTGGATCCTCAAGATAGAGAGTAGACTGTGGTTAGCAGAGGCCCAGGAGG
14	>SRR018422.18_FWGR3X101AH7LN_length=90	TGAATTGAATGATGGACGTCATCATCGAATAGGAGTTCGTAATAGGAAGTACATCGAATAA
15	>SRR018422.19_FWGR3X101DW3H2_length=49	CTCGAGAATTCTGGATCCTCAGGCATGCACCACCATACCAGGCTAA
16	>SRR018422.20_FWGR3X101BF25U_length=77	CTCGAGATTCTGGATCCTCATACGCACCACACACACATATCACCACAGATTACACACCACAC
17	>SRR018422.21_FWGR3X101D6HNA_length=59	CTCGAGAATTCTGGATCCTCTTCAACGTCATCAGTCATTAAG
18	>SRR018422.22_FWGR3X101CQEFQ_length=26	CTCGAGAATTCTGGATCCTCGTCCTCAAGGTTCACCCATGTGTCAGAATTTTCTTCCTTTT
19	>SBB018422.23_EWGB3X101B9A8S_length=56	CTCGAGATTCTGGATCCTCTGCCTCGGCAACAGCTCTGGGGTCTCTTTGTAGAATGC

Figure 6-94: Matched/Unmatched report example

Distribution report

By default, the Distribution report shows the coverage distribution across the whole reference sequence. If you are carrying out targeted sequencing and want to view the coverage distribution for specific regions, then you can use the option to load a BED file.



To load a BED file, on the Distribution report menu, click File > Load BED file. For detailed information about a BED file, see "BED file" on page 463.

The Distribution report provides four different charts that display coverage information for the alignment project. All four charts display information for both forward and reverse reads, with the forward reads represented in blue and the reverse reads represented in red. The reverse coverage is stacked on top of the forward coverage.




Figure 6-95: Distribution Report example

From top to bottom, the charts display the following unique information:

- For projects that include condensation, the Original Coverage chart displays the coverage distribution for the original reds that were used for condensation. For projects that did not include condensation, the chart is not displayed.
- The Directional Coverage chart displays the coverage of the reads across the reference sequence.

- The Sequence Starting Location chart displays the distribution of the sequence starting points.
- The Read Length Distribution chart shows the distribution by read lengths.


The report is interactive.

• To change the view (which charts are displayed and which are not), on the report menu, click View, and then on the View menu, clear the selections for the charts that you do want to display.



The Original Coverage option is displayed on the View menu only if you are viewing condensed data.





To save the exact coverage information for any location or region, on the report menu, click File > Save Coverage to open the Save Coverage Settings dialog box, and on the General tab, specify how to save the coverage information. Optionally, you can click Load Settings and browse to and select a Settings file (.ini file) to save the coverage information based on the saved settings in the file.

Figure 6-97: Save Coverage Settings dialog box, General tab

eral Summary Report	
🕫 Condensed 🤄 Original	
Input Region Manually	
Start 1	
End 1000	
Input Points of Interest Text File (*.txt)	
	Bel
Input Region of Interest BED File (*.bed)	_
	Set
Save Davelege for R01	
Save Coverage for Entire Reference Range	
Ignore the Uncovered Regions	
tep. 1	
MR 1.	

Setting	Description
CondensedOriginal	Available only if the project included condensation. Indicate to save coverage for either condensed reads or original reads.
Specify the coverage region of the following:	n for which you want to save the coverage settings. You can select one
Input Region Manually	 Input the region manually. (You must specify the starting position and the ending position.)
Input Points of Interest Text File (*.txt)	 There are no special requirements for uploading a comma-delimited text file. If the input text file is a comma-delimited text file, it must contain one of the following lists:
	 Specific reference locations (position number or a range of positions (start position number - end position number)) separated by commas
	A list of reference gene names separated by commas
 Input Region of Interest BED File (*.bed) 	• A BED file is a tab-delimited text file. You can upload a BED file only if the reference sequence contains chromosome information, which means that the reference sequence must be either a preloaded reference that NextGENe supplies, or a GenBank reference file that contains chromosome information. Each row in the file contains a region of the reference that is to be used for the report, and at a minimum, the file must contain the following information:
	Field #1 - Chromosome number for the region
	 Field #2 - Chromosome start position Field #3 - Chromosome end position
	Note: Field #4, which is used for the Description column, is optional.
Save Coverage for ROI	 Save the coverage information based on Regions of Interest as defined in the GenBank reference file.
	Note: For information about creating Regions of Interest in a GenBank reference file, see "Advanced GBK Editor tool" on page 280.
Save Coverage for Entire Reference Range	 If you select this option, then coverage is saved for the entire region, which means that you do not need to manually specify a range.
Ignore the Uncovered Regions	Select this option to exclude uncovered regions from the Save Coverage Settings report.
Step	You must set the Step value, which is the increment (for example, >1) at which the coverage is to be measured.
Average Sum	Report the coverage as either the average value for a region or the sum total of all covered bases across the region.
	Note: If Step =1, there is no difference between the two options because the coverage for every base is reported.

- Optionally, open the Summary Report tab and do one or both of the following as needed:
 - Specify an alternate name for the Distribution report when it is displayed in the Summary report.
 - Clear the options for the sections of the Distribution report that are *not* to be included in the Summary report.

Figure 6-98: Save Coverage Settings dialog box, Summary Report tab

Re	port Name:
Г	Display(Dirginal)Collected
V	Display Directional Coverage
V	Display Sequence Starting Location
V	Display Read Length Distribution
V	Display Table



You must click Save Settings to save these settings in a Settings file (.ini file). These settings are applied to the Distribution report only if you select this Settings file during the setup of the Summary report. See "Summary report" on page 246.

Coverage Curve report

The Coverage Curve displays the coverage distribution of sample reads along the reference sequence *without directional information* and reports low coverage regions. The report is useful for identifying regions that were not adequately sequenced because of low coverage. If the project used condensation, then the report displays the condensed coverage information. If you are carrying out targeted sequencing, then to view the coverage distribution for specific regions, use the option to load a BED file. If you used PCR amplicons to obtain sequencing data, you can create and upload amplicon text files for analysis.



The following procedure describes how to set up a new Coverage Curve report. Optionally, you can click Load Settings to browse to and select a Settings file (.ini file) to generate the report based on the saved settings in the file.

1. On the Reports menu, click Coverage Curve.

The Coverage Curve report opens. Two options are possible:

- If post-processing options were *not* used to specify a Settings file for the report, then by default, the *first* time that the report opens for a sequence alignment project, it displays all the low coverage regions across the entire reference with a low coverage threshold that is equal to the total coverage threshold that was specified in the Mutation Filter settings for the project regions. (See "Mutation Filter settings" on page 137.)
- If post-processing options *were* used to specify a Settings file for the report, then by default, the *first* time that the report opens for a sequence alignment project, the settings that are specified in the loaded settings file are applied. If multiple Coverage Curve reports were selected in the post-processing settings, then the first loaded Settings file is applied.

After you change any of these default values for a project, NextGENe "remembers" these values and generates the report accordingly. See "Coverage Curve report example" on page 259.




Figure 6-99: Coverage Curve report example



Reference sequence regions that are highlighted in red indicate regions where the coverage falls below the user-set mutation filter coverage threshold. The highlighted regions are useful for identifying large deletions or regions where *PCR* failed. Detailed information for each highlighted region is displayed in the report table below the graph.

2. On the report menu, click Settings > Settings.

The Coverage Curve Settings dialog box opens. The General tab is opened by default.

Figure 6-100: Coverage Curve Settings dialog box, General tab

Input amplicon TEXT file (*.txt)		
		스러리
		<u>To</u> etne y g
		$(ene_{\hat{Z}}) \ge ($
Input region of interest		
🗭 Use riði cennal in BLU Na		
C\Deta\Demo_Data\Ukumina\Haloplek\Cardiac.be	d	191
C The end constructerence has		-
🕐 Ure devilge		
Coverage setting		

3. To define the regions of the reference that are to be used for reporting low coverage regions, do one or both of the following as applicable:

Action	Step
Load an Amplicon Text file for analysis	Select Input amplicon TEXT File (*.txt), and then click Add to browse to and select the appropriate Amplicon text file. You can load multiple Amplicon text files.
	An Amplicon text file must be a tab-delimited text file with the following format:
	 From left to right, the column headings are: Amplicon ID, Start, and End. Each column heading must be separated by a tab.
	 Enter the values for each amplicon in a separate row, with a tab between each value. Use reference positions for Start and End fields.
	Save the file as a tab-delimited text file.
	Figure 6-101: Amplicon text file example
	Amplicon ID Start End
	12 1 80 22 70 190
	22 10 190
Load Regions of Interest for	Select Input Region of Interest, and then do one of the following:
analysis	 To load a BED file, select Use ROI Defined in BED Files, and then click Set to browse to and select the appropriate BED file.
	Note: For information about the required format for a BED file, see "BED file" on page 463.
	 To use Regions of Interest that are defined in GenBank reference files, select Use ROI Defined in Reference Files.
	 To use Regions of Interest that are relative to the contigs of the reference, click Use contigs.
	Note: This option is appropriate if you are using a reference that was recreated from a BED file for custom amplicons.

4. Define the Coverage settings for the project.

Option	Description
Define the low coverage threshold for including regions in the report,	Enter the cut-off value in the Highlight Coverage field.
Use Original Coverage Settings	Available only for Condensation projects. Select this option to use original coverage values for generating the Coverage Curve report instead of condensed reads coverage.

5. Optionally, open the Display tab and select the columns that are to be included in the report (by default, all columns are included), or clear the options for the columns that are not to be included. See Figure 6-102 on page 261.

Length	Reference Position Start	Reference Position End
Description	🔽 Chr	
	Chr Position Start	🗁 Chr Position End
	I [™] Gene Start	🗁 Gene End
	IT CDS Start	F CDS End
	F HGVS Start	F HGVS End
	F RNA Accession Start	T RNA Accession End
	Protein Accession Start	F Protein Accession End

Figure 6-102: Coverage Curve Settings dialog box, Display tab

Column	Description
Length	The total length of the low coverage region.
Description	If this option is selected and you have loaded:
	 A BED file, then, when available, information in Column 4 for the file is displayed.
	 An amplicon text file, any description that you have entered in the amplicon text file is displayed.
Reference Position Start	The starting location for the low coverage region in the reference.
Chr	The name of the chromosome on which the low coverage region is located.
Chr Position Start	The base number that indicates where the low coverage region starts in the chromosome.
Gene Start	The name of the gene where the low coverage region starts.
CDS Start	The CDS number where the low coverage region starts.
HGVS Start	The HGVS nomenclature for the start of the low coverage region.
RNA Accession Start	The RNA accession from NCBI for the gene at the start of the low coverage region.
Protein Accession Start	The protein accession from NCBI for the gene at the start of the low coverage region.
Reference Position End	The ending location for the low coverage region in the reference.
Chr Position End	The base number that indicates where the low coverage region ends in the chromosome.
Gene End	The name of the gene where the low coverage region ends.
CDS End	The CDS number where the low coverage region ends.
HGVS End	The HGVS nomenclature for the end of the low coverage region.
RNA Accession End	The RNA accession from NCBI for the gene at the end of the low coverage region.

Column	Description
Protein Accession End	The protein accession from NCBI for the gene at the end of the low coverage region.

6. Optionally, open the Summary Report tab and specify how the Coverage Curve report is to be named and which of its information is to be displayed in the Summary report.



You must save these settings in a Settings file (.ini file). These settings are applied to the Coverage Curve report only if you select this Settings file during the setup of the Summary report. See "Summary report" on page 246.

Figure 6-103: Coverage Curve Report Settings dialog box, Summary report tab

Coverage Curve Settings	×
General Display Summary Report	
Report Name:	
✓ Display Coverage Curve	
✓ Display Target Region Statistics	
✓ Display Coverage Report	
Save Settings Load Settings DK	ncel

Setting	Description
Report Name	The name that is displayed for the Coverage Curve report in the Summary report.
Display Coverage Curve	Display the coverage curve in the Summary report.
Display Target Region Statistics	Display the target region statistics in the Summary report.
Display Coverage report	Display the coverage information in the Summary report.

- 7. Optionally, click Save Settings to save the settings for this report in a Settings file (.ini file). You can use a saved Settings file to specify the post processing options for a project in:
 - The Project Wizard. See "To specify the post-processing options for a Sequence Alignment project" on page 64.
 - The NextGENe AutoRun Tool. See Chapter 9, "The NextGENe AutoRun Tool," on page 391.
 - The Summary report. See "Summary report" on page 246.

8. Click OK to generate the report.

The report is interactive:

• To zoom in the graph view, hold down the left mouse button and draw a box from the upper left hand corner of any region in the graph towards the lower right hand corner. A box is formed around the area that being reduced for viewing.




After you zoom in on a region, you can use the use right mouse button to scroll the region.


• To zoom out the graph view, hold down the left mouse button and draw a box from the lower right hand corner of any region in the graph towards the upper left hand corner.



The magnification for zooming out is always 100%.

- To save Low Coverage Region information to a text file, on the report menu, click File > Save Coverage Report, or on the report toolbar, click the Save Report icon . A default name and location are provided for the file, but you can change both of these values.
- After you load a BED file and generate the Coverage Curve report for the file, on the report menu, you can click File > Target Region Statistics, or on the report toolbar, you can the Target Region Statistics icon III to open the Target Region Statistics dialog box. This dialog box displays summary coverage information for the BED file regions. You can click the Save Report icon III at the top of the dialog box, or you can click File > Save Target Region Statistics to save the target region information to a text (*.txt) file.





• If you have a subscription to Pathway Studio, then right-click a region in the report, and on the context menu that opens. select View in Pathway Studio to import the gene for the region into Pathway Studio and visualize the biological pathway information for the gene.



Before you can use the Coverage Curve report in conjunction with Pathway Studio, your Pathway Studio access option must be set for the NextGENe Viewer. See "Process" in "NextGENe Viewer main menu" on page 142.

• To modify the report settings, on the report toolbar, click Settings > Settings to open the Coverage Curve Settings dialog box and modify the report settings as needed. The report display is dynamically updated after you save the modifications.

Mismatched Base Numbers report

The Mismatched Base Numbers report displays the counts of reads that aligned anywhere to the reference sequence and that showed a given number of mismatches when aligned.

Figure 6-105	Mismatched Base Numl	hers report example
1 iyure 0-100.	IVIISITIALUTIEU DASE IVUITI	

Mismatched	Base Number
4,400,000	
4,200,000	
4,000,000-	
3,800,000-	
3,600,000-	
3,400,000-	
3,200,000-	
3,000,000-	
2,800,000-	
2,600,000-	
2,400,000-	
0 2,200,000-	
2,400,000- 2,200,000- 2,200,000- 2,000,000-	
1,800,000-	
1,600,000-	
1,400,000-	
1,200,000-	
1,000,000-	
800,000-	
600,000-	
400,000-	
200,000-	
0-	1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 Number of Mismatches

The report is interactive.

• To zoom in the graph view, hold down the left mouse button and draw a box from the upper left hand corner of any region in the graph towards the lower right hand corner. A box is formed around the area that being reduced for viewing.



After you zoom in on a region, you can use the use right mouse button to scroll the region.

• To zoom out the graph view, hold down the left mouse button and draw a box from the lower right hand corner of any region in the graph towards the upper left hand corner.



The magnification for zooming out is always 100%.

Expression Report

The Expression report provides expression levels/coverage for different regions of the reference genome, which is critical information that is needed for expression studies such as small RNA analysis and transcriptome studies. If you have a subscription to Pathway Studio, then for any sequence alignment project, you can import the report data for a single gene or all genes into Pathway Studio and view the associated biological pathway information.



Before you can use the Expression report in conjunction with Pathway Studio, your Pathway Studio access option must be set for the NextGENe Viewer. See "Process" in "NextGENe Viewer main menu" on page 142.



The following procedure describes how to set up a new Expression report. Optionally, you can click Load Settings to browse to and select a Settings file (.ini file) to generate the report based on the saved settings in the file.

1. On the Reports menu, click Expression Report to open the Expression Report Settings dialog box. The General tab is opened by default.

Figure 6-106: Expression Report Settings dialog box, General tab

General Display Filters S	ummary Report		
Regions			
Use segments as defined	ed in reference files		
C Contig	C 80)	F Amplican	
Gene	C mBNA	CDS	
C Continuous mRNA	C Continuous CDS		
C Set incremental segment	nt length 10000	bases	
	r thunaise	bax	Set
(F. Loria	r thunaise	hase;	Ser
C Input region of interest	r thunaise	fges:	Set
C Input region of interest	(".bed)	hge:	Şer

2. Specify how you want to define the segments that are to be analyzed for the report.

Option	Description				
Use segments as	Contig - Report coverage levels for each contig.				
defined in the reference files.	Note: This option is appropriate if you are using a reference that was recreated from a BED file for custom amplicons.				
	 ROI - Enabled only if you have loaded a project with Regions of Interest defined in a GenBank reference file. Report coverage levels based on Regions of Interest that are defined in the GenBank reference file. 				
	Note: For information about defining Regions of Interest in a GenBank reference file, see "Advanced GBK Editor tool" on page 280.				
	• Amplicon - Available only if an amplicon BED file was loaded during the Load Data step for the project. (See "To set ROI regions from a BED or GBK file" on page 58.) For overlapping amplicons, each read is counted only for its intended amplicon, where the intended amplicon is determined by the percentage of the amplicon that the read covers. The amplicon with the higher coverage is selected as the intended amplicon.				
	Gene - Report coverage levels for each gene region.				
	 mRNA - Report coverage levels for each mRNA region. (Coding and non-coding exons.) 				
	CDS - Report coverage levels for each coding region.				
	 Continuous mRNA - Report coverage levels for the entire mRNA region for a gene, one region per gene. 				
	 Continuous CDS - Report coverage levels for the entire coding region for a gene, one region per gene. 				
Set incremental segment length	Specify the segment length, relative to either the reference positions in the contig or the chromosome positions.				
Input region of interest (*.bed)	You can upload a Region of Interest file in a BED format. Note: For information about the required format for the BED file, see "BED file" on page 463.				

3. Optionally, select one or both Limit options and if needed, modify the default limits (200 bp) for reporting the coverage for only the first or last "x" number of bases of the selected segment type.



If any Limit option and CDS are selected, then the coverage levels for the first or last "x" number of bases in each CDS region is reported.

4. Optionally, open the Display tab and select the columns that are to be included in the report, or clear the options for the columns that are not to be included. See Figure 6-107 on page 267.

Index □ Cescaption Image: Chr □ Contig Image: Chr □ Contig Image: Chr □ Locus Tag Image: Chr □ Start Image: Chr □ Start Image: Chr □ End Image: Chr □ Chr Image: Chr □ Chr Image: Chr □ Chr Image: Chr □ Reference Ling Image: Chr □ Chr Image: Chr □ C	Min Coverage Max Coverage Average Coverage Minimum Forward Read Coverage Minimum Reverse Read Coverage Minimum Reverse Read Coverage Read Counts Forward Read Read Counts Forward Read Read Counts Forward Read Read Counts Forward Read Read Read Read Read Read Read Rea
---	--

Figure 6-107: Expression Report Settings dialog box, Display tab

Column	Description
Index	An ordered count of the segments that are used in the report.
Chr	
NameNumber	 The name of the chromosome on which the segment is located.
	The number of the chromosome on which the segment is located.
Chr Position Start	The base number that indicates where the segment starts in the chromosome.
Chr Position End	The base number that indicates where the segment ends in the chromosome.
Gene	The gene name for the segment when the segment is the whole gene or the name of the gene on which the segment is found.
CDS	The coding sequence number for the segment.
Description	Available if the reference file is a .fasta file with multiple segments. Select this option to display the title line for each segment in the Description column.
Contig	The contig that the segment is on. The contig is based on the genome assembly from the NCBI.
Locus Tag	An alternate way to identify the gene.
Start	The starting location for the reference region.
End	The ending location for the reference region.
Reference Length	The total length of the reference region, which provides for easy identification of expressed regions by size (such as when locating small RNA transcripts).

Column	Description		
	-		
Min Coverage	The minimum number of reads that aligned at any single position within the reference region.		
	Note: For projects that also used condensation, this column shows the minimum number of condensed reads.		
Max Coverage	The maximum number of reads that aligned at any single base position within the reference region.		
	Note: For projects that also used condensation, this column shows the maximum number of condensed reads.		
Average Coverage	The average coverage for the reference region, which is calculated according to the following:		
	Total Number of Bases Aligned to the Region/Region Length		
	Note: For projects that also used condensation, this calculation uses the total number of bases in the condensed reads.		
Minimum Forward Read Coverage	The minimum number of forward reads that aligned at any single position within the reference region.		
Minimum Reverse Read Coverage	The minimum number of reverse reads that aligned at any single position within the reference region.		
Read Counts	The total number of reads aligned to the indicated reference region.		
	Note: The middle base of a read must be aligned to the region to be counted. If only the end of the read is aligned to the region, then the read is not counted.		
	Note: For projects that also used condensation, this is the total number of condensed reads.		
Forward Read Counts	The number of forward reads aligned to the indicated reference region.		
	Note: The middle base of a read must be aligned to the region to be counted. If only the end of the read is aligned to the region, then the read is not counted.		
Fragment Counts	Applicable only if the project used paired read data. Counts each paired read as one fragment instead of each individual read being counted.		
RPKM	Reads per Kilobase Exon Model per Million mapped reads. RPKM = 10^9 * R / (T*L)		
	where:		
	R = Number of mapped reads in a region		
	• T = Total number of mapped reads.		
	• L = Length of the region.		
	Normalizes the expression levels based on the length of the reference region and the total number of aligned reads.		
RPK	Reads that mapped to the indicated segment divided by the total number of mapped reads and then multiplied by 1000. Normalizes the expression levels based on the total number of aligned reads.		

Column	Description
FPKM	Applicable only if the project used paired end data. Fragments per Kilobase of exon per Million mapped reads.
	FPKM = 10^9 * F / (T*L)
	where:
	• F = Number of mapped fragments in a region and:
	 A "fragment" corresponds to a pair of reads.
	Single reads are not counted.
	 The position of a fragment is the location between the two 5' ends of the pairs.
	 T = Total number of mapped fragments.
	 L = Length of the region.
	Normalizes the expression levels for paired end data based on the length of the reference region and the total number of aligned reads.
Original Max Counts	Applicable only if the project also used condensation.
Original Average Counts	Applicable only if the project also used condensation.
Original Read Counts	Applicable only if the project also used condensation.

5. Optionally, open the Filters tab, and then specify the filter settings for the report. Only those genes that have the FPKM values or the RPKM values that fall within the indicated range are displayed in the report.

Figure 6-108: Expression Report Settings dialog box, Filters tab

General Display	Filters	Summary Rep	port
F FRM	From	0.10	T a 20000.00
	From:	0.10	Tb: 20000.00



FPKM is available only if the project used paired end data.



Setting filters is particularly useful for limiting the number of genes that are imported into Pathway Studio for visualization of the biological pathway information.

6. Optionally, open the Summary Report tab, and specify how the Expression report is to be named and which of its information is to be displayed in the Summary report.



You must save these settings in a Settings file (.ini file). These settings are applied to the Expression report only if you select this Settings file during the setup of the Summary report. See "Summary report" on page 246.

Figure 6-109: Expression Report Settings dialog box, Summary Report tab

Expressio	n Report	Setting	s				×
General	Display	Filters	Summary Report				
Rep	ort name	Express	sion Report				
V	Display e	pression	report summary				
V	Display e	pression	report				
	Save S	ettings	Load Settings	(OK	Ca	ncel

Setting	Description
Report Name	The name that is displayed for the Expression report in the Summary report.
Display Expression Report Summary	Display the summary information for the Expression report in the Summary report.
Display Expression Report	Display the expression information in the Summary report.

- 7. Optionally, click Save Settings to save the settings for this report in a Settings file (.ini file). You can use a saved Settings file to specify the post processing options for a project in:
 - The Project Wizard. See "To specify the post-processing options for a Sequence Alignment project" on page 64.
 - The NextGENe AutoRun Tool. See Chapter 9, "The NextGENe AutoRun Tool," on page 391.
 - The Summary report. See "Summary report" on page 246.

8. Click OK to generate the report.

Figure 6-110 [.]	Expression (report exampl	e (not for	SAGE studies)
1 iguio 0 1 io.	LAPICOOICIII	opon oxumpr	0 (1101 101	

File Settings											
.											
Software	NextGENe V]_
Project Name	SRR018422_										╞
Date/Time	1/7/2011 12										1
Total Reads	1300858										1
Matched Reads	1027900										1
Instrument	Illumina										1
Application	SNP/Indel D										1
Index	Contig	Chr	Chr Position	Chr Position	Gene	Locus Tag	CDS	Start	End	Lengt	ł
1	NT_113796	1	142184340	357521				1	251648	25164	-
2	NT_077912	1	357522	358460	OR4F16; +		1	251649	252587	939	1
3	NT_077912	1	357522	358460	OR4F16; +		1	251649	252587	939	1
4	NT_077912	1	357522	358460	OR4F16; +		1	251649	252587	939	1
5	NT_077912	1	358461	142558666				252588	477976	2253	8
6	NT_113797	1	142558667	142559404	PPIAL4G; ·		1	477977	478714	738	1
7	NT_113797	1	142559405	143011870				478715	546178	6746	-
8	NT_077932	1	143011871	143052130	LOC728855:		1	546179	586438	4026	ł



The Expression report results for SAGE studies are different from the results for other Expression reports. See "Expression report for SAGE studies" on page 272.

The report is interactive:

- To sort the report results, double-click any column heading.
- To view a position or region in the Alignment viewer, double-click any value in any column.
- To import a selected gene into Pathway Studio for visualization of its biological pathway information, right-click the gene, and on the context menu that opens, select View in Pathway Studio.
- To import *all* the genes that are displayed in the report into Pathway Studio for visualization of the biological pathway information, on the report main menu, click File
 > Upload gene list to Pathway Studio.
- To copy any information in the report (a single cell or multiple cells, a row or rows, or a column or columns) to your clipboard, select the cells, rows, or columns, right-click any selection, and on the context menu that opens, click Copy. You can then use the standard Paste commands to paste the copied information into a third-party product such as Microsoft Word or Excel.
- To save the report to a text (*.txt) file, on the report menu, click File > Save, or on the report toolbar, click the Save Report icon . A default name and location are provided for the file, but you can change both of these values.

• To modify the report settings, on the report menu, click Settings > Settings to open the Expression Report Settings dialog box and modify the report settings as needed. The report display is dynamically updated after you save the modifications.

Expression report for SAGE studies

The Expression report for SAGE Studies provides expression levels/coverage for different regions of the reference genome, which is critical information that is needed for SAGE studies. To generate the Expression report for SAGE studies, you must load SAGE study project into the NextGENe Viewer, and then on the NextGENe Viewer toolbar, click the Expression report for SAGE studies icon +

Figure 6-111: Expression report example (for SAGE studies)

Index	Position	Gene Name	Chromosome	Sequence	Occuring Counts	# of Gene Ambiguities	Expression
457	12q23-q	Uracil-DNA		GGCCCACA	0	1(456)	18
458	12q23-q;	Uracil-DNA		AGATATATA	72	3(459,32778,32779)	18
459	3a	Splicing		AGATATATA	0	3(458,32778,32779)	18
460	3a	Splicing		CCCCAATGO	67	1(461)	33

Column	Description
Position	Position of the gene in the genome (as indicated in the reference genome.)
Gene Name	The name of the gene that is represented by the tag.
Chromosome	The chromosome on which the gene is located (as indicated in the reference genome.)
Sequence	The tag sequence.
Occurring Counts	The number of reads with the indicated tag.
	Note: If multiple genes have the same tag sequence, a value is displayed in this column for the first gene with the sequence. A zero is displayed for all subsequent tags.
# of Gene Ambiguities	The number of genes that have this same tag sequence. The number in parenthesis is the index number for the other genes with this tag.
Expression	Defined as:
	Occurring Counts/Total number of genes with the tag
	where: Total number of genes with the tag = (# of Gene Ambiguities + 1)
	Note: If the Occurring Counts = 0, then the value for the Occurring Counts for the first listed index with the same tag is used.

Structural Variation report

When a structural variation occurs, often the result is that reads that are aligned to a region have a high number of mismatches in a localized region that is located to one side of the variation. The Structural Variation report identifies and lists these areas of possible structural variations across the entire reference sequence. The report lists a start position and an end position for each local region that has a high number of mismatches. A position location is provided that indicates where the variation might have occurred.



The following procedure describes how to set up a new Structural Variation report. Optionally, you can click Load Settings to browse to and select a Settings file (.ini file) to generate the report based on the saved settings in the file.

1. On the Reports menu, click Structural Variation to open the Structural Variation Report Settings dialog box. The General tab is opened by default.

Structural Variation Report Settings	x
General Display Summary Report	
 Short Reads (<= 75bp) Long Reads (> 75bp) In CDSs Only +/- 0 Input Region of Interest (*,bed) 	Set
Save Settings	Cancel

Figure 6-112: Structural Variation Report Settings dialog box, General tab


- 2. Indicate whether the data that is being analyzed consists of:
 - Short Reads (\leq 75 bp)
 - Long Reads (> 75 bp)
- 3. To modify the report so that the report displays only those structural variations that are within "x" number of bases on either side of a coding region, select "In CDS Only +/-" and then specify the number of bases.
- 4. If you are carrying out targeted sequencing, and want to view the possible structural variations in specific regions, then select Input Region of Interest (*.bed), and then browse to and select the appropriate BED file.



For information about the required format for the BED file, see "BED file" on page 463.

5. Optionally, open the Display tab and select the columns that are to be included in the report (by default, all columns are included), or clear the options for the columns that are not to be included.





Column	Description
Length	The number of bases that are mismatched to the reference sequence, indicating a possible structural variation.
Avg. Count	The average number of reads that have the mismatches in them.
Sequence	The sequence of the mismatched bases that indicate a possible structural variation.
Comments	If Long Reads is selected, and a region has a count of only one, then the entry for the region in the report is dimmed/unavailable, and "Deleted" is displayed in this column.
Ref Position Start	The position in the reference sequence where the structural variation begins.
Ref Position End	The position in the reference sequence where the structural variation ends.
Chr	The name of the chromosome where the structural variation is found.
Chr Position Start	The starting base number for where the structural variation starts on the chromosome.
Chr Position End	The starting base number for where the structural variation ends on the chromosome.
Gene Start	The name of the gene where the structural variation starts.
Gene End	The name of the gene where the structural variation ends.
Contig Start	The name of the contig where the structural variation starts. The contig is based on the genome assembly from the NCBI.
Contig End	The name of the contig where the structural variation ends. The contig is based on the genome assembly from the NCBI.

6. Optionally, open the Summary Report tab, and specify an alternate name for the Structural Variation report when it is displayed in the Summary report.



You must save these settings in a Settings file (.ini file). These settings are applied to the Structural Variation report only if you select this Settings file during the setup of the Summary report. See "Summary report" on page 246.

Figure 6-114: Structural Variation Report Settings dialog box, Summary Report tab

Structural Variation	on Report Settings		×
General Display	Summary Report		
Report Name			
<u>S</u> ave S	Settings Load Settings	<u>O</u> K	Cancel

- 7. Optionally, click Save Settings to save the settings for this report in a Settings file (.ini file). You can use a saved Settings file to specify the post processing options for a project in:
 - The Project Wizard. See "To specify the post-processing options for a Sequence Alignment project" on page 64.
 - The NextGENe AutoRun Tool. See Chapter 9, "The NextGENe AutoRun Tool," on page 391.
 - The Summary report. See "Summary report" on page 246.
- 8. Click OK to generate the report.

Figure 6-115: Structural Variation report

File	Settings								
Index	Ref Position Start	Ref Position End	Chr	Chr Position Start	Chr Position End	Length	Avg Counts	Gene Start	Gene
1	2284	2297	N/A	2284	2297	14	77.46	thrA	thrA
2	6301	6322	N/A	6301	6322	22	77.90	yaaA	yaa/
3	11383	11392	N/A	11383	11392	10	54.44	yaal	yaal
4	11823	11841	N/A	11823	11841	19	72.78		
5	11857	11876	N/A	11857	11876	20	80.53		
6	11909	11928	N/A	11909	11928	20	61.05		
7	11943	11961	N/A	11943	11961	19	70.33		
8	12009	12026	N/A	12009	12026	18	69.53		
9	13853	13874	N/A	13853	13874	22	63.52	dnaK	dnał
10	21139	21157	N/A	21139	21157	19	80.94		
11	22071	22082	N/A	22071	22082	12	71.18	ribF	ribF
12	24542	24555	N/A	24542	24555	14	82.54	ileS	ileS
13	26723	26746	N/A	26723	26746	24	65.22	ispH	ispH
14	29149	29170	N/A	29149	29170	22	73.10	dapB	dapl
15	31907	31932	N/A	31907	31932	26	79.64	carB	carE
16	31947	31958	N/A	31947	31958	12	63.45	carB	carE
17	35090	35108	N/A	35090	35108	19	60.22	caiE	caiE
18	35843	35854	N/A	35843	35854	12	64.55	caiD	caiD
19	35890	35909	N/A	35890	35909	20	72.79	caiD	caiD



For short reads, the Count column is blank. For long reads, regions where the count is only one are shown in gray and regions where the count is greater than one are shown in blue.

The report is interactive:

- To view a position or region in the Alignment viewer, double-click any value in any column.
- To save the report to a text (*.txt0 file, on the report menu, click File > Save, or on the report toolbar, click the Save Report icon **[]**. A default name and location are provided for the file, but you can change both of these values.
- To modify the report settings, on the report menu, click Settings > Settings to open the Structural Variation Report Settings dialog box and modify the report settings as needed. The report display is dynamically updated after you save the modifications.

Score Distribution report

The Score Distribution report is available from the NextGENe viewer any time after you complete an alignment project. The report shows the number of variants that have a particular score—Overall Score, Coverage Score, Read Balance Score, Allele Balance Score, Homopolymer Score, Mismatch Score, or Wrong Allele Score. The report is applicable only for projects that were created in Version 2.0 or later of NextGENe.




Figure 6-116: Score Distribution report

By default, when the report first opens, Overall Score, Coverage Score, and Read Balance Score are displayed. To change the scores that are displayed, on the report menu, click View, and then select the score that is to be displayed, or clear a selected score to remove it from the report display.



For a detailed discussion about each of the available scores, see "Overall Mutation Score" on page 446.

NextGENe Viewer Tools

Several NextGENe Viewer tools are available that provide additional options for working with the results of an alignment project. After you load a project in the viewer, almost all the viewer tools are available from the Tools menu on the viewer main menu See:

- "Export Sequences tool" on page 278.
- "Export Sequences to CSFASTA tool" on page 279.
- "Advanced GBK Editor tool" on page 280.
- "Peak Identification tool" on page 285.
- "Synthetic SAGE Data tool" on page 288.
- "Create SAGE Library from mRNA tool" on page 289.
- "Modify Titles for mRNA GenBank tool" on page 290.
- "Resume Project and Load Project" on page 290.



For information about the NextGENe Viewer comparison reports and tools, see "NextGENe Viewer Comparison Reports and Tools" on page 291.

Export Sequences tool

You use the Export Sequences tool to generate a .fasta file that contains all the reads that aligned to a specific region in the reference sequence.

Figure 6-117: Export Sequences Settings dialog box

Input Region Ma	a	
Start	End End	1
C Input Points of In	rsterest Text File(*.txt)	
		-
C Input Points of In	isterest BED File(*.bed)	

You can manually set the region length (you must set the starting position and the ending position), or you can upload a Comma-delimited text file or a tab-delimited text file that is in a BED file format.



For more information about the format for a comma-delimited text file or a BED file format, see "Comma-delimited text file" on page 463 or "BED file" on page 463.

Optionally, after you specify the settings for the Export Sequences tool, you can click Save Settings to save the settings to a Settings (.ini) file. You can select this saved general Settings file for post-processing options in:

- The Project Wizard. See "To specify the post-processing options for a Sequence Alignment project" on page 64.
- The NextGENe AutoRun Tool. See Chapter 9, "The NextGENe AutoRun Tool," on page 391.
- The Summary report. See "Summary report" on page 246.

Export Sequences to CSFASTA tool

This tool is available only for SOLiD System data analysis.

You use the Export Sequence to CSFASTA tool to generate a csfasta file for SOLiD System data that contains all the aligned reads for a specified region in color-space format.

Figure 6-118: Export Sequences to CSFASTA Settings dialog box

Export Sequences to C	SFASTA Settings	
 Input Region Mar Start 	ually End	
C Input Points of Ins	terest Text File(*.txt)	Ē
C Input Points of Ins	terest BED File(*.bed)	Ĕ
	<u>S</u> ave <u>L</u> oad	<u>D</u> k

You can manually set the region length (you must set the starting position and the ending position), or you can upload a Comma-delimited text file or a tab-delimited text file that is in a BED file format.



For more information about the format for a comma-delimited text file or a BED file format, see "Comma-delimited text file" on page 463 or "BED file" on page 463.

Optionally, after you specify the settings for the Export Sequences to CSFASTA tool, you can click Save Settings to save the settings to a Settings (.ini) file. You can select this saved general Settings file for post-processing options in:

- The Project Wizard. See "To specify the post-processing options for a Sequence Alignment project" on page 64.
- The NextGENe AutoRun Tool. See Chapter 9, "The NextGENe AutoRun Tool," on page 391.
- The Summary report. See "Summary report" on page 246.

Advanced GBK Editor tool

You use the Advanced GBK Editor tool to view, edit or annotate a GenBank reference file. You can load a .gbk/.txt file which is a file that contains both the annotations and the sequence or you can load the files separately. A .gbs file contains only the annotations (no sequences) and the .fna file contains only the sequence (no annotations). To load the GenBank file that is to be edited/annotated, do one of the following:

- On the GBK Editor window main menu, click File > Open.
- On the GBK Editor window toolbar, click the Load icon 🚘.

Figure 6-119: Advanced GBK Editor window

File Edit Search Tools Output	
==> Number of sections in Gbk file is	s 1 , select current section 1 • Show
E- ■ BRCA1.gbk G- ● Gene E- ● SPCA1 E- ♥ CDS - ● ♥ NP_009225.1 E- ♥ mRNA	Basic Information Sequence
	Legend Gene: MRNA: CDS: SNP: AG CG GT AC AT IT InDel
	-539 -479 -419 -359 -299 -299 -299 -179 -119 -59 1 teracetrea treesate creatives grassoctic pertroofe
	61 GCAACGGAAA AGOGCGGGAA TTACAGAtAA ATTAAAACtG CGACTGCGGG GCGTGAGGTC 121 GCTGAGACT4 CCTGGACGGG GGACAGGCTG TGGGGTTTCT CAGATAACTG GCCCCTGGG Sequence: Base Count: 0: 22778 C: 16555 G: 17839 T: 22657 Ukam 0 Stat Pontion on Chronocome for This Sector: Reset

Continue to the following:

- "GBK Editor tool GenBank Tree File" on page 281.
- "GBK Editor window- Sequence View pane" on page 282.

GBK Editor tool - GenBank Tree File

The left pane in the GBK Editor window is the GenBank Tree File pane. This pane displays all the GenBank file information in a simple tree format. Click the plus (+) and minus (-) symbols to expand and collapse the tree structure, respectively.

Figure 6-120: GenBank Tree File



The GenBank Tree File is interactive. You can:

- Expand the Gene folder to view CDS and mRNA sequences that were identified in the gene.
- Expand the Variations folder to view all the recorded SNPs for the gene. All known variants are displayed in blue in the Sequence View window (the window on the right of the GBK Editor tool).
- Double-click a Variation SNP file to open the Variation Setting dialog box. The Variation Setting dialog box provides detailed information about the selected SNP, including varying alleles and position in the gene. You can do the following in this dialog box:
 - If you know the gene name, you can enter this value in the Gene Name field.
 - To edit the values in the Population ID and Allele fields, you can double-click a displayed value to select it and then modify the value.

If you enter a gene name, or edit any values, you must click OK to save these edits.

Position	Population Are	a Allele	Area Frequen	cy Area
1154	Population ID	Allele1	Allele2	
Gene Name		A	G	
synonym="BRCAI;	N/A	N/A	N/A	
db_xref				
dbSNP:8176077				

GBK Editor window- Sequence View pane

The Sequence View pane is the right pane in the Advanced GBK Editor window. It has two tabs—the Sequence tab and the Basic Information tab. The Sequence tab provides a visual representation of the gene. A color-coded bar chart representing the gene is displayed in the middle pane of the tab. mRNA regions are shown in green and CDS regions are shown in red. SNP locations are indicated by small vertical lines above the bar chart. These lines are also color-coded according to the base change that they represent. The lower pane displays the full sequence for the region. mRNA regions are again displayed in green and CDS regions are again displayed in red. The amino acid sequence is also provided below the CDS sequence. SNPs are displayed in blue.



Basic Information	Sequence	
>BRCA1		-
1		81
		Щ
2 1154409770 1	1399961 13026 1675320331 23965 27811 31381 35104 38883 42809 46504 50418 5395957637 612966497668619 72405 76037 2 3 4 6 7 8 9 10 11 12 13 14 15 16 18 19 20	7967: 22
Legend Ge	ne: mRNA: CDS: SNP: <u>AG_CG_GT_AC_AT_CT_InDel</u>	_
2641	ttgateteet gaeettgtga teeaceegee tgggeeteee aaagtgetag gattacagge	-
2701	ataagccact gogtccagcc attettgtat ttttetgttg tagagatagg gttttgetat	
2761	gttggocatg ctggteteaa acteetgaee teaagtgate taeeeteeet tggeetetea	
2821	aggtgetggg attacaggee tgageeattg cacceageea tggtetaaaa atettgattg	
2881	aaataccace tttteattte eagacaeeee tatttaaaat taecaeaeee eeageaeaea	
2941	ctttatette tatteetget getteteeat aacaetgatt actagetgae attetatgta	
3001	atgtateeat tttttatete tagteeeaca gaatgtaaae teeaggatgg gatttttgtt	
3061	ttgtttacat acatetgtat gtteagtagt tagaaeggta ettgggaeet agttgeeaet	
3121	caataaacat ttgtcaaata aataataaac taaactaaat tagttcttta atttttttaa	
3181	atatggtgat ggttagtagt gagtaacatt caaaaaataa gttgaaaagt tgtaccattg	
3241	cotottacco acaataaaaa agggtaaatt ottttotgot ttatgaaagt tgtttttoat	
3301	atttgaagtc aagttaatca gattaaggaa aatgtatgtt gtgttttcag agcgatacaa	
3361	gatttataaa taaccatoot otocottgoo ottoaacatt atagotaaac aaaaataaga	-
Sequence:	Base Count: A: 22778 C: 16955 G: 17899 T: 23557 Others: 0	
Start Position on	Chromosome for This Section: ReSet	

The Sequence tab is interactive. To search for a specific sequence, on the Advanced GBK Editor Tool main menu, click Search > Find to open the Find Sequence dialog box. You enter the sequence for which to search in this dialog box, and you can also indicate whether to search by the complementary sequence. If the sequence is found, it is displayed in purple and italics in the Sequence tab. (See Figure 6-124 on page 283.)

Figure 6-123: Find Sequence dialog box

	Eind
	Cancel

Figure 6-124: Located sequence in Sequence tab

1081 actititgtt tigttigtt tigttittt gagacaeggt etegetetge tgeetagget

The Basic Information tab displays information about the gene sequence. The information that is displayed on this tab depends on what option is selected in the GenBank Tree file—the gene name, the CDS file name, the mRNA file name, or the Variations folder. If the gene name is selected, then the gene name and region are displayed on this tab. The information also indicates if the sequence is a reverse complement.

Figure 6-125: Advanced GBK Editor tool, Gene name selected

⊡-sa BRCA1.gbk ⊡-sa Gene	Basic Information Sequence	
	Item	Value
⊡ • • CDS	Gene	BRCA1
NP_009225.1	Region	2.>81189
⊡~ <i>∜</i> mRNA	Reverse Complement	false

If the CDS file name is selected, and the Auto Create ROI tool is used, then the Region of Interest row is populated with information that is based on the ROI settings. If the CDS file name is selected, you can also add primer locations to further annotate the file and you can also change the Codon Start position.

Figure 6-126: Advanced GBK Editor tool, CDS file name selected

BRCA1	Item	Value
	CDS	join(13891468,97069759,1895219029,2052920617,2122421363,2560525710,28196
NP 009225.1	Region of Interest	
⊡	Amplicon Id	
₩ NM_007294.3	External primer	
±√>>>>>>>>>>>>>>>>>>>>>>>>>>>>>>>>>>	Internal primer	
	CodonStart	1 🔹
	product	
	protein_id	NP_009225.1
	note	isoform 1 is encoded by transcript variant 1
	translation	MDLSALRVEEVQNVINAMQKILECPICLELIKEPVSTKCDHIFCKFCMLKLLNQKKGPSQCPLCK
	Corresponding_mRNA_Region	NM_007294.3
	Reverse Complement	false

Figure 6-127: Advanced GBK Editor tool, mRNA file name selected

Basic Information Sequence]
Item	Value
Region	join(2214,13701468,97069759,1895219029,2052920617,2122421363,256052571
transcript_id	NM_007294.3
product	breast cancer 1, early onset
note	isoform 1 is encoded by transcript variant 1
Corresponding_CDS_Region	NP_009225.1
	Item Region transcript_id product note

If Variations is selected in the GenBank Tree file, then information about the known SNPs is displayed on the Basic Information tab. This information includes the SNP position, the number of alleles observed, the dbSNP identification and the gene name.

Figure 6-128: Advanced GBK Editor tool, Variations folder selected

	*	Basic Information	Sequence					
# dbSNP:8176075(88) # dbSNP:35436937(complement/)		No	Position	Allele Number	db_xref	Frequency	Gene	
dbSNP:34191881(complement)		1	88	2	dbSNP:8176075	N/A	synonym="BRCAI;	
dbSNP:799905(complement(31)		2	complement(9910	2	dbSNP:35436937	N/A	synonym="BRCAI;	
dbSNP:55680227(complement(:		3	complement(1301	2	dbSNP:34191881	N/A	synonym="BRCAI;	

You can annotate the information in the Frequency column by right-clicking on a cell in the column and on the context menu that opens, selecting Modify Parameter. Options are also available for adding a variation, deleting a variation, and copying a variation (which you can annotate after copying).

N/A 🚽	OUDODUD-"DDCAL
N/A	Modify Parameter
N/A	Add variation
N/A	Delete

Delete

Copy

Figure 6-129: Advanced GBK Editor tool, Context menu

N/A

N/A

Advanced GBK Editor tool - Auto Create ROI tool

You use the Auto Create ROI tool to select a particular region of the gene sequence for use as a Region of Interest (ROI). You can use this ROI for generating reports. To open this tool, on the Advanced GBK Editor Tool main menu, click Tools > Auto Create ROI to open the Create ROI for CDSs dialog box. You define the region of interest by specifying the number of bases on either side of the CDS.

Figure 6-130: Create ROI for CDSs dialog box

Left 🖪	bps
Right 5	bps



If you select the ROI Filter option for the Mutation Report settings on the Filters tab, Annotation sub-tab, the Mutation report displays only those variants that are found in the ROIs that you define. See "Filter tab, Annotation sub-tab" on page 223.

Advanced GBK Editor tool Output Options

- mRNA for gbk—Output the mRNA sequence for the GenBank file. (Introns are not included.)
- Appointed Region—Output only a specified region of the GenBank file.

Advanced GBK Editor tool Save options

On the Advanced GBK Editor tool main menu, click File > Save As to open the Save As dialog box.

Figure 6-131: Save As dialog box

Save as				×		
🗖 Add SNPs	from Annota	ation Database				
Mode						
C Selected	C Selected Gene, and Selected mRNA					
C Current 9	ection					
All Section	ns					
		Ok	Cancel	1		
		<u>u</u> ĸ				

- Add SNPs from the Annotation database—Before saving the annotated GenBank file, add the annotations to the GenBank file from the appropriate whole genome annotation database.
- Selected Gene, and Selected mRNA—Saves only the CDS/mRNA that is selected in the GenBank Tree File as a GenBank file.
- Current Section—Saves only the section that is currently selected and shown in the sequence view.
- All Sections—The default value. Saves all information in all sections of the GenBank file.

Peak Identification tool

You use the Peak Identification tool to identify a list of regions that satisfy the coverage level requirements to be identified as a peak for any alignment project. This includes applications such as ChIP-Seq and or miRNA detection (where you want to locate highly covered regions) as well as any other application where you want to determine the location of regions that occur above a set threshold.



When "ChIP-Seq" is selected as the Application Type, automatic peak detection is applied during the initial processing and peak regions are indicated with brown ticks in the NextGENe Alignment viewer upon project completion. (See Figure 6-134 on page 288.) After automatic peak detection, you can then open the Peak Identification tool and manually specify settings for peak identification as needed.



You can also use the Peak Identification tool to create a reference sequence. See Chapter 7, "Specialized Applications," on page 353.

You can specify that the software automatically identifies such regions, or you can manually set the values for identification. See Figure 6-132 on page 286.

Peak Identification Settings	— ×
Peak Identification:	
Coverage >= 10	ps
Set Baseline of Noise	0 <u> OK</u> <u> Cancel</u>

Figure 6-132: Peak Identification Settings dialog box for peak identification

Manual Setting	Description
Coverage	The coverage threshold for a position to be considered part of a peak.
	Note: Although you can set the coverage level to any value, for ChIP-Seq or miRNA analysis, SoftGenetics recommends a value that is equal to twice the average coverage that is reported in statinfo.txt file.
Gap	Maximum number of bases between regions that meet the coverage threshold to be considered one continuous peak.
Set Baseline Noise	Used in conjunction with the Gap size to determine whether two nearby regions each with a coverage that is above the Coverage threshold are to be merged into one peak, or whether they are to remain as two separate peaks.
	• If the regions are separated by a distance that is less than the Gap size and the coverage in this region exceeds the Set Baseline Noise, then the two nearby regions are merged into a single peak.
	• If the regions are separated by a distance that is less than the Gap size but the coverage in this region does not exceed the Set Baseline Noise, then the two nearby regions remain separated.

After the peaks have been identified in your data, a Peak Identification report is automatically generated. See "Peak Identification report" below.

Peak Identification report

To view this report, on the NextGENe Viewer main menu, click Reports > Peak Identification Report. This report shows all the peaks that were detected across the entire reference sequence. (See Figure 6-133 on page 287.) If you are carrying out targeted sequencing and want to view the peaks for specific regions, then you can use the File > Load BED file option to load a BED file.



For information about the required format for the BED file, see "BED file" on page 463.

	日 火									
Index	Chr	Reference Region	Chromosome Region	Length	Coverage(75	Transcript site	Gene Distance	Sequence		
1	1	14395211440135	142730673.142731287	615	4	1439778.,1439877	None	CAAGGTGGCACAAGAA		
2	1	1507624.,1507918	142798776142799070	295	4	1507721.,1507820	None	AGATGGTTTCATATTG		
3	1	19603061961106	176081. 176881	801	6	1960646.,1960765	None	TCTCGGAGCCGGAGTT		
4	1	3374241.,3375330	3119293731194026	1090	10	33747043374866	PUM1(+117125)	GATATATAGAAAGAGA		
5	1	3443902.,3445455	3126259831264151	1554	8	34445623444794	PUM1(+47000)	TATTGGAAAAAACAAA		
6	1	3470662.,3470736	3128935831289432	75	5	3470662.,3470736	PUM1(+21719)	TATACATTACAAATTTA		
7	1	3686016.,3686088	3150471231504784	73	8	3686016.,3686088	None	TTTGTGTTTTTAGTAG.		
8	1	4478378.,4478540	32297074.32297236	163	7	44784094478508	None	GCTCATGCCTGTAATA		
9	1	4481658.,4482051	3230035432300747	394	4	4481804.,4481904	None	GTGGGCGCCCCTAGTC		
10	1	5432102.,5432166	33250798.33250862	65	5	54321025432166	AK2(+24217)	AGCTGGGCTGGGTGT/		
11	1	6000870.6001002	3381956633819698	133	4	6000886.,6000985	CSMD2(+584332)	AAATACAAAAATTATCT		

Figure 6-133: Peak Identification report example

The report provides the following information:

Value	Description
Chr	The chromosome on which the peak region was found.
Reference Region	The beginning and ending bp for the region based on the overall reference position.
Chromosome Region	The beginning and ending bp for the region based on the chromosome position.
Length	The total length of the region in bp.
Coverage	The 75th percentile of coverage for the region.
Transcript Site	The central regions for peaks that are larger than 100 bp. Each peak end is trimmed by 7.5% of the region length, for a total of 15% of the region length.
Gene Distance	The location of the peak relative to the nearest gene.
	 If a peak overlaps the start of a gene, then "Gene Distance" is listed as 0.
	 If it occurs before a gene, then it is a negative value measuring the distance between the peak and the start of the gene.
	 If it occurs within a gene, then it is a a positive value measuring the distance between the peak and the start of the gene.
	 If it is not located in a gene and the next start of a gene is more than 5,000 bp away, then the distance is listed as "None."
	• The direction of genes is accounted for. For example, a peak is "before" a gene if it occurs at an earlier position than a forward gene or at a later position than a reverse gene. Only the closest gene is reported.
Gene Direction	Not displayed by default. The strand (plus or minus) on which the gene is found.
Read Orientation	Not displayed by default. The percentage of reads that aligned to the region in the forward direction / the percentage of reads that aligned to the region in the reverse direction.
Sequence	The sequence for the peak region.

The report is interactive:

- To save the report to a .fasta file, on the report toolbar, click the Save Report icon **I**. A default name and location are provided for the file, but you can change both of these values.
- To modify the report settings, on the report menu, click Settings > Settings, or on the report toolbar, click the Settings icon not to open the Peak Identification Settings dialog box and modify the report settings as needed. The report display is dynamically updated after you save the modifications.




Figure 6-134: Sequence Alignment results with ChIP-Seq as the selected Application Type

Synthetic SAGE Data tool

You use the Synthetic SAGE Data tool to create to create SAGE data from sequence reads. You must specify the first letter for each SAGE tag and the total tag length. The input data is broken up into sequences of the specified length at each occurrence of the nucleotide that was selected as the first letter for each SAGE tag.

Figure 6-135: Synthetic SAGE Data dialog box

Synthetic SAGE Data	×
Input File	<u>S</u> et
Output File	<u>Se</u> t
Options First Letter T v Reads Length = 17 bps Random Max = 50000	
<u>D</u> k	<u>C</u> ancel

Create SAGE Library from mRNA tool

You use the Create SAGE Library from mRNA tool to create a SAGE library from mRNA sequence input files.

Figure 6-136: Create SAGE Library from mRNA dialog box

		Add
		<u>R</u> emove
		Re <u>m</u> ove Al
Output File		S <u>e</u> t
Options		
Create SAGE Library:	Enzyme Nialli	CATG 17
Tag Sequence: CATG Segment Length(bps): 17	Dpnll	
Supplementary Character if Available Segment is too Short: N		
🔲 Only for PolyA Tail		
Only Output Segments with Gene Names from Following File		
Gene File		<u>S</u> et
🗖 Load mRNA Info File		Seţ
Update Sequence Titles of Input Files with mRNA Info File		

Setting	Description
-	les only a high-level description of the Synthetic SAGE Library from mRNA Genetics for assistance with this tool.
Only for PolyA Tail	If this option is selected, then the software checks the last 20 bps of the mRNA sequence and if there are not seven consecutive "A" bases, the sequence is not included in the output.
Supplementary Character if Available Sequence is too Short	"X" placeholders are automatically added if the tag sequence occurs towards the end of an mRNA sequence read.
Only Output Segments with Gene Names from following file	If this option is selected, then the software compares the titles found in the mRNA sequence input file to a user-defined text file that lists gene names (one gene per line). If a title in the mRNA sequence file matches a string (gene name) in the user-defined text file, then the segment is used to create synthetic SAGE data.
Load mRNA into File	If this option is selected, then the software compares the titles found in the mRNA sequence input file to a user-defined csv file that lists sequence titles. The information in the csv file is used for naming the tags in the output library and if the "Update Sequence Titles of Input Files with mRNA Info File" is selected, to change the mRNA titles in the original file

Setting	Description
Update Sequence Titles of Input Files with mRNA Info File	Available only if "Load mRNA into File" is selected. If this option is selected, then software uses the new titles to update the loaded mRNA sequence files. (The files are saved as new files.)

Modify Titles for mRNA GenBank tool

You use the Modify Titles for mRNA GenBank tool to retain critical information in an mRNA GenBank file. At times, critical information such as chromosome information and gene name, are not contained in the first line of an mRNA GenBank file. Instead, this information is found deeper in the file, in the file body. The NextGENe software uses the first line of an mRNA file as the title for the GenBank reference file, so to ensure that this information is retained, you must use this tool to modify the first line of the file to include this critical information. Figure 6-137 below illustrates this.

Figure 6-137: Modifying Titles for mRNA GenBank tool

Gene name is "EM	в."					
Original: LOCUS	NT_006713	42230486 bp	DNA linear	CON 29-FE	B-2008	
After process: Modified: LOCUS	NT 006713 5 E	MBLOC402214	42230486	5bp DNA	linear	CON 29-FEB-200

Resume Project and Load Project

If an error occurs when you are attempting to load a NextGENe Viewer report, you can select this option to attempt to correct the error and allow the report to open. If this option does not correct the error, then you must reload the project.

NextGENe Viewer Comparison Reports and Tools

After you load a project in the NextGENe viewer, the following reports and tools available (all from the Comparisons menu) for comparing selected information (for example, the expression levels) between two or more projects that were aligned to the same reference sequence.

- The Expression Comparison report. See "Expression Comparison report" below.
- The Variant Comparison Tool. See "Variant Comparison tool" on page 295.
- The Somatic Mutation Comparison Tool. See "Somatic Mutation Comparison tool" on page 310.
- The CNV Tool. See one of the following:
 - "CNV (Copy Number Variation) tool (Dispersion and HMM)" on page 317.
 - "CNV (Copy Number Variation) tool (SNP-based Normalization with Smoothing)" on page 330.
- The Batch CNV Tool. See "Batch CNV Tool" on page 348.

Expression Comparison report

You use the Expression Comparison report to carry out parallel comparisons of expression levels in multiple projects that were aligned independently to the same reference sequence. The report details the variations in the depth of coverage per region between projects.



You can load a maximum of ten projects for comparison.

୩୫
പയം

If you have a subscription to Pathway Studio, then you can upload report results to Pathway Studio and visualize the biological pathway information for the genes in the report. Moreover, if the data is transcriptome data with alternative splicing, you can not only visualize the biological pathway information for the genes, but also their differential expression values. See "Differential gene expression analysis of transcriptome data" on page 176.



The following procedure describes how to set up a new Expression Comparison report. Optionally, you can click Load Settings to browse to and select a Settings file (.ini file) to generate the report based on the saved settings in the file.

1. On the Comparisons menu, click Expression Comparison Report.

The Expression Comparison Report Settings dialog box opens. The General tab is the only tab.

Figure 6-138: Expression Comparison Report Settings dialog box, General tab

Expression Comparison Report Settings	×
General	
Regions	
 Use Segments as Defined in Reference Files 	
Gene C mRNA C CDS ■	
C Continuous mRNA C Continuous CDS	
C ROI	
C Set Incremental Segment Length 10000 Bases C Input Region of Interest (".bed)	
	Set
Limits	
Limit to First 200 bp	
Limit to Last 200 bp	
Save Settings	3I

2. Indicate how to define the segments that are to be analyzed and reported on by the tool.

Option	Description
Use segments as defined in the reference files.	 Gene - Report coverage levels for each gene region. mRNA - Report coverage levels for each mRNA region. (Coding and non-coding exons.) CDS - Report coverage levels for each coding region. Continuous mRNA - Report coverage levels for the entire mRNA region for a gene, one region per gene. Continuous CDS - Report coverage levels for the entire coding region for a gene, one region per gene. ROI - Report coverage levels based on Regions of Interest that are defined in a GenBank reference file. Note: For information about defining Regions of Interest in a GenBank reference file, see "Advanced GBK Editor tool" on page 280
Set incremental segment length	Specify the segment length.
Input region of interest (*.bed)	You can upload a Region of Interest file in a BED format. Note: For information about the required format for the BED file, see "BED file" on page 463.

3. Optionally, select one or both Limit options and if needed, modify the default limits (200 bp) for reporting the coverage for only the first or last "x" number of bases of the selected segment type.



If any Limit option and CDS are selected, then the coverage levels for the first or last "x" number of bases in each CDS region is reported.

4. Optionally, click Save Settings to save the settings for this report in a Settings file (.ini file).

You can use a saved Settings file to generate the Expression Comparison report for another project based on the settings in the file.

5. Click OK to open the Load Project Files dialog box.

Figure 6-139: Load Project Files dialog box

Load Project Files	— ×-
Reference File:	
	<u>S</u> et
Sample File(s):	
	Add
	<u>R</u> emove
J	
	<u>C</u> ancel

6. Click Set to browse to and uploading the reference project file (the control sample, for instance).



J.L.

You can leave this field blank to compare multiple samples without a control.

7. Click Add to browse to and select an alignment project file that is to be included in the comparison. Repeat this step until you have added all the necessary project files.



You can load a maximum of ten projects.

8. Click OK to close the Load Project Files dialog box and generate the report.

See Figure 6-140 on page 294.




Figure 6-140: Expression Comparison Report example

The report is interactive:

The report can display either the "Min Coverage," "Max Coverage," the "Average Coverage," "Minimum Forward Read Coverage," "Minimum Reverse Read Coverage," "Read Counts," "Forward Read Counts," "RPKM," "RPK," or "FPKM" for each region. (The default view is "Max Coverage.") To change the view, on the report menu, click View, and then on the View menu, select a different viewing option.

FPKM is available only if paired end data was analyzed for the projects.

- For projects that used condensation, the views are based on the condensed reads. To change the view so that is based on the original reads, click Display Original Information at the top of the report.
- To save the report to a text (*.txt) file, on the report menu, click File > Save, or on the report toolbar, click the Save Report icon . A default name and location are provided for the file but you can change both of these values. The saved report is a table that lists the gene name and description for each region as well as the actual expression values for each region for every loaded project. The differential expression values of Ratio, log2Ratio, z-value, and p-value are also calculated and displayed for each gene in the report.
- To upload the reported genes into Pathway Studio to visualize differential gene expressions and biological pathway information, on the report main menu, click File > Upload gene list to Pathway Studio. See "Differential gene expression analysis of transcriptome data" on page 176.


• To modify the report settings, on the report menu, click Settings > Settings to open the Expression Report Settings dialog box and modify the report settings as needed. The report display is dynamically updated after you save the modifications.

Variant Comparison tool

You use the Variant Comparison tool to compare the variant calls in two or more aligned projects that use the same reference sequence. Typically, you use to the tool to simply compare up to 20 multiple projects to show variant calls that meet specific criteria, such as variant calls that are shared among all the projects and that meet a minimum coverage requirement. For certain data sets, however, additional functionality is available.

- If tumor/normal comparison data is available, you can use the Top List function to analyze somatic variants.
- If family data (relationship and phenotype) is available, you can use specific family data comparison options to help you to narrow the list of possible causative variants.

Figure 6-141: Variant Comparison Tool window



See:

- "To use the Variant Comparison tool to compare multiple projects" on page 296.
- "To use the Variant Comparison Tool Top List function" on page 299.
- "To use the Variant Comparison tool to analyze family data" on page 303.

To use the Variant Comparison tool to compare multiple projects

You can load up 20 project files when comparing multiple projects.

1. On the Comparisons menu, click Variant Comparison Tool.

The Variant Comparison Tool window opens.

- 2. To load the files that are to be compared, do one of the following:
 - On the Variant Comparison Tool main menu, click File > Load Projects.
 - On the Variant Comparison Tool toolbar, click the Load Projects icon 🚘.

The Variant Comparison dialog box opens.

Figure 6-142: Variant Comparison dialog box

ample	Relationship	Phenotype	Mutation Type	Load Project File
				<u>R</u> emove File
				Remove <u>A</u> ll

3. For every project file that is to be loaded into the tool, click Load Project File to open a Load NextGENe Project File dialog box in which you can browse to and select the project file.

After you load the *first* project file, the Variant Comparison dialog box is refreshed with columns for Relationship, Phenotype, and Mutation Type.

Figure 6-143: Variant Comparison dialog box with Relationship, Phenotype, and Mutation Type columns

ample	Relationship	Phenotype	Mutation Type	
·	· · ·			Load Project File
HS1897_all_paired_hg19.pjt	Relationship 💌	Phenotype 💌	Mutation Type	
HS1898_all_paired_hg19.pjt	Relationship 🔹	Phenotype 🔹	Mutation Type 🔹	Remove File

4. Click Next.

The Variant Comparison dialog box is refreshed with the settings for specifying the types of variants that are to be displayed in the Variant Comparison Tool report.

Figure 6-144: Variant Comparison dialog box with Comparison Type settings

Comparison type	
C Show all	
Show shared/different	
C Show shared	 Show different
Minimum coverage >=	10
Percentage change >=	50 %
Exclude 02 molation	· · · · · · · · · · · · · · · · · · ·
C Low coverage SNPs	
Opplay.cow.coverage SM	10
C Mutation lyne sellings C Template	
Custóm Template	- Autosomal Dominant
	Autosomial Dominant
 Compound hereizevgens 	Autosomial Dominant I
	Autosomia Dominant I
C Compound herenarygou.	Autocomial Dominent !
C Compound hereateyour.	

5. Specify the type of variants that are to be displayed in the Variant Comparison Tool report.



You can select only one filtering option—Show All, Show shared/different, Low Coverage SNPs, or Gene Association.

Setting	Description
Comparison Type	
Show all	Show all variants in all projects.
 Show shared/ different 	Select showed shared/showed different, and then select one of the following:
Show shared	Show only those variants that are shared among all loaded projects.
Show different	 Show only those variants that are present in a single project when comparing only two projects or only those variants that are shared among some, but not all the projects, when comparing more than two projects.

Setting	Description
Minimum coverage	• The minimum coverage threshold that is required in all samples for a variant to be included in the Variant Comparison Tool report.
Percentage change	• The difference (in percentage) in the mutant allele frequency that is required for variants in two samples be categorized as "Different." If two samples have the same variant that is found at frequencies with a difference that is less than the indicated threshold, then the variant is categorized as "Shared" for the samples.
Exclude 0% variants	Available only if Show shared is selected. Ignore the Percentage Change threshold and always considers two samples as being different if a variant is called in one of the samples but it is not called in the other sample <i>and</i> the variant allele is found at 0% in the other sample.
Low coverage SNPs	View all variants in all projects that meet the indicated low coverage requirements.
	Note: If you select Low Coverage SNPs, then you can accept the default value of 10 for Display Low Coverage SNPs, or you can modify the value.
Gene association	At least "x" number of projects have a variant in the same gene, regardless of variant type and/or location.

- 6. Do one or both of the following in the Filter and Display Settings pane:
 - To specify the information that is to be displayed for each variant, click Mutation Report Filter/Display Settings.

Because the Variant Comparison Tool report settings are identical to those used in the Sequence Alignment Mutation report, the Mutation Report Settings dialog box opens. (See "Mutation Report settings" on page 213.)

• To specify the tracks that are to be used in the comparison, click Tracks Filter/ Display settings to open the Query Tracks dialog box and select and/or import the appropriate tracks. You can also set the display and filter settings for the selected tracks at this point. See "Variation Tracks Settings dialog box" on page 232.



For detailed information about loading track data for previously run projects, see the Reference & Track Manager Tool User's Manual or Online Help.

7. Click OK on the Variant Comparison dialog box.

The Variant Comparison Tool report opens. Green indicates a negative variant. "N/A" is displayed for allele calls for negative variants unless Check Allele Counts for Negative Mutations was selected. See Figure 6-145 on page 299.

<i>≩</i> %		1	00	-	•													
Chr All	1	•	Gen	EA	dl													
Page	of 117 Firstee	Previous<	1 2	3 4	1 5	>Next >>	Last to F	age 1	Go									
					1		UDP2753				UDP2755				UDP3165			
ID	Chr Position	Gene	CDS	Ch	Ref	db_xref	Coverage	Score	Mutation Call	AminaAcid C	Coverage	Score	Mutation Cal	AminoAcid C	Coverage	Score	Mutation Cal	AminaAcid (
33	909221	PLEKHN1	14	1	T	rs62639985	67	14.5	c.1443T>CT	481S>SS	38	12.3	c.1443T>CT	481S>SS	35	0.0		
34	909238	PLEKHN1	14	1	G	rs3829740	72	13,9	c.1460G>CG	487R>PR	40	10.4	c.1460G>CG	487R>PR	39	12.5	c.1460G>C	487R>P
35	909419	PLEKHN1	14	1	С	rs28548431	9	6.1	c.1641C>CT	547D>DD	13	8.4	c.1641C>CT	547D>DD	8	0.0		
36	935222	HES4	1	1	С	rs2298214	2	0.0			0	0.0			5	2.3	c.132C>A	44R>S
37	949608	ISG15	2	1	G	rs1921	21	7.1	c.248G>AG	83S>NS	14	6.0	c.248G>AG	835>NS	20	0.0		
38	949654	ISG15	2	1	A	rs8997	22	10.9	c.294A>G	98V>V	12	7.5	c.294A>G	98V>V	20	10.2	c.294A>G	98V>V
39	970691	AGRN	3	1	G		79	14.9	c.498G>AG	166P>PP	74	0.0			82	14.2	c.498G>AG	166P>PP
40	981931	AGRN	18	1	A	rs2465128	28	11.4	c.3066A>G	10225>5	24	10.5	c.3066A>G	10225>5	40	12.7	c.3066A>G	10225>S
41	982994	AGRN	21	1	Т	rs10267	50	13.5	c.3558T>C	1186F>F	27	11.2	c.3558T>C	1186F>F	34	12.0	c.3558T>C	1186F>F
42	984302	AGRN	24	1	T	rs9442391	6	3.6	c.4161T>CT	1387T>TT	6	0.0			6	5.5	c.4161T>C	1387T>T
43	990280	AGRN	36	1	С	rs4275402	7	3.1	c.6057C>CT	2019D>DD	4	3.9	c.6057C>T	2019D>D	5	3.6	c.6057C>T	2019D>D
44	1120431	TTLL10	10	1	G	rs1320571	53	5,5	c.1343G>AG	448S>NS	47	0.0			54	12.3	c.1343G>AG	448S>NS
45	1147422	TNFRSF4	5	1	С	rs17568	15	8.7	c.534C>CT	178E>EE	8	0.0			18	6.6	c.534C>CT	178E>EE

Figure 6-145: Variant Comparison Tool report example

8. Optionally, continue to "To use the other Variant Comparison Tool functions" on page 307.

To use the Variant Comparison Tool Top List function

You use the Top List function to analyze somatic variants that can be found in a mutant sample/normal sample comparison, or in a multiple sample similarity comparison. In a mutant sample/normal sample comparison, such as a tumor/normal comparison, you can load only two sample project files—the mutant sample project file and the normal sample project file. The Top List function ranks the detected variants in these two files and returns the top 100 results for the following three types of variants:

- Gain in heterozygosity variants, which are low frequency novel/somatic variants in the normal sample.
- Loss of heterozygosity variants, which are low frequency variants in the mutant sample.
- Absolute change variants, which are the variants with the most significant allele change and that are not low frequency in either the mutant sample or the normal sample.

In a multiple sample similarity comparison, you can load up to 20 sample project files. The Top List function returns a list of variants that have the highest rankings in all the files. The variants' rankings are based on the three criteria—the number of samples that share the variant, the frequency at which the variant occurs in each sample, and the size of the standard deviation for the allele frequency between samples.

1. On the Comparisons menu, click Variant Comparison Tool.

The Variant Comparison Tool window opens.

- 2. To load the files that are to be compared, do one of the following:
 - On the Variant Comparison Tool main menu, click File > Load Projects.
 - On the Variant Comparison Tool toolbar, click the Load Projects icon 🔁.

The Variant Comparison dialog box opens. See Figure 6-146 on page 300.

Sample	Relationship	Phenotype	Mutation Type	
				Load Project File
				Bemove File
				Remove <u>A</u> ll

Figure 6-146: Variant Comparison dialog box

- 3. Do one of the following:
 - For a mutant sample/normal sample comparison, click Load Project File to open a Load NextGENe Project File dialog box, and then browse to and select the mutant project file, and then browse to and select the normal sample file.



For a mutant/normal sample comparison, you must load the mutant sample file first, and the normal sample file second.

For either comparison type, after you load the *first* project file, the Variant Comparison dialog box is refreshed with columns for Relationship, Phenotype, and Mutation Type.

Figure 6-147: Variant Comparison dialog box with Relationship, Phenotype, and Mutation Type columns

•				
Sample	Relationship	Phenotype	Mutation Type	
HS1897_all_paired_hg19.pjt	Relationship 💌	Phenotype 💌	Mutation Type 💌	Load Project File
HS1898_all_paired_hg19.pjt	Relationship 💌	Phenotype 💌	Mutation Type	<u>R</u> emove File
HS1899_all_paired_hg19.pjt	Relationship 💌	Phenotype 💌	Mutation Type 🗨	
				Remove <u>A</u> ll

4. Click Next.

The Variant Comparison dialog box is refreshed with the settings for specifying the types of variants that are to be displayed in the Variant Comparison Tool report. See Figure 6-148 on page 301.

C Show all	
Show shared/different	
C Show shared	Show different
Minimum coverage >=	10
Percentage change >=	50 %
Exelude 02 multation	
C Low coverage SNPs	
Opplay dow coverage SNP	10
C Mutation loss salting: C Trendale	
Dustom Template	🚊 [Autosomal Dominant
 Compound hereidaygous 	
C Gene association	
Atileest 1 project	n have a nutation integration dens
Filter and display settings	
	ay Settings Tracks Filter/Display Settings

Figure 6-148: Variant Comparison dialog box with Comparison Type settings

- 5. Do the following.
 - Select Show shared/different and then:
 - If you are carrying out a multiple sample comparison, select Show shared to show only those variants that are shared among all loaded projects.
 - If you are carrying out a tumor sample/normal sample comparison, Select Show different to show only those variants that are present in only one of the projects.
 - Set a Minimum coverage and Percent change to filter out variants if one sample fails the coverage setting or if the difference in allele frequency is less than the specified threshold.
- 6. Do one or both of the following: in the Filter and Display Settings pane:
 - To specify the information that is to be displayed for each variant, click Mutation Report Filter/Display Settings.

Because the Variant Comparison Tool report settings are identical to those used in the Sequence Alignment Mutation report, the Mutation Report Settings dialog box opens. (See "Mutation Report settings" on page 213.)

• To specify the tracks that are to be used in the comparison, click Tracks Filter/ Display settings to open the Query Tracks dialog box and select and/or import the appropriate tracks. You can also set the display and filter settings for the selected tracks at this point.



For detailed information about loading track data for previously run projects, see the Reference & Track Manager Tool User's Manual or Online Help.

7. Click OK on the Variant Comparison dialog box.

The Variant Comparison Tool report opens. Green indicates a negative variant.

Figure 6-149: Variant Comparison Tool report example, Before Top List function

File	Settings	Vie	W													
£ 3	? ■ 相	Ŧ	1 🕅		K.											
					L.		-	1								
Chr Al			-		ne All		2	1								
Page	1 of 1 First	<			ext >>Las	to Pag	e 1	Go								
			702Ts_2							702Ns_2_	4		1			
ID	Gene	Re	f A Ratio%	C Ratio	G Ratio%	T Ratio%	Ins Ratio	Del Ratio	Mutation Call	A Ratio%	C Ratio%	G Ratio%	T Ratio%	Ins Ratio	Del Ratio	Mutation Call
3	ATP8B2	G	0.00	0.00	100.00	0.00	0.00	0.00		0.00	0.00	89.29	0.00	0.00	10.71	c.835delG
4	ATP8B2	τ	0.00	0.00	0.00	100.00	0.00	0.00		10.71	0.00	0.00	89.29	0.00	0.00	c.836T>AT
5	ATP8B2	С	0.00	98.97	0.00	1.03	0.00	0.00		0.00	89.29	10.71	0.00	0.00	0.00	c.837C>CG
6	ATP8B2	T	0.00	0.00	0.00	100.00	0.00	0.00		0.00	0.00	10.71	89.29	0.00	0.00	c.841T>GT
7	ATP8B2	Т	0.00	0.00	0.00	100.00	0.00	0.00		0.00	0.00	10.71	89.29	0.00	0.00	c.842T>GT
8	ATP8B2	А	96.25	2.50	1.25	0.00	0.00	0.00		77.27	22.73	0.00	0.00	0.00	0.00	c.1025A>AC
9	ATP8B2	A	96.47	2.35	0.00	1.18	0.00	0.00		88.89	11.11	0.00	0.00	0.00	0.00	IVS1742-17A>A0
10	ATP8B2	С	0.00	65.07	0.68	34.25	0.00	0.00	c.2277C>CT	0.00	35.29	0.00	64.71	0.00	0.00	c.2277C>CT
11	ATP8B2	Т	0.00	44.83	0.00	55.17	0.00	0.00	IV\$2386-29T>CT	0.00	60.00	0.00	40.00	0.00	0.00	IVS2386-29T>C
12	ATP8B2	A	93.43	6.57	0.00	0.00	0.00	0.00		81.08	18.92	0.00	0.00	0.00	0.00	c.2839A>AC
13	IL6R	А	59.85	38.64	0.00	1.52	0.00	0.00	c.1073A>AC	63.04	36.96	0.00	0.00	0.00	0.00	c.1073A>AC
14	SHE	T	0.00	0.00	4.17	95.83	0.00	0.00		0.00	5.56	22.22	72.22	0.00	0.00	c.1154T>GT
15	SHE	T	1.47	1.47	5.88	91.18	0.00	0.00		0.00	0.00	23.33	76.67	0.00	0.00	c.842T>GT
16	SHE	С	0.00	0.00	100.00	0.00	0.00	0.00	c.372C>G	0.00	0.00	100.00	0.00	0.00	0.00	c.372C>G
17	TDRD10	А	96.26	3.74	0.00	0.00	0.00	0.00		84.62	15.38	0.00	0.00	0.00	0.00	c.406A>AC
18	TDRD10	T	0.00	100.00	0.00	0.00	0.00	0.00	c.636T>C	0.00	100.00	0.00	0.00	0.00	0.00	c.636T>C
19	TDRD10	A	85.94	12.50	0.00	1.56	0.00	0.00	c.921A>AC	76.19	23.81	0.00	0.00	0.00	0.00	c.921A>AC
20	UBE2Q1	A	76.81	23.19	0.00	0.00	0.00	0.00	c.407A>AC	62.50	37.50	0.00	0.00	0.00	0.00	c.407A>AC
21	CHRNB2	T	0.00	0.00	25.64	74.36	0.00	0.00	c.98T>GT	0.00	0.00	50.00	50.00	0.00	0.00	c.98T>GT

8. Click the Top List 🕴 icon.

The variants are ranked and sorted accordingly.

- For a mutant/normal comparison project, two additional columns (Category and Change) are displayed in the report, where Category indicates the variant type (1 = Gain of Heterozygosity, -1 = Loss of Heterozygosity, and 0 = Absolute Change), and Change indicates the absolute change in allele frequency between the two samples.
- For a multiple sample comparison project, one additional column, Similar, is displayed in the report, where similar indicates the similarity in allele frequency among all the different samples.

See Figure 6-150 and Figure 6-151 on page 303.

File	Settings	Vie	ew															
2%	• 🖬 俳		I I	91	k													
hr A		_	-		Law.		-	1										
					All		-	i anti-										
Page	1 of 1 First	~	Previous				e 1	Go										
				_	702Ts_2							702Ns_2			-			
D	Gene	Re	Catogory	Change.	A Ratio%	C Ratio%	G Ratio%	T Ratio%	Ins Ratio%	Del Ratio%	Mutation Call	A Ratio%	C Ratio%	G Ratio%	T Ratio ²	Ins Ratio%	Del Ratio%	Mutation Call
3	CD5L	A	1	11.9	77.42	21.51	1.08	0.00	0.00	0.00	c.110A>AC	96.15	3.85	0.00	0.00	0.00	0.00	
1	PBXIP1	A	1	16.2	88.84	16.16	0.00	0.00	0.00	0.00	IVS1045+2881638A>AC	100.00	0.00	0.00	0.00	0.00	0.00	
5	MEF2D	T	1	12.0	000	0.00	12.05	87.95	0.00	0.00	IVS1045+1354870T>GT	0.00	0.00	0.00	100.00	0.00	0.00	
5	ATP882	T	1	7.0	00	0.00	18.11	81.89	0.00	0.00	IVS1045+3497864T>GT	0.00	0.00	4.44	95.56	0.00	0.00	
7	NTRK1	A	1	10.3	87.18	10.26	0.00	2.56	0.00	0.00	IVS1045+955746A>AC	100.00	0.00	0.00	0.00	0.00	0.00	
3	HDGF	A	1	10.8	86.15	10.77	1.54	1.54	0.00	0.00	IV\$1045+1087673A>AC	100.00	0.00	0.00	0.00	0.00	0.00	
3	PKLR	T	1	11.8	00	0.00	11.76	88.24	0.00	0.00	IVS1045+2540215T>GT	0.00	0.00	0.00	100.00	0.00	0.00	
10	TTC24	T	1	2.4	00	0.00	12.82	87.18	0.00	0.00	IVS1045+1248590T>GT	0.00	0.00	4.17	95.83	0.00	0.00	
11	C1orf85	С	-1	5.9	000	0.00	0.00	100.00	0.00	0.00	IVS1045+1537106C>T	0.00	5.88	0.00	94.12	0.00	0.00	IVS1045+15371060
12	ATP8B2	С	0	30.5	00	65.07	0.68	34.25	0.00	0.00	IVS1045+3484601C>CT	0.00	35.29	0.00	64.71	0.00	0.00	IVS1045+34846010
13	ADAR	С	0	18.1	000	60.71	0.00	39.29	0.00	0.00	IVS1045+3239829C>CT	0.00	42.59	0.00	57.41	0.00	0.00	IVS1045+32398290
4	ARHGE	С	0	21.0	000	41.90	0.00	58.10	0.00	0.00	IVS1045+862579C>CT	0.00	62.86	0.00	37.14	0.00	0.00	IVS1045+862579C
15	UBQLN	G	0	13.5	35.00	0.00	65.00	0.00	0.00	0.00	IVS1045+1790015G>AG	7.94	0.00	90.48	1.59	0.00	0.00	
16	AQP10	С	0	35.4	000	34.62	0.00	65.38	0.00	0.00	IVS1045+3504942C>CT	0.00	70.00	0.00	30.00	0.00	0.00	IVS1045+35049420

Figure 6-150: Variant Comparison Tool report, Top List function, mutant/normal comparison

Figure 6-151: Variant Comparison Tool report example, Top List function, multiple sample comparison

-																			
Eile	Settin	ngs ⊻i																	
÷ 💈	2 🗖	俳	1 🖬 🖬	0.01	ñ,														
hr Al	-		•		Al		*												
Page	1 of 1	Fester	Previous	1 >Next	SLast	to Page	1	Go											
	1		555T_s_	1						702Ts_2_							900T_align	p	
D	Re	Similar	A Ratio	C Ratio?	G Ratio	T Ratio%	Ins Ratio	Del Ratio%	Mutation Call	A Ratio%	C Ratio%	G Ratio%	T Ratio%	Ins Ratio	Del Ratio%	Mutation Call	A Ratio%	C Ratio%	G Ratio%
	A	89.7	85.67	12.22	0.00	1.11	0.00	0.00	IVS1-5A>AC	86.99	13.01	0.00	0.00	0.00	0.00	IVS1-540AC	80.83	19.17	0.00
	G	99.1	0.00	1.53	98.47	0.00	83.16	0.00	IVS1540+529582_1540+	0.00	3.28	96.72	0.00	84.84	0.00	IVS1540+529582_1540+	0.00	1.80	98.20
3	Ţ	98.9	0.00	0.00	10.00	90.00	0.00	0.00	IVS1540+859004T>GT	0.00	1.03	9.28	89.69	0.00	0.00		0.00	0.00	2.27
1	T	88.7	0.00	0.00	16.67	83.33	0.00	0.00	IVS1540+838510T>GT	0.00	0.00	15.38	84.62	0.00	0.00	IVS1540+838510T>GT	0.00	0.00	12.00
5	T	90.9	0.00	0.00	11.76	88.24	0.00	0.00	IVS1540+2068764T>GT	0.00	0.00	19.67	80.33	0.00	0.00	IVS1540+2068764T>GT	0.00	0.00	13.43
5	G	100.0	0.00	100.00	0.00	0.00	0.00	0.00	IVS1540+1256768G>C	0.00	100.00	0.00	0.00	0.00	0.00	IVS1540+1256768G>C	0.00	100.00	0.00
7	A	91.1	89.47	10.53	0.00	0.00	0.00	0.00	IVS1540+563891A>AC	82.43	17.57	0.00	0.00	0.00	0.00	IVS1540+563891A>AC	79.17	20.83	0.00
3	T	100.0	0.00	100.00	0.00	0.00	0.00	0.00	IVS1540+1685998T>C	0.00	100.00	0.00	0.00	0.00	0.00	IVS1540+1685998T>C	0.00	100.00	0.00
9	T	100.0	0.00	100,00	0.00	0.00	0.00	0.00	IVS1540+561656T>C	0.00	100.00	0.00	0.00	0.00	0.00	IVS1540+561656T>C	0.00	100.00	0.00
0	С	100.0	0.00	0.00	0.00	100.00	0.00	0.00	IVS1540+530781C>T	0.00	0.00	0.00	100.00	0.00	0.00	IVS1540+530781C>T	0.00	0.00	0.00
1	G	0,001	100.00	0.00	0.00	0.00	0.00	0.00	IVS1540+530820G>A	100.00	0.00	0.00	0.00	0.00	0.00	IVS1540+530820G>A	100.00	0.00	0.00
2	A	100.0	0.00	100.00	0.00	0.00	0.00	0.00	IVS1540+530907A>C	0.00	100.00	0.00	0.00	0.00	0.00	IVS1540+530907A>C	0.00	100.00	0.00
13	G	100.0	0.00	100.00	0.00	0.00	0.00	0.00	IVS1540+558412G>C	0.00	100.00	0.00	0.00	0.00	0.00	IVS1540+558412G>C	0.00	100.00	0.00

9. Optionally, continue to "To use the other Variant Comparison Tool functions" on page 307.

To use the Variant Comparison tool to analyze family data

When you use the Variant Comparison tool and you have family data available, you have three options for comparing samples. You can:

- Manually specify the expected variant types.
- Specify the relationship and the phenotype for each sample, and then load an Inheritance template to automatically adjust the expected variant types.
- Specify the relationship and the phenotype for each sample, and then carry out compound heterozygous filtering and review the results of this filtering in the Compound Heterozygous report.

1. On the Comparisons menu, click Variant Comparison Tool.

The Variant Comparison Tool window opens.

- 2. To load the files that are to be analyzed, do one of the following:
 - On the Variant Comparison Tool main menu, click File > Load Projects.
 - On the Variant Comparison Tool toolbar, click the Load Projects icon 🚘.

The Load Projects dialog box opens.

Figure 6-152: Load Projects dialog box

ample	Relationship	Phenotype	Mutation Type	Load Project File
				<u>R</u> emove File
				Remove <u>A</u> II
				Themove Bit

3. For each family data project file that is to be analyzed, click Load Project File to open a Load NextGENe Project File dialog box, and then browse to and select the file.

After you load the *first* family data project file, the Variant Comparison dialog box is refreshed with columns for Relationship, Phenotype, and Mutation Type.

Figure 6-153: Variant Comparison dialog box with Relationship, Phenotype, and Mutation Type columns

٧	ariant Comparison				×
	Sample	Relationship	Phenotype	Mutation Type	
	HS1897_all_paired_hg19.pjt	Relationship 💌	Phenotype 💌	Mutation Type 💌	Load Project File
	HS1898_all_paired_hg19.pjt	Relationship 💌	Phenotype 💌	Mutation Type 🔹	<u>R</u> emove File
	HS1899_all_paired_hg19.pjt	Relationship 💌	Phenotype 💌	Mutation Type	Remove <u>A</u> ll

4. For each sample file, select the relationship and the phenotype, and if applicable, the expected variant type.

5. Click Next.

The Variant Comparison dialog box is refreshed with the settings for specifying the types of variants that are to be displayed in the Variant Comparison Tool report.

Figure 6-154: Variant Comparison dialog box with Comparison Type settings

Comparison type							
🕖 Show all							
Show shared/different							
(@) Show shared	Show different						
Mmmuni coverage	10						
Rementage Change X	50						
Exclude 0% mutations							
Low coverage SNPs							
Display low coverage SNP	10						
 Mutation type settings Template 							
 Template Mitochondrial 	▼ C.\Program	Files (x86)\Sof	lGenetics\NextGl	ENe\NG_V2	4.2_Validatio	n(Béta)_35Day	sW64\templates
Template	▼ C\Program	Files (x86)\Sof	(Genetics\NextGl	ENe\NG_V2	4.2_Validatio	n(Beta)_35Day	stX64\templates
 Template Mitochondrial 	▼ C\Program	Files (x86)\Sof	(Genetics\NextGl	ENe\NG_V2	4.2_Validatio	n(Beta)_35Day	s\X64\templates
Template Mitochondrial Compound helerozygous Gene association	CAProgram Calendrate		(Genetics\NextG)	ENe\NG_V2	4.2_Validatio	n(Beta)_35Day	sVXD4Vtemplates
Template Mitochondrial Compound helerozygous Gene association			(Genetics (NéxtG)	ENe\NG_V2	4.2_Validatio	n(Beta)_35D ay	sWD4\templates
Femplate Mitochondkial Compound Intercorgous Gene association Attende 1 procee	92 bave à mutation with	te same derte	tGenetics/NéxtGl		4.2_Validatio	n(Beta)_35D ay	sWXD4\templates

- 6. Do one of the following:
 - To show only those variants that meet the expected variant type that you specified for each of the sample files, select Mutation type settings.
 - To show variants that meet a specific pattern, select an Inheritance template or Compound heterozygous.

Setting	Description
Template	Each template defines a specific inheritance pattern. Select a template to automatically adjust the expected variant types for the sample files based on the relationships and phenotypes settings for the project.
	Note: You can select from a pre-configured list of templates, or you can create your own custom template.
Compound heterozygous	Select this option to carry out compound heterozygous filtering. The filtering results are displayed in the Compound Heterozygous report, which shows all possible combinations of two heterozygous variants in a gene if the variants meet the relationship and phenotype settings for the project. For example, if a Mother is Unaffected and a Father is Unaffected, but a Son is Affected, then one heterozygous variant must come from each parent.

• Select Gene association, and then enter the minimum number of projects in which the *same* gene must have a variant (regardless of variant type and/or location) to report the gene in the output.

- 7. Do one or both of the following in the Filter and Display Settings pane:
 - To specify the information that is to be displayed for each variant, click Mutation Report Filter/Display Settings.

Because the Variant Comparison Tool report settings are identical to those used in the Sequence Alignment Mutation report, the Mutation Report Settings dialog box opens. (See "Mutation Report settings" on page 213.)

• To specify the tracks that are to be used in the comparison, click Tracks Filter/ Display settings to open the Query Tracks dialog box and select and/or import the appropriate tracks. You can also set the display and filter settings for the selected tracks at this point.



For detailed information about loading track data for previously run projects, see the Reference & Track Manager Tool User's Manual or Online Help

8. Click OK on the Variant Comparison dialog box.

The Variant Comparison Tool report opens. Green indicates a negative variant. "N/A" is displayed for allele calls for negative variants unless Check Allele Counts for Negative Mutations was selected.

		•	0.01		*													
Chr All		•	Ger	EA	xII													
Page	of 117 Firste	Previous	1 2	3 .	4 5	>Next >>	Last to P	age 1	Go									
1							UDP2753				UDP2755				UDP3165			
ID	Chr Position	Gene	CDS	Ch	r Rel	db_xref	Coverage	Score	Mutation Call	AminoAcid 0	Coverage	Score	Mutation Cal	AminoAcid C	Coverage	Score	Mutation Cal	AminaAcid C
33	909221	PLEKHN1	14	1	T	rs62639985	67	14.5	c.1443T>CT	481S>SS	38	12.3	c.1443T>CT	481S>SS	35	0.0	1 1	
34	909238	PLEKHN1	14	1	G	rs3829740	72	13.9	c.1460G>CG	487R>PR	40	10.4	c.1460G>CG	487R>PR	39	12.5	c.1460G>C	487R>P
35	909419	PLEKHN1	14	1	С	rs28548431	9	6.1	c.1641C>CT	547D>DD	13	8.4	c.1641C>CT	547D>DD	8	0.0		
36	935222	HES4	1	1	С	rs2298214	2	0.0			0	0.0			5	2.3	c.132C>A	44R>5
37	949608	ISG15	2	1	G	rs1921	21	7.1	c.248G>AG	83S>NS	14	6.0	c.248G>AG	835>NS	20	0.0		
38	949654	ISG15	2	1	A	rs8997	22	10.9	c.294A>G	98V>V	12	7.5	c.294A>G	98V>V	20	10.2	c.294A>G	98V>V
39	970691	AGRN	3	1	G		79	14.9	c.498G>AG	166P>PP	74	0.0			82	14.2	c.498G>AG	166P>PP
40	981931	AGRN	18	1	А	rs2465128	28	11.4	c.3066A>G	1022S>S	24	10.5	c.3066A>G	10225>5	40	12.7	c.3066A>G	10225>S
41	982994	AGRN	21	1	T	rs10267	50	13.5	c.3558T>C	1186F>F	27	11.2	c.3558T>C	1186F>F	34	12.0	c.3558T>C	1186F>F
42	984302	AGRN	24	1	T	rs9442391	6	3.6	c.4161T>CT	1387T>TT	6	0.0			6	5.5	c.4161T>C	1387T>T

 If you selected Compound heterozygous filtering, then on the toolbar, click the Show/ Hide Compound Heterozygous icon → to open the Compound Heterozygous report.

Figure 6-156: Compound Heterozygous report example

File	Settings Vie	ew .															
🔊 🎾	2 🖬 🖷 🖇	📫 🗊 🛛	1 K.														
Chr A	1	-	Gene All		-						Index	Chr	Gene	Pos1	Genoty	Pos2	Geno
Page	1 of 27 First<<	Previous< 1	2345	>Next >>I	Last to Pag	je 1	Go				1	1	TTLL10	1120536	A/G	1119546	G/T
							HS1897_all_	_		^	2	1	TTLL10	1120536	A/G	1120091	A/G
ID	Chr Position	Gene	Gene Dir	RNA Access	Chr	Reference N	Coverage	Ambiguous L	A(#F,#R)		3	1	MORN1	2282990	C/T	2283161	A/G
	1119546	TTLL10	+		1	G	11	0.000	n/a;n/a		4	1	MORN1	2282990	C/T	2283266	C/T
2	1120091	TTLL10	+		1	G	12	0.000	n/a;n/a		5	1	MORN1	2282990	C/T	2283313	C/G
3	1120536	TTLL10	+		1	G	12	0.000	0;4		6	1	MOBN1	2282990	C/T	2288852	A/G
4	2282990	LOC1001295	5.		1	С	13	0.000	0;0		7	1	1001001		C/T	2283161	A/G
5	2283161	LOC1001295	i.		1	A	44	0.000	n/a;n/a								
6	2283266	LOC1001295	i.		1	т	41	0.000	n/a;n/a		8	1	LOC1001	2282990	C/T	2283266	C/T
7	2283313	1001001295			1	C.	17	0.000	nlanla		9	1	LOC1001	2282990	C/T	2283313	C/G



Click the Show/Hide Compound Heterozygous report icon \mathbf{H} - again to hide the report.

10. Optionally, continue to "To use the other Variant Comparison Tool functions" below.

To use the other Variant Comparison Tool functions

After the Variant Comparison Tool report is generated, several other Variant Comparison tool functions become available from the report main menu.

 To view alignments for selected projects, click View > Check Projects to View Alignments, or on the report toolbar, click the Check Projects to View Alignments icon
 .

The Sequence Display Settings dialog box opens. The dialog box displays all the projects for which you can view the alignments. By default, the option to Mark Center Lines (a green vertical line) in the alignment display is selected and there is an option to change the font size of the bases (the Base Display Size with a default value of eight) in the view.

Figure 6-157: Sequence Display Settings dialog box

Check Projects to View Alignments		
C:\Users\Spectrum Writing\Spe C:\Users\Spectrum Writing\Spe	ctrum Writing Info\A	
4 [
∢ m Base Display Size: 8 ÷		,

At a minimum, you must select the projects for which you want to view the alignments. You can also indicate whether to show the center lines in each alignment view and/or you can change the font size for the base display. After you click OK to close the dialog box, a window that is linked to the report table for the selected projects opens. (See Figure 6-158 on page 308.) You can do the following in this window:

- Double-click on a variant in the alignment view to change the focus of the report to the selected variant.
- Right-click on a variant in the alignment view, and on the context menu that opens, select Go to position in Mutation report to change the focus of the report to the selected variant.
- Double-click on a variant in the Mutation report to change the focus in the corresponding alignment view to the selected variant.




Figure 6-158: Variant Comparison Tool report showing individual projects

- To automatically save the Sequence Display Settings that you selected, click View > AutoSave Display Status. The next time you run a comparison in the Variant Comparison tool, these setting are automatically applied for the display.
- To search the displayed alignment, click Search > Sequence Search, or on the report toolbar, click the Sequence Search icon indicate how you want to search the displayed alignment—by Sequence, by Position (chromosome, chromosome position (for example., 1, 20000)) or by Gene Name. You can also click Option to search by a reverse complement sequence.



The Search Sequence function is enabled only when the Check Projects to View Alignments option is selected.

Figure 6-159: Search dialog box

Search		×
Find Options	C Search by Position	 Search by Gene Name
EPHB6	♥ Option	Previous <u>N</u> ext

• To change the current Mutation report display, click Settings > Settings to open the Mutation Report Settings dialog box. Select the Filter and Display options for the report.



For detailed information about the available settings on each of the tabs on the Mutation Report Settings dialog box, see "Mutation Report settings" on page 213.

- To change the current comparison settings, click Settings > Sample Settings to open the Load Project(s) dialog box, and then do any of the following:
 - Select one or more projects for deletion.
 - Add different projects for comparison.
 - Modify settings for Relationship, Phenotype and/or Mutation Type for each project.
 - Click Next, and then change the Comparison Type Settings.
- To select the tracks that are to be queried for the projects, click Settings > Tracks Settings > Query to open the Query Tracks dialog box.



For detailed information about loading track data for previously run projects, see the Reference & Track Manager Tool User's Manual or Online Help.

• To change the display and filter settings for the tracks that are included with the projects, click Settings > Tracks Settings > Filter/Display to open the Variation Tracks Settings dialog box. Select the Filter and Display options for the report relative to the imported tracks.



For detailed information about the available settings on each of the tabs on the Variation Tracks Settings dialog box, see "Variation Tracks Settings dialog box" on page 232.

- To save the report and/or related information in a variety of formats, click the indicated option on the File menu:
 - Save Report To save the report to a tab-delimited text (*.txt) file, or a VCF file.

The default Save as file type is tab-delimited text. To save in VCF format, select VCF file from the Save as type dropdown. A default name and location are provided for the file, but you can change both of these values.



You can also click the Save Report icon **[***on the report toolbar.*

- Save VarMD Report To save the report as a VarMD report, which is a format that you can use in the third party VarMD tool.
- Save as Project Link To save all the information for the currently displayed comparison (the samples, the comparison settings, and the report settings) click File > Save as Project Link. The information is saved in an .ini file. You must specify the file name. By default, the file link is saved in the project folder for the project that was loaded last for the comparison, but you can always select a different location.

- To load a project link To load a previously saved comparison, click File > Load Project Link, and then scroll to and select the appropriate project link. The comparison is loaded into the Variant Comparison tool. The comparison display is determined by the information (the samples, the comparison settings, and the report settings) that was saved for the project link.
- To save SNP Sequences To save the consensus sequences for all the variants that are displayed in the Variant Comparison tool report, click File > Save SNP Sequences. The sequences are saved to a .fasta file in the project output folder for the first loaded project. The default name for the file is based on the name of the first loaded project appended with _SNP_Sequences, but you can change one or both of these values.

Somatic Mutation Comparison tool

You use the Somatic Mutation Comparison tool to generate a filtered variant report for somatic variant detection. The tool is similar in both layout and function to the Variant Comparison tool. The tool filters variants based on comparison with a matched normal sample as well as a project with pooled normal samples to eliminate both non-somatic variants and artifacts that are the result of library preparation or alignment. You must load three different sequence alignment project (*.pjt) files that were aligned to the same reference sequence:

- The project file for a sequence alignment project for a cancerous tumor sample from a patient.
- The project file for the sequence alignment project for the *matched* normal sample, where the matched normal sample (for example, a blood sample) is from the same patient.
- The sequence alignment project file for the *pool*, where the pool consists of four to five normal samples that were aligned together in a single alignment project in the Project Wizard.

The tool then filters out the following variants based on your specified settings:


- All the variants that were found in the tumor sample project that were also found in the matched normal sample project.
- All the variants that were found in the tumor sample project that were also found in the pooled alignment project.

To generate the Somatic Mutation Comparison Tool report

1. On the Comparisons menu, select Somatic Mutation Comparison Tool.

The Somatic Mutation Comparison Tool window opens.

Figure 6-160: Somatic Mutation Comparison tool window



- 2. To load the files that are to be compared, do one of the following:
 - On the Somatic Mutation Comparison Tool main menu, click File > Load Projects.
 - On the Somatic Mutation Comparison Tool toolbar, click the Load Projects icon 🚘.

The Load Projects dialog box opens.

Figure 6-161: Load Projects dialog box

				_
Matched Normal				
Pool				
Maximum Contamination	5.000	%	I Relative Directional Balance (T/N) <=	7,000
Number of Pooled Samples =	2		Somatic Allele Frequency Ratio (T/N)>=	3.000
Somatic Allele Count >=	4	-	T Pooled Allele Count Ratio (T/P) >=	3,000
Filter and Display Settings			CNV Rep	toot
Mutation Report Filter/Displa	y Settings	Tra		Display Settings

- 3. For each project (Tumor, Matched Normal, and Pool), click the Load File icon 😰 to browse to and select the appropriate sequence alignment project file (Aligned Sequence Project (*.Pjt)) for loading.
- 4. Specify your report settings.

Setting	Description
Maximum Contamination	Independently compares the normal sample to the tumor sample to account for the possibility of the contamination of the normal sample with tumor DNA. If the frequency of the variant in the matched normal sample is less than the indicated threshold, then the variant is not filtered from the tumor sample.
Number of Pooled Samples	The number of samples that are included in the pool. Used in conjunction with the Maximum contamination threshold to consider possible contamination in the pool, such as low level tumor DNA. Sets an acceptable low level frequency that determines if a variant should be filtered out from the tumor sample. If the variant falls below this frequency, then it is not filtered out from the tumor sample. Note: Four to five samples is the recommended value for the pool.
Somatic Allele Count	The minimum coverage that is required for the variant in the tumor sample to be included in the Somatic Mutation Tool report.
Relative Directional Balance (T/N)	Selected by default. The ratio of the Read Balance for the variant in the tumor sample to the Read Balance for the reference allele in the normal sample. If the value for a variant falls below this ratio threshold, then it is filtered out from the report.
	Note: This option is useful for filtering out variants that are less directionally balanced in the tumor sample than in the normal sample.
Somatic Allele Frequency (T/N)	The ratio of the frequency of the variant in the tumor sample to the frequency of the variant in the normal sample. If the ratio is less than the indicated threshold, then the variant is filtered out from the report.
Pooled Allele Count Ratio (T/P)	The ratio of the number of reads with the variant in the tumor sample to the number of reads with the variant for the pool.

- 5. Optionally, do any or all the following as needed in the Filter and Display Settings pane:
 - To specify the information that is to be displayed for each variant, click Mutation Report Filter/Display Settings.

Because the Variant Comparison Tool report settings are identical to those used in the Sequence Alignment Mutation report, the Mutation Report Settings dialog box opens. (See "Mutation Report settings" on page 213.)

• To specify the tracks that are to be used in the comparison, click Tracks Filter/ Display settings to open the Query Tracks dialog box and select and/or import the appropriate tracks. You can also set the display and filter settings for the selected tracks at this point.



For detailed information about loading track data for previously run projects, see the Reference & Track Manager Tool User's Manual or Online Help.

• To generate a CNV (SNP-Based Normalization with Smoothing) report for the data, select CNV report, and then click CNV Filter/Display Settings to open the and specify the appropriate settings for the report. (See "CNV (Copy Number Variation) tool (SNP-based Normalization with Smoothing)" on page 330.)



If you select this option, then the report is displayed on a CNV Table tab in the report. You can toggle the report view between the SNP Table tab and the CNV Table tab.

6. Click OK.

The Somatic Mutation Comparison Tool report is generated. It is displayed on the SNP Table tab.

File	Settings Sea	rch View										
÷ 🖇	- • 🔲 🕞 🏭 🖻	1 🗊	• K	Mutatio	n Call 📃 🗸	-						
	Table	•••••••	• 1 = *			< 1						
							1 of 1 << <	• • • •	De en la			
Chr	All	-	Gene /	40	-	rage			to Page 1	Go	_	
							D.pjt					
ID	Chr Position	Gene	CDS	Chr	Reference N	Similar	Coverage	Score	A(#F,#R)	C(#F,#R)	G(#F,#R)	T
1	114284645	ANK2		4	С	99.2	2828	26.4	3;0	7;9	4;0	10
2	114276880	ANK2	38	4	Т	99.4	1206	24.0	0;0	200;999	0;0	0;
3	114276884	ANK2	38	4	A	99.4	1204	24.0	0;7	0;0	198;999	0;
4	114275243	ANK2	38	4	С	99.6	800	22.7	0;0	1/1	0;0	4(
5	74168411	KCNE3	1	11	A	52.9	5253	29.4	1176;1296	0;0	1336;1443	1;
6	114294308	ANK2	44	4	Т	99.5	576	22.0	0;0	227;346	0;0	1:
7	114279422	ANK2	38	4	A	100.0	473	21.5	0;0	0;0	188;285	0;
8	8787167	CAV3		3	С	57.3	2250	24.6	0;0	464;495	0;0	2;
9	8787168	CAV3		3	G	57.4	2250	24.6	1;4	0;1	461;490	2;
10	8787169	CAV3		3	G	57.4	2251	24.6	0;4	0;0	463;493	0;
11	8787170	CAV3		3	G	57.6	2249	24.6	0;1	0;0	459;493	0;
12	8787171	CAV3		3	Т	57.5	2247	24.3	2;4	4;0	4;0	44
13	8787172	CAV3		3	G	57.5	2247	24.3	0;4	0;0	459;493	0;
14	8787173	CAV3		3	G	57.5	2247	24.3	0;0	0;0	459;497	0;
4	0707174	0.000		-	-		00.47	0.0	0.0	100.107	0.0	- 1

Figure 6-162: Somatic Mutation Comparison Tool report

The Somatic Mutation Comparison Tool report is interactive.

To view alignments for selected projects, click View > Check Projects to View Alignments, or on the report toolbar, click the Check Projects to View Alignments icon
 .

The Sequence Display Settings dialog box opens. The dialog box displays all the projects for which you can view the alignments. By default, the option to Mark Center Lines (a green vertical line) in the alignment display is selected and there is an option to change the font size of the bases (the Base Display Size with a default value of eight) in the view.

Figure 6-163: Sequence Display Settings dialog box

Sequence Display Settings		- X
Check Projects to View Alignments		
C:\Users\Spectrum Writing\Spec C:\Users\Spectrum Writing\Spec		
4 [III]		,
Base Display Size: 8		
☑ Mark Center Lines	Ok.	Cancel

At a minimum, you must select the projects for which you want to view the alignments. You can also indicate whether to show the center lines in each alignment view and/or you can change the font size for the base display. After you click OK to close the dialog box, a window that is linked to the report table for the selected projects opens. You can do the following in this window:

- To change the focus of the report to the selected variant, double-click on a variant in the alignment view.
- To change the focus of the report to the selected variant, right-click on a variant in the alignment view, and on the context menu that opens, select Go to position in Mutation report.
- To change the focus in the corresponding alignment view to the selected variant, double-click on a variant in the Mutation report.

See Figure 6-164 on page 315.





Figure 6-164: Somatic Mutation Comparison Tool report showing individual projects

- To automatically save the Sequence Display Settings that you selected, click View > AutoSave Display Status. The next time you run a comparison in the Variant Comparison tool, these setting are automatically applied for the display.
- To search the displayed alignment, click Search > Sequence Search, or on the report toolbar, click the Sequence Search icon f_{∞} . The Search dialog box opens, where you can indicate how you want to search the displayed alignment—by Sequence, by Position (chromosome, chromosome position (for example, 1, 20000)) or by Gene Name. You can also click Option to search by a reverse complement sequence.



The Search Sequence function is enabled only when the Check Projects to View Alignments option is selected.



Search		×
Find		
C Search by Sequence	C Search by Position	Search by Gene Name
EPHB6	▼ Option	Previous <u>N</u> ext

• To change the current Mutation report display, click Settings > Settings to open the Mutation Report Settings dialog box. Select the Filter and Display options for the report.



For information about the available settings on each of the tabs on the Mutation Report Settings dialog box, see "Mutation Report settings" on page 213.

• To select the tracks that are to be queried for the projects, click Settings > Tracks Settings > Query to open the Query Tracks dialog box.



For detailed information about loading track data for previously run projects, see the Reference & Track Manager Tool User's Manual or Online Help.

• To change the display and filter settings for the tracks that are included with the projects, click Settings > Tracks Settings > Filter/Display to open the Variation Tracks Settings dialog box. Select the Filter and Display options for the report relative to the imported tracks.



For detailed information about the available settings on each of the tabs on the Variation Tracks Settings dialog box, see "Variation Tracks Settings dialog box" on page 232.

- To save the report and/or related information in a variety of formats, click the indicated option on the File menu:
 - Save Report To save the report to a tab-delimited text (*.txt) file.

A default name and location are provided for the file, but you can change both of these values.



You can also click the Save Report icon 🔲 on the report toolbar.

- Save VarMD Report To save the report as a VarMD report, which is a format that you can use in the third party VarMD tool.
- Save as Project Link To save all the information for the currently displayed comparison (the samples, the comparison settings, and the report settings) click File > Save as Project Link. The information is saved in an .ini file. You must specify the file name. By default, the file link is saved in the project folder for the project that was loaded last for the comparison, but you can always select a different location.
- To load a project link To load a previously saved comparison, click File > Load Project Link, and then scroll to and select the appropriate project link. The comparison is loaded into the Variant Comparison tool. The comparison display is determined by the information (the samples, the comparison settings, and the report settings) that was saved for the project link.

• To save SNP Sequences - To save the consensus sequences for all the variants that are displayed in the Somatic Mutation tool report, click File > Save SNP Sequences. The sequences are saved to a .fasta file in the project output folder for the first loaded project. The default name for the file is based on the name of the first loaded project appended with _SNP_Sequences, but you can change one or both of these values.

CNV (Copy Number Variation) tool (Dispersion and HMM)

You use the CNV tool to carry out parallel comparisons of the copy number variations in projects that were aligned independently to the same reference sequence. One project file must be the sample and all other project files must be the control. If Dispersion and HMM is the selected method, then the CNV tool first calculates the coverage ratios for each region. The tool then calculates the amount of dispersion (noise) for each region. The noise can be calculated automatically or manually. Finally, a Hidden Markov Model (HMM) uses the coverage ratio value and the amount of noise in each region to calculate a CNV classification (Duplication, Normal, Deletion, or Uncalled) for each region. Two options are available for calculating the coverage ratios:

- Normalized counts—Selected by default. Ratios are based on read counts for each region with both samples normalized by a size factor.
- RPKM—Ratios are based on RPKM measurements, where the measurements are read counts that are normalized by region length and the total number of reads.



For information about the SNP-based Normalization with Smoothing method for the CNV tool, see "To generate the CNV Tool report (SNP-based Normalization with Smoothing)" on page 332.

To generate the CNV Tool report (Dispersion and HMM)



The following procedure describes how to generate a new CNV Tool report. Optionally, you can click Load Settings to browse to and select a Settings file (.ini file) to generate the report based on the saved settings in the file. As you create a new report, at any time, you can click Default to return all values on all tabs to their default values.

1. On the Comparisons menu, select CNV Tool.

The CNV Tool window opens. The Method Selection tab is the active tab. See Figure 6-166 on page 318.

Method Selection	Data Input	Basic Settings	Advanced Settings	Report Settings	_
Dispersi	on and HM	1M			
Sample/T	otal ratios are	compared to exp	ected values and the	amount of noise affects	
likelihoods	entered into	a Hidden Marko	/ Model		
i Normali	zed Counts - I	Palios are based	on read counts forea	ich region with both	
sample	s normálized	by a rice factor.			
RPKM -	Ratios are b	ased on RPKM n	easurements (Read c	ounts normalized	
by real	on length and	(letal (cads)			
SNP-Ba	sed norma	lization with s	moothing		
					_
Save Settings	Load Setting	Default		OK	Cancel

Figure 6-166: CNV Tool window, Method Selection tab

- 2. Select Dispersion and HMM.
- 3. Leave Normalized Counts selected or select RPKM.
- 4. Open the Data Input tab.

Figure 6-167: CNV Tool window, Data Input tab



- 5. Load the Sample and Control project (*.pjt) files, and the do the following:
 - If you load only a single Control project file, select Single Control.
 - If you load multiple Control project files, select Multiple Controls, and then indicate how the control values are to be determined:

Control	Description
Best Match	Select the single control project that has the best correlation to the sample project when comparing coverage in each region as the control project. Ignore the other projects.
Average Controls	Use the average coverage in each region across all control projects as the control value.
Median Controls	Use the median coverage in each region across all control projects as the control value.

6. Open the Basic Settings tab.

Figure 6-168: CNV Tool window, Basic Settings tab

NV				×
Method Selection Data Input	Basic Settings	Advanced Settings	Report Settings	
Regions				
Use segments as defined in the segments as de	in reference file	\$		
(e) CDS	1	mBNA		
Continuous mRNA	0	Continuous CDS		
© RDI				
💿 Set incremental segment k	ength 1000) bates = 10	101	
(@) Contig	Chromosome			
🗇 Input region of interest (*.b	ied)			
C.\Users\Spectrum Writing	ng\Spectrum W	/riting.Into\Active Clien	Work\SoltGenel Set	
Limit reporting to BED	regions with sp	ecific descriptions	5ec	
Exclude Chr X				
Exclude Chr M				
Save Settings Load Settings	Default		ОК	Cancel
Save Settings Load Settings	Default	<< >>	AU 10	Lancel

7. Indicate how to define the segments that are to be analyzed and reported on by the tool.

Option	Description
Use segments as defined in the reference files.	 CDS - Report coverage levels for each coding region. mRNA - Report coverage levels for each mRNA region. (Coding and non-coding exons.) Continuous mRNA - Report coverage levels for the entire mRNA for a gene, one region per gene. Continuous CDS - Report coverage levels for the entire coding region for a gene, one region per gene. ROI - Report coverage levels based on Regions of Interest that are defined in a GenBank reference file. Note: For information about defining Regions of Interest in a GenBank reference file, see "Advanced GBK Editor tool" on page 280
Set incremental segment length	Specify the segment length, relative to either the reference positions in the contig or the chromosome positions.
Input region of interest (*.bed)	You can upload a Region of Interest file in a BED format. Note: For information about the required format for the BED file, see "BED file" on page 463.
Limit reporting to BED regions with specific descriptions	Optional. If you uploaded a Region of Interest file in a BED file format, then you can create a text file that lists the descriptions for selected regions of this file. (Each description must be its own line entry.) You can then upload this text file, and although all calculations are carried out on the whole BED file, only those regions of the uploaded BED file that have descriptions that match those contained in the text file are included in the CNV report. Note: Remember, BED file descriptions are optional, and if they are included in a BED file, then are located in
	Note: Remember, BED file descriptions are optional, and if they are included in a BED file, then are located in Column 4.

- 8. Optionally, select the chromosomes that are to be excluded from the analysis.
- 9. Optionally, open the Advanced Settings tab, select the appropriate fitting method, and then modify any of the default values as needed. See Figure 6-169 on page 321.

CNV × Method Selection Data Input Basic Settings Advanced Settings Report Settings Dispersion HMM settings Auto fitting Minimum Normalized Read Counts 100.00 Manual fitting log10(Dispersion)= a + b log10(Coverage) a = 0.7288 b = -0.8850 Minimum dispersion 0.002 Minimum region length 20 Expected CNV percentage 5.00 % Manual dispersion value Dispersion = 0.002 Estimated sample purity 100.00 % Custom fitting point number = 3 Save Settings Load Settings Default << >> OK. Cancel

Figure 6-169: CNV Tool window, Advanced Settings tab



If you make a change to any of the values that are listed in the table below, then at any time, you can click Default to return all values on all tabs on the dialog box their default values.

Fitting Method	Description
Auto fitting	Selected by default. Automatic fitting is the recommended approach for large panels (thousands of regions/exons) and whole exome sequencing. With this method a line is automatically fit to the dispersion fitting points. Manual fitting is recommended for small targeted panels (< hundreds of regions/exons), especially if the data does not have a lot of noise. The number of points for automatic fitting should be sufficient enough to have one fitting point accurately reflect a sufficient number of raw data points.
	 If Custom fitting point number is not selected, then NextGENe automatically selects the appropriate number of points based on the regions. If Custom fitting point number is selected, then typically, the default value of 15 fitting points is acceptable for most data for large panels; however, if you have a small number of raw data points, then the rule of thumb is one fitting point for every 100 raw data points, so you can decrease this value as needed. For example, if your data has 375 regions, then you would set the number of points to three or four fitting points for Auto fitting. Even with a smaller number of regions, the number of points for Auto fitting should never be less than three.
	Note: Typically, even if you know that a manual fitting or a manual dispersion is the appropriate approach for your data, you should run an automatic fitting first, and then view the resulting data so that you have an idea of how to modify all the fitting settings for either method.

Fitting Method	Description
Manual fitting	For Manual fitting, "a" and "b" represent the values for the line that is fit to the dispersion fitting points. These values are automatically populated after an Automatic fitting. You must modify these values for a Manual fitting. The Minimum Dispersion value is the minimum threshold for the dispersion of the data, regardless of the value that is set for "a." As with Auto fitting, the number of points for manual fitting should be sufficient enough to have one fitting point accurately reflect a sufficient number of raw data points.
	• If Custom fitting point number is not selected, then NextGENe automatically selects the appropriate number of points based on the regions. If Custom fitting point number is selected, then typically, the default value of 15 fitting points is acceptable for most data for large panels; however, if you have a small number of raw data points, then, again, the rule of thumb is one fitting point for every 100 raw data points, so you can decrease this value as needed.
Fixed dispersion value	Select this option to use a single dispersion value for all regions in lieu of fitting a line to all the dispersion points. As with the other fitting methods, the number of points for manual dispersion should be sufficient enough to have one fitting point accurately reflect a sufficient number of raw data points.
	• If Custom fitting point number is not selected, then NextGENe automatically selects the appropriate number of points based on the regions. If Custom fitting point number is selected, then typically, the default value of 15 fitting points is acceptable for most data for large panels; however, if you have a small number of raw data points, then, again, the rule of thumb is one fitting point for every 100 raw data points, so you can decrease this value as needed.
	Note: The Fixed dispersion option is useful for targeted panels where the dispersion (noise) is relatively low.
	 Auto-Detect: The manual dispersion value is automatically adjusted. This automatically chosen value works well in most cases, but you can modify this value as needed. You can select this value to be displayed in the CNV report.

10. Leave the default values for the other HMM settings as-is, or modify them as needed.

Setting	Description	
Minimum RPKM	Regions with a total RPKM that are less than the indicated value are identified as "uncalled."	
Minimum region length	Minimum size of a region in base pairs for the region to be included in the CNV Tool report.	
Normalized ratios by the median	Applicable only when the RPKM option is selected. Normalize the ratios by the median value to ensure that the median ratio value is 0.5.	
Expected CNV Percentage [5.00]%	Indicates the percentage of regions in which CNV calls are expected to be made.	
	Note: Typically, the default value of 5% is acceptable for most data. If the data is confident (not noisy), then increasing this value does not significantly increase the percentage of regions in which CNV calls are made. If the data is not confident (noisy), then increasing this value increases the percentage of regions in which CNV calls are made.	

Setting	Description
Estimated sample purity	If the sample is mixed, or it has possible contamination, then enter an appropriate sample purity to adjust the calculations accordingly.

- 11. Optionally, open the Report Settings tab and do either or both of the following as needed:
 - For the Display settings, select the columns that are to be included in the report, or clear the options for the columns that are not to be included.
 - For the Filter settings, specify the thresholds for the regions that are to be included in the report.

Figure 6-170: CNV Tool window, Report Settings tab

Method Selection	Data Input	Basic Settings Advanced Setti	ings Report Settings	
Display				
 ✔ Index ✔ Chr ♥ Nr ♥ Chr Positi ♥ Chr Positi ♥ Gene ♥ CDS 	umber on Start	Locus Tag Start End Length Original Coverage Position Selected Nomaized Coverage	Neighbor Ratios Dispersion Hmm	
RNA Acc Protein Acc	cession	Control Allele Ø Sample Allele Ø Log2Ratio		
Filter V Display De V Display No V Display Du V Display Un	rmal plication	Log2 Ratio <= Scores >= Minimum Coverage	0.700 or >= -0.700 3.000 At Least For One Project >: 5.01 ath low coverage	

Setting	Description
Display Settings	
Index	An ordered count of the segments that are used in the report.
Chr	
Name	 The name of the chromosome that the segment is on.
Number	The number of the chromosome that the segment is on.
Chr Position Start	The base number that indicates where the segment starts in the chromosome.
Chr Position End	The ending base number that indicates where the segment ends in the chromosome.
Gene	The gene name for the segment when the segment is the whole gene or the name of the gene on which the segment is found.

Setting	Description
CDS	The coding sequence number for the segment.
RNA Accession	Show the RNA accession for the gene from NCBI.
Protein Accession	Show the protein accession for the gene from NCBI.
Description	Available if the reference file is a .fasta file with multiple segments. Select this option to display the title line for each segment in the Description column.
Contig	The contig that the segment is on. The contig is based on the genome assembly from the NCBI.
Locus Tag	An alternate way to identify the gene.
Start	The starting location for the reference region.
End	The ending location for the reference region.
Length	The total length of the reference region, which provides for easy identification of expressed regions by size (such as when locating small RNA transcripts).
Dispersion	The dispersion value for the region. N/A for Uncalled regions.
Normalized Likelihoods	The normalized likelihood value for each potential CNV call (duplication, deletion, or normal). A likelihood value closer to zero indicates an increased likelihood for the call.
Display settings ava	ailable with Normalized Counts selected
Ratio	The ratio of the sample RPKM to total RPKM for the region.
Total Read Counts	The sum of the Sample read counts and the Control read counts.
Display settings ava	ailable with RPKM selected
RPKM	Reads per Kilobase Exon Model per Million mapped reads.
	RPKM = 10^9 * R / (T*L)
	where:
	 R = Number of mapped reads in a region
	• T = Total number of mapped reads.
	• L = Length of the region.
	Normalizes the expression levels based on the length of the reference region and the total number of aligned reads.
FPKM	Applicable only if the project used paired end data. Fragments per Kilobase of exon per Million mapped reads.
	FPKM = 10^9 * F / (T*L)
	where:
	 F = Number of mapped fragments in a region and:
	 A "fragment" corresponds to a pair of reads.
	Single reads are not counted.
	 The position of a fragment is the location between the two 5' ends of the pairs.
	• T = Total number of mapped fragments.
	• L = Length of the region.
	Normalizes the expression levels for paired end data based on the length of the reference region and the total number of aligned reads.
Ratio	The ratio of the sample RPKM to total RPKM for the region

Setting	Description
Total RPKM	The sum of the Sample RPKM and the Control RPKM.
Filter Settings	
Display Deletion	Selected by default. Show CNVs that are classified as Deletions. Clear this option to hide this classification from the CNV Tool report.
Display Normal	Selected by default. Show regions that are classified as Normal (little evidence of a CNV). Clear this option to hide this classification from the CVN Tool report.
Display Duplication	Selected by default. Show CNVs that are classified as Duplications. Clear this option to hide this classification from the CNV Tool report.
Display Uncalled	Selected by default. Show CNVs that are classified as Deletions. Clear this option to hide this classification from the CNV Tool report.
Score	Filter the calls shown based on their respective scores. (Deletion, Normal, and Duplication.)The default value is 1.000, which means that all calls with a score > 1.000 are shown in the report. You can modify this value as needed.

12. Optionally, click Save Settings to save these settings to a Settings file (.ini file).



You can click Load Settings to select this Settings file at a later date and generate the report according to the saved settings in the file.

13. Click OK.

The CNV Tool report is generated.

Figure 6-171: CNV Tool report example (Dispersion and HMM)

CNV	leport													
2.50	1	NE												
Semple	A.													
Control	F													
Index	Chr	Chr Start	Chr End	Gene	CDS	Ratio	Total Read C	Dispersion	Nomelized Likelihoods	Deletion Score	Normal Score	Duplication Score	HMM Call	Normalized Read Count (Sample, Control)
1	chiri	17345351	17345478	SDHB	8	0.3670	981 000	0.0453	-0.21:-0.50:-1.19	416	1.67	0.29	Deletion	360.000.621.000
Į.	chr1	17349078	17349250	SDHB,*	7	0.3464	1556.000	0.0319	0.10-0.72-1.83	6.88	0.92	0.05	Deletion	539 000 1017 000
3	chr]	17350443	17350594	SDHB -	5	0.3270	1749.000	0.0319	-0.07-0.88-210	8.52	0.52	0.03	Deletion	572 000 1177 000
4	chr1	17354219	17354385	SDHB -	5	0.3511	1592 000	0.0313	-0.11 -0.69 -1.77	6.51	1.00	0.07	Detetion	559.000 1033.000
5	chr1	17355070	17355256	SDHB -	4	0.3312	2237.000	0.0119	-0.07-0.84:-2.04	8.15	0.60	0.04	Deletion	741.000:1495.000
6	chr1	17359530	17359665	SDHB -	3	0.3254	1183.000	0.0387	-0.090.761.78	7.23	0.92	0.07	Deletion	385.000.799.000
F	chr1	17371231	17371408	SDHB:-	2	0.3439	1605.000	0.0319	0.03 0.74-1.85	7.08	0.87	0.05	Delution	552 000 1053 000
0	chr3	9040964	9041024	SRGAP3		0.3241	469.000	0.0044	-0.23:-0.51:-0.97	3,03	1.50	0.50	Deletion	152.000.317.000
9	chr3	10183507	10183605	VHC+	1	0.2821	319.000	0.1168	-0.23-0.53-0.91	3.61	1.51	0.56	Deletion	90.000,229.000
10	chr3	10183607	10183705	VHL+	1	0.2549	408,000	0.0949	-016-0.83-1.17	5.23	1.15	0.30	Deletion	104.000.304.000
11	chr3	10183707	10183896	VHL +	1	0.3179	969.000	0.0458	0 11-0 72-1 60	6 65	0.92	0.11	Delotron	308.000.661.000
12	chr3	10180173	10188345	VHL .	2	0.3561	1699 000	0.0313	-012-065-170	6.13	1.10	0.03	Deletion	605 000 1094 000
13	chr3	10191446	10191544	VHL+	1	0.3464	1247.000	0.0171	-0.12-0.65-1.60	6.06	0.09	0.11	Deletion	432 000,815,000
14	chir3	10191546	10191674	VHL .	3	0.3245	1328.000	0.0351	-0.080.83:-1.95	7.99	8.69	0.05	Deletion	431.000.897.000
15	chr3	12955952	12956012	IDSECT:-		0.3240	645.000	0.0645	0.18-0.57:1.17	4.70	1.37	0.31	Delution	209.000.436.000
16	chr3	14107416	14107514	XPC -	16	0.3115	581.000	0.0705	-0.10:-0.50;-1.16	479	1.32	0.31	Deletion	101.000,400.000
17	chr3	14187516	14187684	MPG-	16	0.3572	267 000	0.0558	-0.22-0.50-7.09	3.99	1.66	0.37	Deletion	274 000:493 000
18	chr3	14188765	14188904	XPC-	15	0.3298	1416.000	0.0333	-0.08-0.83-1.98	7.96	0.70	0.05	Deletion	467.000,949.000
19	chr3	14189383	14189526	XPC: *	14	0 3230	1055.000	0.0423	010-073-166	6.83	0.89	0.10	Deletion	344,000,721,000
20	chr3	14190037	14190135	XPC	13	0.3823	688.000	0.0511	0.30-0.43-0.89	3.01	2.02	0.59	Deletion	263.000 425.000
21	chr3	14190137	14190256	XPC-	13	0.3374	1227.000	0.0176	-0.11:-0.70:-1.69	6.60	0.95	0.03	Deletion	414.000,813.000
22	chr3	14190289	14190473	XPC-	12	0.3181	1726.000	0.0319	-0.05-0.96-2.23	9.33	0.51	0.03	Deletion	549.000.1177.000
23	chr3	14193810	14193941	XPC -	11	0.3130	920.000	0.0479	0.11.0.72-1.58	6.66	0.91	0.11	Deletion	288.000.632.000
24	chr3	14197810	14197908	XPC -	10	0.3520	838,000	0.0518	-0.20-0.53:-1.18	4.40	1.53	0.30	Deletion	295 000 543 000
25	chr3	14197910	14198020	XPC-	10	0.3198	935,000	0.0472	-011:-069-754	6.36	0.98	013		299.000,636.000
25	Suis-	14399498	14199594	ver	4	0.3400	267-000	0.05.40	.0.19-0.55-1.22	A.96	1.40	0.27	and a	271 000 525 000

The CNV Tool report is interactive:

- To view the region of the genomic database in the Database of Genomic Variants (DGV) for which the call was made, click the call type in the HMM Calls column.
- To load different projects and/or change the project settings, on the report menu, click File > Load Projects, or on the report toolbar, click the Load Projects icon the CNV Tool window and make the appropriate changes.
- To modify the report settings, on the report menu, click Settings > Settings, or on the report toolbar, click the Settings icon needed. The report Bettings dialog box and modify the report settings as needed. The report display is dynamically updated after you save the modifications.
- To save the report to a text file, on the report menu, click File > Save Report, or on the report toolbar, click the Save Report icon . A default name and location are provided for the file, but you can change both of these values.
- To generate the Block CNV report, on the report toolbar, click the Block CNV report icon
 ▶ E. See "Block CNV report" below.
- To generate the graphical display of the data, on the report toolbar, click the CNV Graphs icon 😹 . See "CNV Graphs" on page 329.

Block CNV report

The Block CNV report groups together consecutive regions that have a CNV into a single report line. Multiple genes can be included in the same block. You can use the Block CNV Report to focus on consecutive regions that show evidence of a CNV.

Figure 6-172:	Block CNV	′ report example
---------------	-----------	------------------

Block	CNV Repo	ort.										00
		-										
mpl	A											
ntro	F											
эx	Chr	Chr Start	Chr End	Gene	Number of Regions	Median Ratio	Median Total Read Co	Median Del Score	Median Dup Score	Max Del Score	Max Dup Score	HMM Calls
	chr1	17345351	17371408	SDHB	7	0.3439	1592.000	7.08	0.06	8.52	0.29	Deletion
	chr3	9040964	52443784	SRGAP3	237	0.3404	998.000	5.33	0.17	10.41	1.52	Deletion
	chr7	6013005	6045687	TRGVA	27	0.6238	1910.000	0.02	5.30	0.22	6.76	Duplication
	chr7	64721516	66460429	ZNF92:S	8	0.3412	1189,500	5.14	0.19	8.24	0.34	Deletion
	chr8	30915939	36092451	WRN	46	0.3260	927.500	5.86	0.15	10.69	0.96	Deletion
	chr9	21802723	27687189	MTAP	28	0.0023	565.000	52.36	0.00	80.00	0.25	Deletion
	chr11	10809832;	133495580	ATM	159	0.3333	926.000	5.28	0.20	10.90	1.18	Deletion
	chr12	112893725	133263920	PTPN11:	81	0.6728	2294,000	0.00	7.50	0.33	9.82	Duplication
	chr17	6847043	17131476	ALOX12;1	42	0.3330	1005.000	5.46	0.17	8.53	0.89	Deletion
	chr17	40467738	41246725	STAT3; E	79	0.6159	2136.000	0.02	5.00	0.27	6.99	Duplication
	chrX	69254730	154005163	EDA; DK	61	0.3296	987.000	5.45	0.17	9.27	1.49	Deletion

The Block CNV report is interactive:

- To view the region of the genomic database in the Database of Genomic Variants (DGV) for which the call was made, click the call type in the HMM Calls column.
- To modify the report settings, on the report menu, click Settings > Settings, or on the report toolbar, click the Settings icon not to open the Block CNV Report Settings dialog box. The dialog box has two tabs—Advanced Settings and Report Settings. The Report

Settings tab is the open tab. Modify the report settings on either tab or both tabs as needed. The report display is dynamically updated after you save the modifications.

Figure 6-173: Block CNV Report Settings dialog box, Report Settings tab

nced Settings	Report Settings	
isplay		
Index Chr Chr Nu Nu Chr Positio Chr Positio Chr Positio RhA Acces Protein Ac CDescription	mber n Start n End Regions ssion cession	Locus Tag Stat ■ End ♥ Length □ Dignersion ■ Normalized Coverage ♥ Ratio ♥ Total Read Counts
Contig ilter Display Del Display Nor	mal	Median Deletion Score > 1.000
📝 Display Dup	dication	Median Duplication Score > 1.000

Setting	Description
Report Settings - Display Settings	
Index	An ordered count of the segments that are used in the report.
Chr	
NameNumber	 The name of the chromosome on which the segment is located.
	• The number of the chromosome on which the segment is located.
Chr Position Start	The base number that indicates where the segment starts in the chromosome.
Chr Position End	The ending base number that indicates where the segment ends in the chromosome.
Gene	The gene name for the segment when the segment is the whole gene or the name of the gene on which the segment is found.
Number of Regions	The number of consecutive regions that have a CNV and that were grouped together as a result.
RNA Accession	Available only for the CNV report.
Protein Accession	Available only for the CNV report.

Chapter 6 Sequence Alignment Tool


Setting	Description
Description	Available if the reference file is a .fasta file with multiple segments. Select this option to display the title line for each segment in the Description column.
Contig	The contig on which the segment is located. The contig is based on the genome assembly from the NCBI.
Locus Tag	Available only for the CNV report.
Start	The starting location for the reference region.
End	The ending location for the reference region.
Length	The total length of the reference region, which provides for easy identification of expressed regions by size (such as when locating small RNA transcripts).
Original Coverage	Available only for CNV report.
Dispersion	The dispersion value for the region. N/A for Uncalled regions.
Normalized Coverage	Available only for CNV report.
The following two Display settings a	re available only if RPKM is selected.
Ratio	The ratio of the sample RPKM to total RPKM for the region
Total RPKM	The sum of the Sample RPKM and the Control RPKM.
The following two Display settings a	re available only if Normalized Counts is selected.
Ratio	The ratio of the sample RPKM to total RPKM for the region.
Total Read Counts	The sum of the Sample read counts and the Control read counts.
Report Settings - Filter Settings	
Display Deletion	Selected by default. Show CNVs that are classified as Deletions. Clear this option to hide this classification from the CNV Tool report.
Display Normal	Selected by default. Show regions that are classified as Normal (little evidence of a CNV). Clear this option to hide this classification from the CVN Tool report.
Display Duplication	Selected by default. Show CNVs that are classified as Duplications. Clear this option to hide this classification from the CNV Tool report.
Median Deletion Score > 1.000	The median deletion threshold across all the regions in the block for the block to be included in the report.
Max Deletion Score > 1.000	The maximum deletion threshold across all the regions in the block for the block to be included in the report.
Median Duplication Score > 1.000	The median duplication threshold across all the regions in the block for the block to be included in the report.
Max Duplication Score > 1.000	The maximum duplication threshold across all the regions in the block for the block to be included in the report.


Setting	Description
Advanced Settings	
Ignore up to [0] regions when merging	If there are "n" number of regions that are reported as normal within a larger number of regions that show the same CNV, then these normal regions are ignored and the regions with the same CNV are merged to create blocks. Note: Uncalled regions are automatically ignored.

To save the report to a text file, on the report menu, click File > Save Report, or on the report toolbar, click the Save Report icon . A default name and location are provided for the file, but you can change both of these values.

CNV Graphs

To generate the graphical display of CNV data, on the CNV report toolbar, click the CNV Graphs icon \bowtie .





• All Chromosomes graph—The All Chromosomes graph displays all the regions across all the chromosomes in the project. Duplications are displayed in green. Deletions are displayed in red. Normal regions, or regions where the data was insufficient for making a call, are displayed in gray. The horizontal red and green lines represent the coverage ratios for duplications and deletions, respectively, in an ideal project without noise.

- Raw Data Dispersion graph—The Raw Data Dispersion graph displays the coverage ratios for all the raw data points. The red lines indicate the confidence interval of the data based on the expected CNV% for the data.
- Filtering Points Dispersion graph—The Filtering Points Dispersion graph displays the dispersion value for each filtering point at the indicated coverage level.

The graphs are interactive:

- Zoom In Hold down the left mouse button and draw a box from the upper left hand corner of any region in a graph towards the lower right hand corner. A box is formed around the area that being reduced for viewing.
- Zoom Out Hold down the left mouse button and draw a box from the lower right hand corner of any region in the graph towards the upper left hand corner.



The magnification for zooming out is always 100%.

- Highlight ROI Click Select ROI to open the Regions of Interest dialog box that displays all the chromosomes in the project on which ROIs are located. Select a chromosome, and then click OK. The All Chromosomes graph is zoomed in on the selected ROI and all the raw data points in the selected ROI are highlighted in purple in the Raw Data Dispersion graph.
- Saving the graph to a file Right-click any graph, and then select Save Picture to save the graph as PNG file. You must name the graph and select a location in which to save the graph.

CNV (Copy Number Variation) tool (SNP-based Normalization with Smoothing)

You use the CNV tool to carry out parallel comparisons of the copy number variations in projects that were aligned independently to the same reference sequence. One of the project files must be the sample and all other project files must be the control. The SNP-based Normalization with Smoothing coverage option has three components—the Log2 ratio calculated based on the perfect heterozygote SNP positions, the score, and the Log2 ratio based on the SNP positions for adjacent (neighbor) regions.

Log2 ratio calculated based on the perfect heterozygote SNP positions—The CNV tool checks the coverage for at least three positions in each region. *Perfect heterozygote SNP positions*, which are positions with a user-specified variant frequency in the selected regions in at least one sample, are chosen first. If three perfect heterozygote SNP positions are not found, the tool chooses positions every 100 bp, starting in the middle of the region. If there are more than 100 bp without a Perfect heterozygote SNP position, the tool chooses additional positions every 100 bp. The tool then calculates the median coverages for these positions and normalizes the median coverage values relative to the global

coverage. The Log2 ratio of the normalized coverage values of the two samples is then calculated.

- Score—A Phred-scaled score is calculated for each potential call (duplication, deletion, and normal) based on a binomial distribution that considers the coverage.
- Log2 ratio for adjacent (neighbor) regions—Considers the Log2 ratio calculated based on SNP positions for the three regions that are directly upstream and the three regions that are directly downstream of the current region.

CNV calls are made according to the following:

Component Values	Call
Upstream and downstream neighbor log2 ratio and current log2 ratio = 0	Uncalled
Log2ratio ≥ 20	Duplication
Log2ratio <u><</u> -20	Deletion
Log2ratio > 2 and duplication score > 20	Duplication
Log2ratio < -2 and deletion score > 20	Deletion
Upstream and downstream neighbor log2 ratios > 0.4 and duplication score > 10	Duplication
Upstream and downstream neighbor log2 ratios < -0.5 and deletion score > 10	Deletion
Neighbor called as a duplication and upstream, downstream and current log2 ratios > 0.3	Duplication
Neighbor called as a Deletion and upstream, downstream and current log2 ratios < -0.4	Deletion
Upstream, downstream, and current log2 ratios are > -0.5 and < 0.4	Normal
The median of upstream, downstream and current log2 ratios > 0.4 and duplication score > 10	Duplication
The median of upstream, downstream and current log2 ratios < -0.5 and deletion score > 10	Deletion
The median of upstream, downstream and current log2 ratios < 0.4 and > -0.5	Normal
Neighbor called as a Duplication and duplication score > 1	Duplication
Neighbor called as a Deletion and deletion score > 1	Deletion
Neighbor called as Normal and normal score > deletion score and > duplication score	Normal
If none of the above criteria are met, then Uncalled, unless:	
 If Uncalled and the coverage for the sample and the control > 1000x, the current log2 ratio > 0.5, and the duplication score > 100 	Duplication
 If Uncalled and the coverage for the sample and the control > 1000x, the current log2 ratio < -0.9 and the deletion score > 100 	Deletion



For information about the Dispersion and HMM method for the CNV tool, see "To generate the CNV Tool report (Dispersion and HMM)" on page 317.


To generate the CNV Tool report (SNP-based Normalization with Smoothing)

The following procedure describes how to generate a new CNV Tool report. Optionally, you can click Load Settings to browse to and select a Settings file (.ini file) to generate the report based on the saved settings in the file. As you create a new report, at any time, you can click Default to return all values on all tabs to their default values.

1. On the Comparisons menu, select CNV Tool.

The CNV Tool window opens. The Method Selection tab is the active tab.

Figure 6-175: CNV Tool window, Method Selection tab



2. Select SNP-Based normalization with smoothing.

3. Open the Data Input tab.

Figure 6-176: CNV Tool window, Data Input tab

Method Selection	Data Input	Basic Settings	Advanced Settings	Report Settings
Input	Sample			Control
Add		emove		ydd <u>B</u> emove
				ontrol Controls Match age
Save Settings	Load Setting	s Default) DK Cancel

- 4. Load the Sample and Control project (*.pjt) files, and then do the following:
 - If you load only a single Control project file, select Single Control.
 - If you load multiple Control project files, select Multiple Controls, and then indicate how the control values are to be determined:

Control	Description
Best Match	Select the single control project that has the best correlation to the sample project when comparing coverage in each region as the control project. Ignore the other projects.
Average Controls	Use the average coverage in each region across all control projects as the control value.
Median Controls	Use the median coverage in each region across all control projects as the control value.

5. Open the Basic Settings tab.

Figure 6-177: CNV Tool window, Basic Settings tab

Regions: Use segments as defined in reference files: CDS CDS Continuous mRNA Set incremental segment length Contrig Charnonoum Input region of interest ("bed) CUSers Spectrum Writing VSpectrum Writing InfoVActive Client Write VSoltGenel Exclude Chr X Exclude Chr X Exclude Chr M	Use segments as defined in reference files CDS mRNA Continuous mRNA Continuous CDS RDI Contegion of interest ("bed) C. Users/Spectrum Writing Into/Active Client Work/SoftGenel Set Limit reporting to BED regions with specific descriptions E. Limit reporting to BED regions with specific descriptions E. Limit reporting to BED regions with specific descriptions E. Exclude Chr X	thod Selection Data Input	Basic Settings	Advanced Settings	Report Settings
Use segments as defined in reference files CDS MRNA Continuous mRNA Continuous CDS RDI Set incremental segment length 10000 kdstar() = (01) Contig Conti	Use segments as defined in reference files CDS MRNA Continuous mRNA Continuous CDS RDI Set incremental segment length 10000 kesser(1 = 4 (01) Conteg Conteg Conteg Conteg Contest ("bed) CUsers/Spectrum Writing Info/Active Client Work/SoftGenel Set Limit reporting to BED regions with specific descriptions Exclude Chr/X Exclude Chr/X Exclude Chr/Y				
CDS Im RNA Continuous RNA Continuous CDS RDI Set incremental segment length 10000 Issue() > 100 (Contig Contig Contig Contig Contig Contig Contig Context() Set	CDS RDI Continuous RNA Continuous CDS RDI Set incremental segment length T0000 Securit (1 > 109) Contig Context Conte	The second second second second second			
Continuous CDS RDI Set incremental segment length Continuous CDS Continuou	Continuous mRNA Continuous CDS RDI Set incremental segment length Continuous CDS Contig Cont	Use segments as defined	l in reference file	s	
BDI Set incremental segment length 10000 bases (> 100) Contog Grannatome Input region of interest (bed) C.VUsers/Spectrum Writing/Spectrum Writing Info/Active Client Work/SchrGenel) Elimit reporting to BED regions with specific descriptions Exclude Chr X Exclude Chr Y	BDI Set incremental segment length 10000 bases (> 100) Contig Chromosome Input region of interest (bed) C.VUsers/Spectrum Writing/Spectrum Writing Info/Active Ellent Work/Softräenel) Set Limit reporting to BED regions with specific descriptions Set Exclude Chr X Exclude Chr Y	🕲 CDS	1.	mBNA	
Set incremental segment length 10000 Setter (>> (00) Contig Chromosome Input region of interest (>bed) C.V.Sers/Spectrum Writing/Spectrum Writing Info/Active Client Wratk/SchrGenel E.Limit reporting to BED regions with specific descriptions E.Exclude Chr X. E.Exclude Chr Y	Set incremental segment length 10000 Setter (1991) Contig Chromosome Input region of interest (1:bed) C.V.Sers/Spectrum Writing/Spectrum Writing Info/Active Client Work/SolfGenel) E.Limit reporting to BED regions with specific descriptions E.Exclude Chr X. E.Exclude Chr Y.	Continuous mRNA.	0	Continuous CDS	
Contig Christiansome Input region of interest ("bed] C. Users/Spectrum Writing MolActive Chert Work/SoldGene) E. Limit reporting to BED regions with specific descriptions E. Exclude Chr X E. Exclude Chr Y	Contig Christians http://contig.conttg.conttg.conttg.conttg.conttg.conttg.cont	🗇 RDI			
Input region of interest ("bed) C. Users/Spectrum Writing Info/Active Client Work/Solt/Seriel Set Limit reporting to BED regions with specific descriptions Exclude Chr X Exclude Chr Y	Input region of interest (".bed) C. Users/Spectrum Writing Into/Active Client Work/SchtGenel Set Limit reporting to BED regions with specific descriptions Exclude Chr X Exclude Chr Y	Set incremental segment	length 1000	0 bates() = (00 Y
Input region of interest ("bed) C \Users\Spectrum Writing\Spectrum Writing Into\Active Client Work\Solt\Serter Set Limit reporting to BED regions with specific descriptions Exclude Chr X Exclude Chr Y	Input region of interest (".bed) C. Users/Spectrum Writing Into/Active Client Work/SoftGenel Set Limit reporting to BED regions with specific descriptions Exclude Chr X Exclude Chr Y	() Contig	Chromosome		
Limit reporting to BED regions with specific descriptions Set Exclude Chr X Exclude Chr Y	Limit reporting to BED regions with specific descriptions Set Exclude Chr X Exclude Chr Y				
Exclude Chr X	Exclude Chr X	C.\Users\Spectrum Wri	ting\Spectrum W	/riting.Into\Active Clier	ht Work \SoftGenel Set
Exclude Chr M	Exclude Chr M	and and attack and a			
		The second			

6. Indicate how to define the segments that are to be analyzed and reported on by the tool.

Option	Description
Use segments as defined in the	CDS - Report coverage levels for each coding region.
reference files.	 mRNA - Report coverage levels for each mRNA region. (Coding and non-coding exons.)
	 Continuous mRNA - Report coverage levels for the entire mRNA for a gene, one region per gene.
	 Continuous CDS - Report coverage levels for the entire coding region for a gene, one region per gene.
	 ROI - Report coverage levels based on Regions of Interest that are defined in a GenBank reference file.
	Note: For information about defining Regions of Interest in a GenBank reference file, see "Advanced GBK Editor tool" on page 280
Set incremental segment length	Specify the segment length, relative to either the reference positions in the contig or the chromosome positions.

Option	Description
Input region of interest (*.bed)	You can upload a Region of Interest file in a BED format.
	Note: For information about the required format for the BED file, see "BED file" on page 463.
	Note: To highlight specific Regions of Interest for the purpose of checking allele ratios to visualize copy number and view this information in the CNV graph (see "CNV Graphs" on page 346), you must select Input region of interest, and then in the BED file, the optional 4th column for these regions must contain an rs accession number based on the dbSNP database. These regions are referred to as "SNP Regions" in the CNV graphs. See Figure 6-178 below for an example.
Limit reporting to BED regions with specific descriptions	Optional. If you uploaded a Region of Interest file in a BED file format, then you can create a text file that lists the descriptions for selected regions of this file. (Each description must be its own line entry.) You can then upload this text file, and although all calculations are carried out on the whole BED file, only those regions of the uploaded BED file that have descriptions that match those contained in the text file are included in the CNV report.
	Note: Remember, BED file descriptions are optional, and if they are included in a BED file, then are located in Column 4.

Figure 6-178: BED file with column identifying specific Regions of Interest for the purpose of checking allele ratios to visualize copy number

	А	В	С	D	E
1	chr1	4849353	4849414	rs2235438	
2	chr1	4955831	4955892	rs6426446	
3	chr1	7434513	7434574	rs845215	
4	chr1	7520098	7520159	rs1725235	-
5	chr1	14192641	14192702	rs1203659	
6	chr1	15295988	15296049	rs880922	

- 7. Optionally, select the chromosomes that are to be excluded from the comparison.
- Optionally, open the Advanced Settings tab and modify any of the default values as needed for the Neighbor ratio settings and/or the call settings. See Figure 6-179 on page 336.

ethod Selection	Data Input	Basic Settings	Advanced Settings	Report Setti	ngs
Neighbor ratio :		La ment			
	heterozygote		%		
Smc Smc	oth Log2Rat	io			1.1
(E) High	resolution (3) 🙆 Low res	olution (41) 👘 Dus	tomized resolu	ution 21
Deletion and d	uplication cal	ls using log2 ratio			
🗇 Auto					
Man	ual -0.60	0 0.50	Display limits	-3.00	3.00
	e block		🙄 Single point		
(9) Larg					
igi Largi					


Figure 6-179: CNV Tool window, Advanced Settings tab

Setting	Description					
Note: If you make a change to any of the values below, at any time, you can click Default to return all values on all tabs on the dialog box their default values.						
Neighbor ratio settings						
Perfect heterozygote SNP	Indicates the frequency requirements for perfect heterozygote SNP positions. Both the reference and variant allele must be found at frequency that is above the specified threshold, or the SNP is not used to determine the median coverage for the region. The default value is 40%, which means that any variant that is found at a frequency between 40% to 60% is considered to be a perfect heterozygote SNP.					
Smooth Log2Ratio	Selected by default. You can clear this option to omit the step of checking Neighbor Ratios.					
High Resolution (3)	 Optimizes the detection sensitivity to call CNVs for smaller regions, such as CNVs that include only part of a gene. Considers three regions total - the region itself and one neighbor region on each side. 					
Low Resolution (41)	 Optimizes the detection to call larger CNVs, such as CNVs that include multiple genes or a whole chromosome. Considers 41 regions total - the region itself and 20 neighbor regions on each side. 					
Customized resolution	 Specify the number of regions that are to be considered for making the CNV call, where the number must reflect the region itself and the same number of neighbor regions on each side. 					

Setting	Description					
Deletion and duplication calls using log2 ratio						
• Auto	NextGENe automatically makes the calls.					
• Manual	 Manually define the range of log2ratio values for regions to be reported as Normal (default is -0.60 - 0.50). Regions with log2ratio values outside of this range are reported as Deletion or Duplication. 					
Display limits	Available only if Manual is selected for the call option. Set the range that is displayed for the minimum and maximum values on the Log2ratio (Y) axis for the CNV graph relative to values defined for the Manual option. See "CNV Graphs" on page 346.					
Large blockSingle point	 Detect and report on CNV regions that are ≥ 3 regions. Detect and report on CNVs regions that are single regions or larger. 					

- 9. Optionally, open the Report Settings tab and do either or both of the following as needed:
 - For the Display settings, select the columns that are to be included in the report, or clear the options for the columns that are not to be included.
 - For the Filter settings, specify the regions that are to be included in the report based on the call and, optionally the log2ratio, score, and/or coverage.

Figure 6-180: CNV Tool window, Report Settings tab



Setting	Description
Display settings	
Index	An ordered count of the segments that are used in the report.
Chr	
Name	The name of the chromosome that the segment is on.
Number	The number of the chromosome that the segment is on.
Chr Position Start	The base number that indicates where the segment starts in the chromosome.
Chr Position End	The ending base number that indicates where the segment ends in the chromosome.
Gene	The gene name for the segment when the segment is the whole gene or the name of the gene on which the segment is found.
CDS	The coding sequence number for the segment.
RNA Accession	Show the RNA accession for the gene from NCBI.
Protein Accession	Show the protein accession for the gene from NCBI.
Description	Available if the reference file is a .fasta file with multiple segments. Select this option to display the title line for each segment in the Description column.
Contig	The contig that the segment is on. The contig is based on the genome assembly from the NCBI.
Locus Tag	An alternate way to identify the gene.
Start	The starting location for the reference region.
End	The ending location for the reference region.
Length	The total length of the reference region, which provides for easy identification of expressed regions by size (such as when locating small RNA transcripts).
Position Selected	The chromosome position for the heterozygous SNP at which the median coverage value is obtained.
Original Coverage	The un-normalized median coverage values for the region for the sample and control.
Normalized Coverage	The median coverage following global normalization for the region for the sample and the control.
Control Allele	Read count for the alleles at the Position Selected in the control project. If there are more than two alleles, then only the two most frequent alleles are reported.
Sample Allele	Read count for the alleles at the Position Selected in the sample project. If there are more than two alleles, then only the two most frequent alleles are reported.
Log2 Ratio	The Log2 of the ratio of the normalized coverages of the two sample files.
Neighbor Ratios	The Log2 ratios for the current region followed by the Log2 ratios of the neighbor regions.

Setting	Description
Dispersion Hmm	Select this option to include the Dispersion hmm analysis in the report results.
	Note: Neighbor Ratios must also be selected.
Filter settings	
Display Deletion	Selected by default. Show CNVs that are classified as Deletions. Clear this option to hide this classification from the CNV Tool report.
Display Normal	Selected by default. Show regions that are classified as Normal (little evidence of a CNV). Clear this option to hide this classification from the CVN Tool report.
Display Duplication	Selected by default. Show CNVs that are classified as Duplications. Clear this option to hide this classification from the CNV Tool report.
Display Uncalled	Selected by default. Show CNVs that are classified as Deletions. Clear this option to hide this classification from the CNV Tool report.
Log2 Ratio <= [-0.700] or >= [0.700}	Display only those regions where the Log2 of the ratio of the normalized coverages of the two sample files is above or below the set thresholds
Scores >= [3.000]	Show only regions where the Phred-scaled score for at least one potential call (insertion, deletion, or normal) meets or exceeds the set threshold.
Minimum Coverage At Least For One Project >= [30]	Default value is 30. At least one project (sample file) must contain at least the minimum read count in the selected regions, or the CNV calculations are not carried out for the region and the region is not included in the report.
Show regions with low coverage	Include regions that have coverage that fall below the indicated minimum coverage in the report. N/A is displayed for the Log2 Ratio value for these regions.

10. Optionally, click Save Settings to save these settings to a Settings file (.ini file).



You can click Load Settings to select this Settings file at a later date and generate the report according to the saved settings in the file.

11. Click OK.

The CNV Tool report is generated.

Figure 6-181: CNV Tool report example (SNP-Based normalization with smoothing)

CIT CIT	Hipor										kontik
÷2		5] H LE									
Sanp	4.4	delligna -l I	auptigme 8								
Contra	18	Tipecardia, 4	Mpercentie	Renorm	Sper	v kilpersenti	25percentle 0.2192	Stpercentile 0.5502			
(titles	Qv.	Or Det	Chr End	Gene	005	Logifieto	Depth Log Shello High Low Ree	Correctionerson Nerveral Displacement)	Resignation Conservation Conservation	ShiP-Enand Critis	Normalphd Covereg (Semple Corect)
1	chi1	1120071	7520118	CAMTAI		-0.6765	-6 E RUD -0 ANOT	667230.00-0.00	-0.62-0.76-1.01	Deleticin	338442
2	del	14190940	14192702			-7.0942	-10108-00112	200.00-0.00-0.00	-1.01-067-034	Deletion	256,743
8 -	ctv1	15/19590%	15296049	KAZIK+		-1.0038	-1.0708-0.9105	72.25.40.00140.08	-1.01-042-0.95	Delation	547.679
4	del	17545381	17345478	3048.1	8	-0.0391	-0.9165-1.0108	48.240.00-0.00	-6.816.956.95	Deletion	152.538
5	chi1	17149078	17549259	SDHE-	7	-10.0124	40 91 04 -0 81 05	200.00-0.00-0.00	-6 NZ -1 (71 -1 d)	Deletion	575.708
8	det	17152445	17350594	SCH8-	5	-4.0537	-0.9185-0.9189.	200 90-0 00-0 00	105-694-698	Deleton	285.727
1	ch/1	17354219	17354309	SCHE-	5	-0.7918	-1 044E-1 0049	250 00-0 20-0 00	-0.78-0.98-1.09	Delation	221.214
	del.	17386025	17355259	3048-	4.1	-1.0439	-1 0045-1 2049	.750.000.000.00	3 04-6 95-0 97	Deletion	455.952
1.1	chr1	17159593	17359645	SDHE-	8.1	3 (03%	-1 5049-1 2049	200.06-0.06-0.00	101-101-101	Delation	344.690
10	idef	17171231	17371408	RONE -	2	-0.9350	10040-10446	200.000.000.00	-693-699-103	Deletion	797.799
11	dul.	17380-ft8	17380539	SDHB /	1	-1.6544	11.0676-1.0049	200.00-0.00-0.00	107-100-03%	Delation	108.226
12	avl.	20541540	20541400			-1.0775	-1.0676-0.9687	200 00-0 00-0 00	-1.08-0.97-0.14	Deleton	291,614
15	stet	22517848	22587508			-0.9799	-0 9807-0 9807	200.00-0.00-0.00	6.98-1.00.0.08	Deletor	103.607
16-	the	118345189	118346249			-0.1054	-01085-00494	-0.00.200.00-0.00	-011-001.003	Duplication	575.623
15	del	120198159	120198219			-0.0325	00494-012494	-0.03260.00-0.90	003-005016	Duplication	499.510
15	avl	147262416	147262476			-0.0451	-0.0340-0.0340	-0.00.200.000.00	0.05-012.043	Duplication	\$53.672
17	det	152330915	152330975	FLG-AS1		1.3296	0.2754.0.2754	0.00 5 38 0 53	0.31-0.05.050	Duplostor	411.222
11	the	154245175	154245277	HAR .	1	0.2765	0 3074 0 3074	0.0016540.05	0.28.0.03.0.54	Duplication	805.665
19.	del.	154245797	154245885	HAN! .	2	0.5675	0 9643,0 4921	-41 03 -41 03 260 50	0570,16,052	Duplication.	1172(79)
28	crol.	154245887	154245985	HAKI .	2	0.5651	0.5843.0.4921	-6.00-0.09.200.50	057.0.430.47	Duplication	1375.329
21	det	154245987	154246095	HANT +	2	0.4928	0 4921 0 4921	-0.000.03.200.00.	048050.046	Duplication	1251 968
22	del.	154246201	154246299	HAR	3.	11.4576	0.4585.0.4705	0 00.0 00.59 46	0.46.0.54.0.40	Duplication	834607
23	del	154246391	154246462	HAXI +	3	0.4397	0.4585.0.4585	-0.03 0.00 72 25	0 44 0 52 0 40	Dublication	1130.833

NextGene User's Manual

Percentile information for the normal distribution of the Log2 ratios is displayed above the report columns. The *delSigma* value is one standard deviation below the 50th percentile. The delSigma value represents the required value for the Log2 ratio to call a deletion for a given region. The *dupSigma* value is one standard deviation above the 50th percentile. The dupSigma value represents the required value for the Log2 ratio to call a duplication for a given region. The other percentile values represent the required values for the Log2 ratio to call a duplication for a given region. The other percentile values represent the required values for the Log2 ratios to place a region in the indicated percentile. For example, 32percentile: -0.0529 means that the Log2 ratio for a given region must equal -0.0529 for the region to be placed in the 32nd percentile of all regions.

The CNV Tool report is interactive:

- To view the region of the genomic database in the Database of Genomic Variants (DGV) for which the call was made, click the call type in the Indel Calls column.
- To load different projects and/or change the project settings, on the report menu, click File > Load Projects, or on the report toolbar, click the Load Projects icon the CNV Tool window, and make the appropriate changes.
- To modify the report settings, on the report menu, click Settings > Settings, or on the report toolbar, click the Settings icon , to open the CNV Report Settings dialog box and modify the report settings as needed. The report display is dynamically updated after you save the modifications.
- To save the report to a text file, on the report toolbar, on the report menu, click File > Save Report, or on the report toolbar, click the Save Report icon . A default name and location are provided for the file, but you can change both of these values.
- To generate the Gene CNV report, on the report toolbar, click the Gene CNV report icon
 See "Gene CNV report" below.
- To generate the Block CNV report, on the report toolbar, click the Block CNV report icon
 ▶ E. See "Block CNV report" on page 343.
- To generate the graphical display of the data, on the report toolbar, click the CNV Graphs icon 🔜 . See "CNV Graphs" on page 346.

Gene CNV report

The Gene CNV report groups together consecutive regions that have a CNV into a single report line. Consecutive regions can be grouped up to a single gene. Regions are not grouped across multiple genes. You can use the Gene CNV Report to focus on consecutive regions that show evidence of a CNV. In general, individual regions are not included in the report, unless their weighted ratios exceed the threshold that is defined. Smaller regions where the number of consecutive regions is less than the threshold that is specified for the Show Gene Exon Number setting can be included in the report based on their weighted ratios according to the following:

Weighted Log2 Ratio = Log2 Ratio * NCR/Show Gene Exon Number

where NCR = Number of Consecutive Regions and Gene Exon Number is a filter setting for the report. See Figure 6-182 on page 341.

Figure 6-182: Gene CNV report example

Gene	CIVV Report									6	
28	Niz										
Sampl	PGDX144	delSigma	dupSigme								
Cantra	PGDX144	10percent	25percent	32percentile: -0	50percen	68percentle:	75percentile: 0.2954	90percentile: (
Index	Chr	Chr Start	Chr End	Gene	CDS	Log2Ratio	Smooth Log2Ratio(High Low Resolution)	Score(Delete SNP Based Calls	Original Coverage (Sample:Control)	Normalized Cove (Sample Control)	
1	chrl	69091	70008	ORIAFS: +	1	0.4492	0.4510;0.4510	-0.00,-0.00,200 Duplication	1226:1131	1226;898	
2	chr)	2985824	3350375	PROMIS -	1,23,45,6	0.4733	0.2705.0.2705	-0.00(0.27,12.1) Duplication	261,237	261,188	
3	chir1	3379649	3397151	ARHGEF16, =	1,2,3,4,5,6	0.6110	0.0294;0.5795	-0.00.0 17.14 81 Emplication	168,139	168.110	
4	chr1	3407092	3527832	MEGF6	1.2.3.45.6	0.5097	0 6653 0 5097	0.00.0.95.7.07 Ovplication	168:149	168:118	
5	chr)	3541637	3545167	TPRGIL .	1.2.3.45	0.3656	-0.2763.0.5343	-0.00 5 98 1 30 Duplication	201/197	201:156	
6	chrl	3547539	2566563	WRAP73 -	1.23,45.6	0.4298	0.3430.0.5343	-0.00,0.54,9.14 Duplication	295:276	295:218	
7	chr1	3598930	1649643	TP73	1.2.3.4.5.6	0.6366	1.1224.0.5342	-0.00.0.06.18.5 Duplication	185:150	185:119	
8	chr1	36690.46	3688087	CCDC27: *	1.2.3.4.5.6	0.5119	0.4941.0.6036	-0.00(0.00:30.6- Duplication	385:340	385:270	
9	chr1	6111597	6150634	KCNAB2: .	1.2.3,4.5,6	-0.0909	-0.99090.0475	44.71:0.00:-0.01 Delation	103,241	103;191	
10	chrl	6166340	6240083	CHOS:-	1.23.45.6	-0.8031	-1 -4330:-0 8466	69 24 0 00-0 0 Deletion	195:431	196;342	
11	che1	6246732	6259533	RPL22 -	1,23,4	-0.4431	-0.8643-0.9554	0.07.18.16.0.00 Deletion	89,152	89,121	
12	chr1	6266596	6279467	RNF207, -	1.2.3.45.6	7,1390	-1.0616-1.0459	200.00;-0.00;-0 Election	89,247	89.196	
13	chr1	6285140	6295971	ICMT -	123.45	0.8949	-1.0459-0.8643	55.43.0.00 -0.8/ Deletion	121 284	121/225	
14	chr)	6304426	6305567	HESE .	1.2.3	-0.2692	-0.5396-0.9236	0.02/21 28:0.01 Deletion	39.59	39,47	
15	chirl.	6309398	6314965	GPR153 -	1,2,3,45	-0.5683	-1 5374-0 9349	0.757.99.0.00 Deletion	58 108	58.86	
15	chr1	6324657	6453459	ACOT7:-	1.2.3.4.5.6	-0.6845	-0.9236;-0.9349	3.70.2.42.0.00 Deletion	56.113	56.90	

The Gene CNV report is interactive:

- To modify the report settings, on the report menu, click Settings > Settings, or on the report toolbar, click the Settings icon 🔀 to open the Gene CNV Report Settings dialog box and modify the report settings as needed. The report display is dynamically updated after you save the modifications.
 - For the Filter settings, specify the thresholds for the regions that are to be included in the report.
 - For the Display settings, select the columns that are to be included in the report, or clear the options for the columns that are not to be included.

Figure 6-183: Gene CNV Report Settings dialog box

Display				
V Index	Description	🔽 Log2 Ratio		
Chr	Contig	V Neighbor Ratios		
Name	Locus Tag			
Number	Start			
Chr Position Start	End			
Chr Position End	Length			
📝 Gene	V Original Coverage			
CDS	V Normalized Coverage			
RNA Accession	Position Selected			
Protein Accession	Sample Allele			
Filter	00 or>= 0.700			
Scores>= 3.00				
		>= 5.000000		
Show Regions with Lo		()= 0.000000		
📝 Show Gene Exon Nur	nber>= 1			

Setting	Description
Display settings	
Index	An ordered count of the segments that are used in the report.
Chr	
Name	• The name of the chromosome that the segment is on.
Number	The number of the chromosome that the segment is on.
Chr Position Start	The base number that indicates where the segment starts in the chromosome.
Chr Position End	The ending base number that indicates where the segment ends in the chromosome.
Gene	The gene name for the segment when the segment is the whole gene or the name of the gene on which the segment is found.
CDS	The coding sequence number for the segment.
RNA Accession	Show the RNA accession for the gene from NCBI.
Protein Accession	Show the protein accession for the gene from NCBI.
Description	Available if the reference file is a .fasta file with multiple segments. Select this option to display the title line for each segment in the Description column.
Contig	The contig that the segment is on. The contig is based on the genome assembly from the NCBI.
Locus Tag	An alternate way to identify the gene.
Start	The starting location for the reference region.
End	The ending location for the reference region.
Length	The total length of the reference region, which provides for easy identification of expressed regions by size (such as when locating small RNA transcripts).
Original Coverage	The actual median coverage for the region in each sample.
Normalized Coverage	The median coverage following global normalization for the region in each sample.
Position Selected	The median coverage position for the region. This position is used for the calculation of the Log2 Ratio.
Control Allele	Read count for the alleles at the Position Selected in the control project. If there are more than two alleles, then only the two most frequent alleles are reported.
Sample Allele	Read count for the alleles at the Position Selected in the sample project. If there are more than two alleles, then only the two most frequent alleles are reported.
Log2 Ratio	The Log2 of the ratio of the normalized coverages of the two sample files.
Neighbor Ratios	The Log2 ratios for the current region followed by the Log2 ratios of the neighbor regions.

Setting	Description
Filter settings	
Log2 Ratio <= [-0.700] or >= [0.700}	Display only those regions where the Log2 of the ratio of the normalized coverages of the two sample files is above or below the set thresholds. The Log2 ratio for each of the consecutive regions must fall above or below the indicated thresholds.
Scores >= [3.000]	Show only regions where the Phred-scaled score for at least one potential call (insertion, deletion, or normal) meets or exceeds the set threshold. The score for each of the consecutive regions must exceed the indicated threshold.
Show Regions with Low Coverage	Select this option to include the regions that do not meet the minimum coverage threshold in the report.
Minimum Coverage >= [5]	Include regions that meet or exceed the indicated coverage level in the report.
Show Gene Exon Number >= [1]	The minimum number of consecutive regions where the Log2 ratios exceed the defined thresholds for the regions to be included in the report.

- To save the report to a text file, on the report menu, click File > Save Report, or on the report toolbar, click the Save Report icon . A default name and location are provided for the file, but you can change both of these values.
- To generate the Block CNV report, on the report toolbar, click the Block CNV report icon
 See "Block CNV report" below.
- To generate a graphical display of the data, on the report toolbar, click the CNV Graphs icon 😹 . See "CNV Graphs" on page 346.

Block CNV report

The Block CNV report groups together consecutive regions that have a CNV into a single report line. Multiple genes can be included in the same block. You can use the Block CNV Report to focus on consecutive regions that show evidence of a CNV.

Figure 6-184: Block CNV report example

Block	CNV Report										- 0	*
20												1
Sampl	PGDX144T_	delSigma -	dupSigme (1
Contro	PGDX144N	10percentile	25percentile	32percentile -0.1488	50percentile: 0.0000	68percontile: 0.1959	75percentile: 0	90percentile 0.6048				
Index	Chr	Chr Start	Chr Erid	Gene	Number of Regions	Log2Flatio(Median SidDev)	Smooth Log2P	Median Score(Deleb	SNP-Based C	Onginal Coverage (Sample,Control)	Normalized Coverage (Sample:Control)	6
1	chr1	69091	70000	OR4F5	1	0.4510;0.000	0.4510.0.4510	-0.00;-0.00.72.25	Deplication	1227:1131	1227.698	
2	che1	3160651	3348704	FRDM16	14	0.6189;0.137	0.5977;0.4692	0.00,6 32:1.16	Duplication	49:41	49:33	
3	ctir1	3385997	5923465	ARHGEF16, NPHP4	136	0.4939(0.273	0,4512,0.4933	0.00.10.00.0.42	Duplication	42.39	42/31	
4	chr1	5923950	6267571	NPHP4, PNF207	90	-0.8611,0.275	0 8809, 0 8794	1 29,5 86,0 00	Deletion	17,38	17,30	
5	chr1	6269474	9673141	FINE207 THEM201	311	2 2515:1.427	2 8554 2 7714	10 55 0 40 0 00	Detetion	9,50	9:40	
6	chr1	11076901	17275019	TARDER CROCC	0.00	0.4283;0.189	0.4028.0.3990	0 10 8 68 0.62	Duplication	72.68	7254	
7	chrl	17285070	23760952	CROCC ASAP3	921	0 4659 0 207	0.4384.0.4384	000881.081	Duplication	60,54	60:43	
8	chr1	23763623	27684367	ASAP3, MAP3K6	595	0.4183.0.172	0.3846.0.3940	0.00.9.69.0.46	Duplication	64,62	64,49	
9	chr1	27586349	29041285	MAP3K6; GMEB1	196	0.4497:0.156	0.4129.0.4048	0.00.9.25:0.54	Duplication	70.58	70:46	
10	chr1	29185466	31210546	OPRD1_LAPTM5	80.	0.4519;0.157	0.4422.0.3844	0.00.8.81,0.61	Duplication	67:63	07:50	
31	chrl	31230506	32193881	LAPTM5: BAI2	162	0.5332;0.189	0.4868,0.4816	0.00,719,092	Duplication	61,55	61:44	
12	chel	32201181	36643802	BAI2: MAP7D1	605	0.4330;0.178	0 4042 0 4029	0 00 8 81;0 60	Duplication	70:67	70.53	

The Block CNV report is interactive:

• To view the region of the genomic database in the Database of Genomic Variants (DGV) for which the call was made, click the call type in the Indel Calls column.

- To save the report to a text file, on the report menu, click File > Save Report, or on the report toolbar, click the Save Report icon . A default name and location are provided for the file, but you can change both of these values.
- To modify the report settings, on the report toolbar, on the report menu, click Settings > Settings, or on the report toolbar, click the Settings icon not be Block CNV Report Settings dialog box. The dialog box has two tabs—Advanced Settings and Report Settings. The Report Settings tab is the open tab. Modify the report settings on either tab or both tabs as needed. The report display is dynamically updated after you save the modifications.

Figure 6-185: Block CNV Report Settings dialog box, Report Settings tab

Ivanced Settings	Report Settings					
Display						
Index		Locus Tag		V Neig	hbor F	atios
Na	me mber	End		🔲 Disp	ersion	нмм
Chr Positic		V Length				
Chr Positic	n End	👿 Original Coverage				
V Gene		Position Selected				
V Number of	Regions	V Normalized Coverage				
RNA Acce		Control Allele				
Protein Ac	cession	Sample Allele				
V Description	1	V Log2Ratio				
Contig						
Filter						
V Display Del	etion	Log2 Ratio <=	0.700	0	(>=	0,700
Display Nor	mal	Scores >=	3.000			
🔽 Display Dup	olication	Minimum Coverage	Át Least F	or One F	roject	> 5.00
🔽 Display Un	called	Show regions wi	th low cov	erage.		

Setting	Description
Report Settings - Display Settings	
Index	An ordered count of the segments that are used in the report.
Chr • Name • Number	 The name of the chromosome on which the segment is located. The number of the chromosome on which the segment is located.
Chr Position Start	The base number that indicates where the segment starts in the chromosome.
Chr Position End	The ending base number that indicates where the segment ends in the chromosome.

Setting	Description
Gene	The gene name for the segment when the segment is the whole gene or the name of the gene on which the segment is found.
Number of Regions	The number of consecutive regions that have a CNV and that were grouped together as a result.
RNA Accession	Available only for the CNV report.
Protein Accession	Available only for the CNV report.
Description	Available if the reference file is a .fasta file with multiple segments. Select this option to display the title line for each segment in the Description column.
Contig	The contig on which the segment is located. The contig is based on the genome assembly from the NCBI.
Locus Tag	Available only for the CNV report.
Start	The starting location for the reference region.
End	The ending location for the reference region.
Length	The total length of the reference region, which provides for easy identification of expressed regions by size (such as when locating small RNA transcripts).
Original Coverage	The actual median coverage for the segment.
Position Selected	Available only for the CNV report.
Normalized Coverage	The median coverage following global normalization for the segment.
Control Allele	Available only for the CNV report.
Sample Allele	Available only for the CNV report.
Log2 Ratio	The Log2 of the ratio of the normalized coverages of the two sample files.
Neighbor Ratios	The Log2 ratios for the current region followed by the Log2 ratios of the neighbor regions.
Dispersion Hmm	Select this option to include the Dispersion hmm analysis in the report results.
	Note: Neighbor Ratios must also be selected.
Report Settings - Filter Settings	
Display Deletion	Selected by default. Show CNVs that are classified as Deletions. Clear this option to hide this classification from the CNV Tool report.
Display Normal	Selected by default. Show regions that are classified as Normal (little evidence of a CNV). Clear this option to hide this classification from the CVN Tool report.
Display Duplication	Selected by default. Show CNVs that are classified as Duplications. Clear this option to hide this classification from the CNV Tool report.


Chapter 6 Sequence Alignment Tool

Setting	Description
Display Uncalled	Selected by default. Show CNVs that are classified as Uncalled. Clear this option to hide this classification from the CNV Tool report.
Log2 Ratio <= [-0.700] or >= [0.700}	Display only those regions where the Log2 of the ratio of the normalized coverages of the two sample files is above or below the set thresholds.
Scores >= [3.000]	Show only regions where the Phred-scaled score for at least one potential call (duplication, deletion, or normal) meets or exceeds the set threshold.
Minimum Coverage At Least For One Project >= [5]	At least one project (sample file) must contain at least the minimum read count in the selected regions, or the CNV calculations are not carried out for the region and the region is not included in the report.
Show Regions with Low Coverage	Include regions that have coverage that fall below the indicated minimum coverage in the report. N/A is displayed for the Log2 Ratio value for these regions.
Advanced Settings	
Ignore up to [0] regions when merging	If there are "n" number of regions that are reported as normal within a larger number of regions that show the same CNV, then these normal regions are ignored and the regions with the same CNV are merged to create blocks. Note: Uncalled regions are automatically ignored.

CNV Graphs

To generate a graphical display of the data, on the CNV report toolbar, click the CNV Graphs icon \bowtie .

Figure 6-186: CNV graphs (SNP-Based Normalization with Smoothing)



- Log2Ratio graph (Top graph)—The Log2Ratio graph is based on the coverage ratios for the CNV regions. Insertions are displayed in green. Deletions are displayed in red. Normal regions, or regions where the data was insufficient for making a call, are displayed in gray. SNP Regions (regions of interest for the purpose of checking allele ratios to visualize copy number) as designated in the region of interest BED file are displayed in blue. The horizontal red and green lines represent the coverage ratios for insertions and deletions, respectively. The differently colored solid lines that are displayed below the Log2Ratio graph indicate the consecutive regions summarized for each call.
- Allele Ratio graph (Bottom graph)—The Allele Ratio graph is based on the allele frequency ratios for the CNV regions. By default, when the graph first opens, it displays all the allele frequency ratios across all the chromosomes in the project.



The SNP-based Normalization with Smoothing algorithm evaluates SNPs that overall are heterozygous with allele frequency ratios that range from approximately 50-50 to 40-60. The typical ratio for a normal region (no CNV) falls within this 40-60 range. The Allele Ratio graph helps to visualize the samples that fall outside this typical range, and therefore identify a potential CNV.

The graphs are interactive:

- For the Log2Ratio graph, you can click:
 - Toggle Resolution to toggle the display through Low Resolution, High Resolution, and if applicable, Custom Resolution.
 - Toggle Ratio to toggle the Y axis between Log2Ratio and Sample Fraction.
 - Toggle SNP Regions to toggle the display of specific Regions of Interest for the purpose of checking allele ratios to visualize copy number as defined by the user in a BED file.
- For the Allele Frequency graph, you can:
 - Click Toggle Sample/Control to toggle the display between showing the following:
 - Allele frequencies for only the sample (solid blue dots).
 - Both the sample and the control sample (open blue dots).
 - Only the control sample.
 - Click the Next Chromosome and Previous Chromosome buttons to move the display through the allele frequency ratio for each individual chromosome in the project.
- For both graphs, the following functions are available:
 - Zoom In Hold down the left mouse button and draw a box from the upper left hand corner of any region in a graph towards the lower right hand corner. A box is formed around the area that being reduced for viewing.

• Zoom Out - Hold down the left mouse button and draw a box from the lower right hand corner of any region in the graph towards the upper left hand corner.



The magnification for zooming out is always 100%.

• Saving the graph to a file - Right-click any graph, and then select Save Picture to save the graph as PNG file. You must name the graph and select a location in which to save the graph.

Batch CNV Tool

You use the Batch CNV Tool to load multiple sequence alignment projects that have been aligned to the same reference and compare the projects to each other for coverage levels in the ROIs.



For detailed information about the Batch CNV Tool, including its advantages and how the tool calculates pileup coverage at each position in the targeted panel, see the NextGENe application note "BatchCNVAppNote" at http://softgenetics.com/appnotes.php.

To use the Batch CNV tool

1. On the Comparisons menu, select Batch CNV Tool.

The Batch CNV Tool dialog box opens.

Figure 6-187: Batch CNV tool dialog box

C:\Data\Demo\	BatchCNVAlig	nments\PID00	001_Output	PID0001	1D0001
C \Data\Demo\U C \Data\Demo\U	BatchCNV\Alig	nments\PID00	003 Output	VPID 0003VF	1D0003
C:\Data\Demo\U C:\Data\Demo\U	BatchCNVAlig	nment:\PIDD0	005_Dutput	\PID 0005\F	1D0005 p
C \Data\Demo\U C \Data\Demo\U	BatchONV\Alig	nments\PID00	07_Output	\PID0007\F	1D0007.
C:\Data\Demo\U C:\Data\Demo\U	BatchCNVVAlig	nments\PID00	009 Output	\PID0009\F	1D0003.p
C \Data\Demo\l C \Data\Demo\l	BatchCNV\Alig	nments\PID00	011 Output	VPID 0011VF	1D0011
C:\Data\Demo\I	BatchENVVAlig	nments\PID00	012_Output	PID0012\F	1D0012
Ba	itch Add	Add		Bemove	
nput Region of Intere	st (*.bed)				
					Se
Report Region of Inter					100
	rest in type				

- 2. Do one of the following:
 - To select the *folder* that contains all the sequence alignment projects (*.pjt) that are to be compared, click Batch Add, and then browse to and select the folder.



You can select a top-level folder in a directory, and NextGENe scans not only the top-level folder for *.pjt files, but also all the associated sub-folders.

- To add one sequence alignment *project* (*.pjt) at a time, click Add, and then browse and select a project. Repeat this step as needed to select all the required projects.
- 3. Click Set, and then browse to and select the BED file that is to be used to define the regions for the projects.
- 4. Optionally, to limit the report results do the following:
 - a. Create a text file that lists the descriptions for selected regions of this file. (Each description must be its own line entry.)
 - b. Click Set, and then browse so and select this text file.

Although all calculations are carried out on the whole BED file, only those regions of the uploaded BED file that have descriptions that match those contained in the text file are included in the Batch CNV report.

5. Click OK.

The Batch CNV report is generated. Each report column represents a different sequence alignment project, and each report row represents a different region in the BED file. The default range for the average normalized coverage is 0.8 to 1.2. The closer that the normalized average coverage is to one for a given project/region combination, the greater the likelihood that the region does not contain a CNV relative to all the other projects that were loaded. The region names are taken from the 4th column of the BED file that used to define the regions for the projects.

Figure 6-188: Batch CNV report

		ACC SALES																13
- 12	12																	
rite	Ox.	Ov Stat	OvEnd	Demosphion	516.09	521 pt	5318	Disci	\$14,58	523cH	Stat	512.04	87.04	\$10.19	55.p#	1807	\$24.04	\$624
	sile3	12047206	12049420	MR82_NM_014874.3_idi_1	1.007	1,016	1.014	0.900	1.046	0.953	0.994	0.972	1.006	0.071	1.066	1.036	1,004	0,944
	det	12052592	12052767	MPH2_NM_014874.3_cds_3	0.530	1 030	1.977	1 (257	1100	0.913	1 037	0.901	0.963	1.076	0.540	1 (23)	1.979	0.914
1.1	ant	12056193	12095-295	MFN2_NM_014874 3_odt_3	0.822	1.002	0.905	1.047	0.873	1108	0.941	11.930	1.036	7.054	1.090	0 979	D 968	0.851
	iteta	12057334	12057436	HITN2_NH_014674.3_ods_4	1.621	0.990	0.970	0.979	0.958	0.568	0.540	1.093	1.006	0.815	6.927	1,038	1.000	1.083
	det .	12058807	12058995	HEN2_NM_014874.3_ods_5	0.967	1.064	0.984	1.012	0.967	0.5%	0.916	1.030	1.021	1.673	3.027	1.015	0.617	1.001
	dV1	12059025	12059172	MEN2_NM_014874.3_645_6	0.937	0.977	1.030	1.032	6963	8.955	0.902	1.029	1.016	1.675	0.986	1.007	0.977	1 027
	dvi	72061430	12061631	MTN2_NH_014674.3_cdl_7	0.989	0.965	1.049	0.979	6.919	1123	0.966	1 034	0.964	0.964	1.004	1.025	0.977	1,033
1.1	del .	12061006	12061917	MFN2_NM_014074.3_ods_0	0.967	1.032	1.042	1.021	0.947	1.069	0.963	1.005	1.041	0.942	1.070	1.102	0.979	1.100
	dif	12062019	12062180	MERIZ_NM_014874.3_cds_9	0.333	1 065	1.013	0.944	1.005	1.076	1.017	1.003	1.046	1.036	1.040	0.972	0.995	1.055
6	dist.	12054029	12064195	MFR2_NM_014874.3_bdr_10	0.994	0.994	11.930	1.001	1.046	1.057	0.952	0.989	1.064	0.915	0.950	1.002	1.010	1.027
t	dit	1256545	12954690	MPR2_NM_014874.2_edi_11	1.625	0.968	1.020	0.971	0.920	8.983	0.527	105	1.032	0.959	1112	0.979	1 (15	0.958
2	intel	12064867	12065008	MFN2_NH_014874.3_ods_12	1.049	1 630	1 034	0.970	6.958	0.987	0.9950	0.929	0.377	0.961	1.055	1 032	0.997	0.975
1	ctv1	12065740	1,2066008	MFN2_NM_014874.3_eds_13	1.037	0.960	0.953	0.986	0.986	0.982	1.024	1.045	1.001	1.015	1.013	0.992	0.945	1.028
4	div1	12096575	12066770	MFH2_NM_014074 3_cdi_14	0.653	1.071	1.054	1 067	0.065	1 671	0.915	0.989	1 7275	0.938	1.022	1.003	0.954	1.023
5	avi	12067(90	12067326	MPN2_NM_014874.1_cdi_15	0.963	0.967	1.043	1 026	6.936	1.018	0.982	1.015	1 642	1.065	1.048	1.040	0.931	1.030
6	ont	12059629	12065000	MTN2_NM_014874 3_cds_16	0.962	1.002	1.034	1.074	0.071	1.067	0.950	0.929	0.999	1.068	1.023	1 029	0.900	1.025
7	del	12071533	12071642	HEN2 NM 014874 3 cdi_17	0.977	1.030	0.691	1.025	0.917	0.992	0.925	1.058	0.997	6.990	1.065	0.529	1.047	1.079
	din.	15(0)4(0)	156005005	LMIGA_NM_170707.3_6dt_1	0.960	1.014	1.007	1.049	1.012	1.624	0.969	0.999	0.954	1,019	1.019	1.041	0.973	0.971
5	diff.	156100338	156100534	LMNA_MM_170707.3_cdt_2	0.996	0.929	1 079	0.946	6 973	E1983	1.062	0.966	1.022	1.124	1.639	0.966	1.039	0.945
9	CNT	156104174	156104339	LMINA_NM_170707.3_cds_3	1.820	0.982	1.068	0.325	1.017	51.974	0.837	1 036	0.962	1.008	1125	1.021	0.969	0.353
1	stat	196104575	156104786	LMMA_NH_170707.3_cal_4	1.014	0.894	1.035	1.041	10 1956	0.913	0.949	1.039	1.000	1.064	1.064	0.937	1.076	0.975
	det	158104958	156105123	LMNA_MH_170707.3_cdr_5	1.636	0.975	1.014	1 (05	13 961	1 (63)	0.956	1.047	0.586	1.082	0.927	1.040	0.991	1.032
1	avi	1551(0672	155102832	LMNA_NM_170707 1_01(B	11 997	1.085	1.042	0.196	0.873	8.971	0 960	0.992	100.1	0.954	1 001	1.051	1/011	0.955
2	1.4	antitudes			4.444	1.000	- 101	a date.	a ske		-	1.000	4 (10)	+ +++	1.140	10.044	Alterat	+ 2004


The Batch CNV report is interactive:

- To load different projects and/or BED file, on the report toolbar, click the Load Projects icon
 icon icon to open the Batch CNV Tool dialog box, and make the appropriate changes.
- To save the report to a text file, on the report toolbar, click the Save Report icon **I**. A default name and location are provided for the file, but you can change both of these values.
- To generate a graphical display of the data, on the report toolbar, click the Batch CNV Graphs icon z . See "Batch CNV graphs" below.

Batch CNV graphs

To generate a graphical display of the Batch CNV data, on the Batch CNV report toolbar, click the Batch CNV Graphs icon \swarrow . The Batch CNV Viewer opens. Three Batch CNV graphs are displayed in the viewer. These graphical displays provide the visualization of the sub-region results for the determination of potential copy number variations. By default, when the viewer first opens, a *Shading* option, which indicates the range of normalized ratios for a given region, is set to 0-100%.





From top to bottom, the following Batch CNV graphs are displayed:

• Global Batch CNV graph – The Global Batch CNV graph displays the global coverage for all the loaded sequence alignment projects. Each report column represents a different project, and each report row represents a different region in the BED file. The default range for the average normalized coverage is 0.8 to 1.2, but you can modify this value as

appropriate. The closer that the average normalized coverage is to one for a given project/ region combination, the greater the likelihood that the region does not contain a CNV relative to all the other projects that were loaded. The region names are taken from the 4th column of the BED file that used to define the regions for the projects. Any region that has an average normalized coverage value that falls outside the default range is highlighted, where red indicates an average normalized coverage that falls below the minimum coverage threshold (default value = 0.8) and therefore, a possible deletion, and green indicates an average normalized coverage that exceeds the maximum coverage threshold (default value = 1.2), and therefore, a possible duplication.

- Sample-Specific Batch CNV graph The Sample-Specific Batch CNV graph displays expands the display that is shown in the Global Batch CNV graph to show the average normalized coverage across all the regions just for the selected sample. Because this graph is simply an expanded view of the coverage for a project (a row) in the Global Batch CNV report, there is direct correlation in the display of the coverage levels - the same regions that were highlighted in red in the Global Batch CNV graph are highlighted in red in the Sample-Specific Batch CNV graph, and the same regions that were highlighted in green in the Global Batch CNV graph are highlighted in green in the Global Batch CNV graph are highlighted in green in the Sample-Specific Batch CNV graph.
- Region-Specific Batch CNV graph The Region-Specific Batch CNV graph expands the display that is shown in both the Global Batch CNV graph and the Sample-Specific Batch CNV graph to show the normalized coverage for every nucleotide within the selected region.

The Batch CNV graphs are interactive:

• You can hold your mouse pointer over any position in the Global Batch CNV graph to open a tooltip that displays the following information about the position: the Project/ Sample ID, the locus, and the average normalized coverage for the position.

Figure 6-190: Tooltip for a position in the Global Batch CNV graph



- You click on any point in the Global Batch CNV graph to dynamically update the Sample-Specific CNV graph.
- You can click on any point (a region) in the Global Batch CNV graph or the Sample-Specific Batch CNV graph to dynamically update the Region-Specific Batch CNV graph.
- You can adjust the range for the Shading to exclude noise, for example, 25-75% and ensure better reliability of the calls. If a call falls outside the Shading range after you adjust it, then the call is a reliable call. If the call remains within the Shading range after you adjust it, then the call is more than likely a false positive or noise.

Chapter 7 Specialized Applications

Typically, if you are aligning your data files against a small genome (one that is less than or equal to 250 Mbp), then you align data against a reference file that is either in .fasta format or GenBank format. If you are aligning the data against a large genome (one that is greater than 250 Mbp, such as the whole human genome), then you align the data against a preloaded reference that SoftGenetics supplies or a custom preloaded reference that was built using the NextGENe Build Preloaded Reference tool. For special data application types, however, such as ChIP-Seq or small RNA analysis, after you align your files to a reference genome, you might then need to align your data files against a reference sequence that you create using NextGENe's Peak Identification tool.



For detailed information about the NextGENe Build Preloaded Reference Tool, see the Reference & Track Manager Tool User's Manual or Online Help

This chapter covers the following topics:

• "Creating a Reference File with the Peak Identification tool" on page 355.

Chapter 7 Specialized Applications

Creating a Reference File with the Peak Identification tool

In addition to using the Peak Identification tool to identify a list of regions that satisfy the coverage level requirements to be identified as a peak, you can use the Peak Identification tool to save these regions of the genome as a reference file and use them as a reference sequence.

Figure 7-1:	Peak Identification Settings dialog box	
	ean raenanean een ge anareg seen	

Peak Identification Settings
Peak Identification:
✓ Automatically
☐ Manual
Coverage >= 10
Gap < 0 bps
Set Baseline of Noise
<u> </u>

Manual Setting	Description
Coverage	The coverage threshold for a position to be considered part of a peak.
	Note: Although you can set the coverage level to any value, for ChIP-Seq or miRNA analysis, SoftGenetics recommends a value that is equal to twice the average coverage that is reported in statinfo.txt file.
Gap	Maximum number of bases between regions that meet the coverage threshold to be considered one continuous peak.
Set Baseline Noise	Used in conjunction with the Gap size to determine whether two nearby regions each with a coverage that is above the Coverage threshold are to be merged into one peak, or whether they are to remain as two separate peaks.
	 If the regions are separated by a distance that is less than the Gap size and the coverage in this region exceeds the Set Baseline Noise, then the two nearby regions are merged into a single peak.
	 If the regions are separated by a distance that is less than the Gap size but the coverage in this region does not exceed the Set Baseline Noise, then the two nearby regions remain separated.

When you use the Peak Identification tool, the Peak Identification report contains information about all regions of the reference that meet the coverage requirements.

Figure 7-2: Peak Identification report example, transcript determination


	副 父										
Index	Chr	Reference Region	Chromosome Region	Length	Coverage(75	Transcript site	Gene Distance	Sequence			
1	1	14395211440135	142730673.142731287	615	4	1439778.,1439877	None	CAAGGTGGCACAAGAA			
2	1	1507624.,1507918	142798776142799070	295	4	1507721.1507820	None	AGATGGTTTCATATTG			
3	1	19603061961106	176081176881	801	6	1960646.,1960765	None	TCTCGGAGCCGGAGTT			
4	1	3374241.,3375330	3119293731194026	1090	10	3374704.,3374866	PUM1(+117125)	GATATATAGAAAGAGA			
5	1	34439023445455	3126259831264151	1554	8	34445623444794	PUM1(+47000)	TATTGGAAAAAACAAA			
6	1	34706623470736	3128935831289432	75	5	34706623470736	PUM1(+21719)	TATACATTACAAATTTA			
7	4	2000010 2000000	21E04712 21E04704	70	0	2000010 2000000	Mana	TTTCTCTTTTTACTAC			

J.

For detailed information about the columns that are displayed in the Peak Identification report, see "Peak Identification report" on page 286.

After peak identification, the results of the alignment project are displayed in the NextGENe Viewer. Brown lines indicate the regions that meet the requirements to be considered a peak.

Figure 7-3: Example of sequence alignment results for transcript determination



To save the report to a .fasta file, click the Save Report icon **I** on the report toolbar. A default name and location are provided for the file, but you can change both of these values.

To align sample files to peak identification reference file

To align sample files to the peak identification reference file, you use the same general procedure as when you are aligning sample files to the whole genome reference with one notable exception—you must use the .fasta file created from the Peak Identification report, which contains only the peak regions, as the reference file. After NextGENe completes the alignment of the sample files to the peak identification reference file, the results are shown in the NextGENe Viewer, which provides a graphic representation of expression levels for each region. Red lines indicate region boundaries. Sequence reads that align with each region are shown beneath where they align. Gray bars indicate coverage (expression level).



You can generate an Expression report to report on the coverage levels for each peak. See "Expression Report" on page 130.

Figure 7-4: Example of small RNA reads aligned to peak identification reference file

Chapter 7 Specialized Applications

Chapter 8 NextGENe Tools

NextGENe provides many tools for optimizing input data and exporting and analyzing results. These include tools that you use to modify the structure of sample files and reference files, tools that you use to use to calculate information about sample files, and tools that you use to preview files.

This chapter covers the following topics:

- "The NextGENe Barcode Sorting Tool" on page 361.
- "The NextGENe Sequence Operation Tool" on page 366.
- "The NextGENe Reads Simulator Tool" on page 377.
- "The NextGENe Pseudo Paired Read Constructor Tool" on page 379.
- "The NextGENe Condensation Results Filter Tool" on page 381.
- "The NextGENe Condensation Results Tool" on page 383.
- "The NextGENe GC Percentage Calculation Tool" on page 385.
- "The NextGENe Overlap Merger Tool" on page 386.
- "The NextGENe Long PE Assembly Mapping Tool" on page 389.
- "The NextGENe File Preview Tool" on page 390.



The NextGENe Format Conversion tool is discussed in Chapter 3, "File Format and Conversion," on page 85. The NextGENe AutoRun tool is discussed in Chapter 9, "The NextGENe AutoRun Tool," on page 391. Chapter 8 NextGENe Tools

The NextGENe Barcode Sorting Tool

If your data files contain barcodes (also referred to as *multiplexed data*), you must use the NextGENe Barcode Sorting tool to parse the barcoded read data into separate files prior to analysis. NextGENe's Barcode Sorting tool parses the barcoded sample files into separate files according to sequence tags. You can use the Barcode Sorting tool for data files in which the barcodes are included within the sequence reads, the barcodes are included in the read names or the barcodes are contained in a separate file. Two options are available for trimming the tags from the reads and parsing the reads according to the tags:

- If all the barcode details are known (barcode sequence tags and the sample ID that they represent), you can create a Barcode/Primer file, which is a tab delimited text file, to provide information to the NextGENe Barcode Sorting tool about the sample IDs, the forward barcode/primer tags, and the reverse barcode/primer tags.
- If some or all the barcode details are not known, you can use the NextGENe Barcode Sorting tool to automatically detect the barcode sequence tags and total tag count and then create separate folders for each tag.

Barcode/Primer File

You can use a program such as Microsoft Excel to create a Barcode Primer File and save the file as a tab-delimited text file. Each line in the file must include the sample ID and an entry for each barcode tag in the sample. Figure 8-1 is a sample Barcode/Primer file with just two tags for each sample. Each line in the file includes the sample ID (Sample_ID), the forward barcode tag (Forward Tag) and the reverse barcode tag (Reverse Tag).

Figure 8-1: Example of a Barcode/Primer file with two tags



If reverse tags are not used, you can leave the Reverse Tag column blank.

Figure 8-2 below is a sample of a Barcode/Primer file with multiple tags for each sample.

Figure 8-2: Example of a Barcode/Primer file with multiple tags

Sample ID	Tag 1	Tag 2	Tag 3	Tag 4
Samp12345	CCGTGAACGT	CCGTTAACGT	CCGTGACCCT	CCGTTAACTG
Samp23456	CCGTGACCGT	CCGTTACCGT	CCGTGATGAC	CCGTGAGTAC

Chapter 8 NextGENe Tools

To parse barcoded sample files

1. On the NextGENe main menu, click Tools > Barcode Sorting.

The Barcode Sorting dialog box opens.

Figure 8-3: Barcode Sorting dialog box

arcode sorting	in constate fil
Input:	-
	Add
	Remove
	Remove All
Import index file	Import
Example of barcode index file (REMOVE THIS LINE!!!) SampleData Index1 Index2 SampleName1 ATCACGAC TGAACCTT SampleName2 ACAGTGGT TGAACCTT 	
Match Type: Perfect match C Loose match	
C Determine index automatically	
Barcode length: 4 Total number of tags: 16	
Paired reads T Dual index Advanced Settings	i l
Output:	-
☐ Keep the barcode in the sequences	
Output:	Set

2. Specify the Barcode sorting for the samples files—Barcode in sequence, Barcode in read name, or Barcode in separate file.

The options on the Barcode Sorting dialog box are dynamically updated based on the Barcode sorting option that you select.

3. Click Add to browse to and select your sample files.

The sample files are listed by name in the Sample List pane. The name includes the full directory path to each sample file.

4. Select *one* of the following options:

Setting	Description
Import index file	Select this option if you created a Barcode/Primer file with known barcode information. Click Import to browse to and select the Barcode/Primer file that you want to import, and then select one of the following:
	• Perfect Match—If you select this option, the tag for a read must be an identical match to the tag that is defined in the Barcode/Primer file, or the read is not allocated to the tag.
	• Loose Match—If you select this option, the tag for a read is divided into three equal segments—the first half, the second half, and the middle segment. Only one of these three segments must be an identical match to the tag in the Barcode/Primer file for the read to be allocated to the tag.
	Note: The Loose Match method is especially useful for longer tag sequences where the likelihood of sequencing errors within the tag region is greater.
	Note: If you are using Barcode Sorting in the NextGENe AutoRun tool, you must import an index file.
Determine index automatically	Select this option if barcode information is not known and you want NextGENe to automatically the detect barcode information, and then do the following:
	 Indicate the barcode length. (Available only if you selected Barcode in Sequence.)
	• If you know the total number of true tags, select Total Number of Tags, and then enter the value.
	Note: When automatically detecting the number of true tags, the Barcode Sorting tool includes only the most frequently observed sequences to avoid parsing reads according tags that are the result of sequencing errors.
	Note: This option is not applicable for the NextGENe AutoRun tool.

5. Depending on your Barcode sorting selection, do the following:

Barcode Sorting Selection	Options
Barcode in sequence	1. If the forward read and the reverse read each have their own barcodes, then select Dual index.
	2. Continue to Step 6.
Barcode in read name	N/A.Continue to Step 8.
Barcode in separate file	 Select one or both of the following: Paired Reads: If you are loading paired read data, then select Paired Reads.
	 Dual Index: If the forward read and the reverse read each have their own barcodes, then select Dual index.
	2. Continue to Step 8.

Chapter 8 NextGENe Tools

6. Optionally, click Advanced Settings to open the Advanced Settings dialog box and select the appropriate settings for your data; otherwise, go to Step 8.

Figure 8-4: Advanced Settings dialog box

T Dual-Barcode	
F Barcode at 5' end only	
Check reverse complements of barcodes	
154 sample orientation estimation	
Estimate sample orientation before sorting	
	Load
	Preloaded
	Renove
	Remove All

Setting	Description
Dual-Barcode	Automatically selected and unavailable only if Dual Index has been selected; otherwise, not selected and unavailable.
Barcodes at 5' End Only	Selected by default and available only if Dual Index is not selected. Checks for barcodes only at the 5'end of reads.
Check Reverse Complements of Barcodes	 Selected by default. This option allows for any of the following four tag combinations: Forward + Forward Reverse + Reverse Forward + Reverse Reverse + Forward Clear this option if do not want NextGENe to check for the reverse complements of barcodes.
454 Sample orientation estimation - Estimate sample orientation before sorting	 Applicable only for Roche/454 data and available for selection only if the following two conditions are met: Barcode in sequence is selected. Import index file is selected. After selecting this option, click Load to load a .gbk or .fasta reference file, or click Preloaded to select a preloaded reference. This results in the alignment of the reads being carried out against the reference before barcode sorting is carried out.

7. Click OK.

The Advanced Settings dialog box closes and you return to the Barcode Sorting dialog box.

- 8. In the Output pane, do the following:
 - If you selected Barcode in sequence and the reads in the output file are to include the barcode sequences, then select "Keep the barcode in the sequences."
 - Leave the default value for the location of the output files as is (the default value is the directory path for the input data file), or you can click Set to specify a folder for storing the output files, a different location for the folder, or both.
- 9. Optionally, before you process the files, click Save to save the settings that you have specified to a Settings file (.ini file).



You can always load this file at a later date and process other data files according to the saved settings in the file.

10. Click OK.

A message opens the process is completed. If you selected "Determine Automatically" and you did not specify the total tag count, then two mutually exclusive criteria are used to determine when sorting by true tag sequences is complete.

- When the count of reads that contain a sample tag is less than 10% of the count for the previous tag, the tag is not used and barcode sorting is complete.
- After 95% of the sample reads have been parsed by barcode, one additional tag is used for sorting and then sorting is completed.

The names of the separate data files that are produced by the parsing are appended with the following information:

- The tag information as shown (if "Determine Automatically" was selected).
- The sample ID (if a Barcode/Primer file was used).

Figure 8-5: Separate data files produced by NextGENe's Barcode Sorting tool

SRR018422_converted_CGAG.fasta	1/27/2010 10:51 AM	FASTA File	662
SRR018422_converted_CTCG.fasta	1/27/2010 10:51 AM	FASTA File	334,720
SRR018422_converted_OtherTags.fasta	1/27/2010 10:51 AM	FASTA File	8,509
SRR018422_converted_TCGA.fasta	1/27/2010 10:51 AM	FASTA File	1,166

The NextGENe Sequence Operation Tool

You use the NextGENe Sequence Operation tool to modify the structure of sample files and references files *before* you work with the files in the NextGENe application, such as loading the files in the Project Wizard. The tool provides options for merging files, splitting files, trimming reads, reverse complementing sequences, arranging paired read files, removing duplicate reads, and creating a random subsample from sample .fasta files or .fastq files.

To use the NextGENe Sequence Operation tool

1. On the NextGENe main menu, click Tools > Sequence Operation.

The Sequence Operation dialog box opens.

Figure 8-6:	Sequence Operation dialog box

Merge files C Split files C Sequence Arrange paired reads C Remove duplicate reads C Reverse/C C Random Subsample	trim omplement seq
put:	Add
	Remove
	Remove A
utput:	
Settings	Set
Trim or reject read when >= 0 base(s) with score <= 0 Remove 5' 0 base(s) and 3' 0 base(s) Save the trimmed reads/qual in one line Trim by sequences	
Trim by sequences in the file	Load



The options that are available on the Sequence Operation dialog box are dynamically updated based on the selected sequence operation.

- 2. Do one of the following:
 - Select Merge Files, and then continue to "To merge files" below.
 - Select Split Files, and then continue to "To split files" on page 368.
 - Select Sequence Trim, and then continue to "To sequence trim reads" on page 369.
 - Select Arrange Paired Reads, and then continue to "To arrange paired reads" on page 373.
 - Select Remove Duplicate Reads, and then continue to "To remove duplicate reads" on page 373.
 - Select Reverse/Complement Seq, and then continue to "To reverse complement sequences" on page 375.
 - Select Random subsample, and then continue to "To create a random subsample" on page 376.



Optionally, instead of manually selecting the settings for any of these operations, you can click Load to browse to and select a Settings file (.ini file) to process the files based on the saved settings in the file. You can click Save after you specify the settings for any of these operations to save the settings to a Settings.ini file.

To merge files

You use the Merge Files option to merge multiple .fasta or .fastq files into a single .fasta or .fastq file.

- 1. In the Input pane, click Add to browse to and select a file that is to be included in the merged file. Repeat this step as needed to all the files that are to be merged into a single file.
- 2. In the Output field, you can leave the default value for the location of the output files as is (the default value is the directory path for the *first* data file added), or you can click Set to select a different location.



The default file name is merged.fasta. You can modify this name, if needed, but you must leave the extension as .fasta.

3. Optionally, before you process the files, click Save to save the settings that you have specified to a Settings file (.ini file).



You can always load this file at a later date and process other data files according to the saved settings in the file.

Chapter 8 NextGENe Tools

4. Click OK.

A message opens when the process is completed.

To split files

You use the Split Files option to split a single .fasta or .fastq file into multiple .fasta or .fastq files. This is a useful option if a single sample file is taking considerable memory to analyze and you would like to carry out a series of smaller and faster analyses.

- 1. In the Input pane, click Add to browse to and select the .fasta file or .fastq file that is to be split into multiple files.
- 2. In the Settings field, enter the maximum acceptable size for each partition in MB.
- 3. In the Output field, you can leave the default value for the location of the output files as is (the default value is the directory path for the input file), or you can click Set to select a different location.
- 4. Optionally, before you process the files, click Save to save the settings that you have specified to a Settings file (.ini file).



You can always load this file at a later date and process other data files according to the saved settings in the file.

5. Click OK.

A message opens when the process is completed.

The single file is split into "x" number of equally sized partitions, with any remainder contained in a smaller file. For example, for a 5.5 KB file with a partition size of 1 KB, six files are produced—five 1 KB files and one 0.5 KB file. As shown in Figure 8-7 below, the name for each partition is based on the name of the split file and is appended with the phrase "_part." In addition, the partitions are numbered sequentially.

Figure 8-7: Multiple .fasta files created by splitting a single .fasta file

merged.fasta	1/27/2010 1:47 PM	FASTA File	362,202 KB
merged_part_1.fasta	1/27/2010 2:18 PM	FASTA File	103,105 KB
merged_part_2.fasta	1/27/2010 2:18 PM	FASTA File	103,176 KB
merged_part_3.fasta	1/27/2010 2:18 PM	FASTA File	103,125 KB
merged_part_4.fasta	1/27/2010 2:18 PM	FASTA File	55,449 KB

To sequence trim reads


You use the Sequence Trim function to trim sequence reads within a .fasta or .fastq file, with or without using quality scores. For example, you can trim unwanted bases at the ends of reads, such as the first color call of SOLiD System reads or barcode tags. You can also trim reads relative to the number of "N" calls. Low quality reads can also be trimmed from a sample if a specified number of bases at the 3' end falls below a set threshold.


- 1. In the Input pane, click Add to browse to and select the .fasta file or .fastq file for which the sequence reads are being trimmed.
- 2. In the Output field, you can leave the default value for the location of the output files as is (the default value is the directory path for the input file), or you can click Set to select a different location.

Setting	Description
Remove 5' [] Bases and 3' [] Bases	Select this option to remove a set number of nucleotides from the 5' end of a sequence, the 3' end of a sequence, or both ends of a sequence.
Max # of Uncalled Bases >=	Select this option to remove entire reads from the sample file when the file contains more N calls than specified.
Called Base Number of Each Read	Select this option to remove entire reads from the sample file when the total number of called bases is less than the specified threshold.
Trim 3' End while >= [] Base(s) with Score <= []	Select this option to trim the 3' end of a read if the specified number of consecutive bases falls below a set quality threshold score.
	Note: For additional information about how this option works, see "Trim or Reject Read While >= [x] Bases with Score <= [y]" on page 91.
Saved the Trimmed Reads/Qual in One Line	Select this option to save trimmed files with each read in a single line.
	Note: This prevents longer reads being divided into multiple lines.
Trim By Sequences	Select this option to trim reads where the specified sequence occurs.
	Note: Select this option to remove primers or sequence tags. See "Trim by Sequences" below.
Trim by Sequences in the File	Selected by default. Load a text file that contains the sequences by which the reads are to be trimmed. See "Trim by Sequences in the File" on page 371.

3. Select the options for filtering and trimming low quality reads.

4. Optionally, if you selected Trim by Sequences or Trim by Sequences in the File, click Advanced Settings to open the Advanced Settings dialog box and select the advanced settings by which trim the sequences.





5. Optionally, before you process the files, click Save to save the settings that you have specified to a Settings file (.ini file).



You can always load this file at a later date and process other data files according to the saved settings in the file.

6. Click OK.

A message opens when the process is completed. Depending on the options that you have selected, up to two files are produced—one with trimmed reads and one with removed reads—as shown in Figure 8-9 below. In addition, if a .qual file was used, two more files are produced—a trimmed .qual file and a removed .qual file.

Figure 8-9: Sequence Trim files

SRR018422_converted_removed.fasta	1/27/2010 2:49 PM	FASTA File	580
SRR018422_converted_trimmed.fasta	1/27/2010 2:49 PM	FASTA File	344,821

Trim by Sequences

NextGENe allows for trimming by sequences in two cases:

- The sequence has an error in it.
- Only part of the sequence is present.

In these situations, NextGENe breaks the input sequence into smaller segments and checks the read for the small segments instead of the whole sequence.

- If the input sequence is >= 16 bp, then it is broken into small segments with a length of 12 bp.
- If the input sequence is < 16 bp but > 7 bp, then it is broken into small segments with a length of 8 bp.

• If the input sequence is < 8 bp but > 3 bp, then it is broken into small segments with a length of 4 bp.



No mismatches are allowed for an input sequence < 4 bp.

Trim by Sequences in the File

The file that contains the trimming sequences is a tab-delimited text file with up to four fields:

Field	Description
1st	Name
2nd	5' Trim Sequence
3rd	3' Trim Sequence
4th	Option Code:
	E - Exact match
	L - Loose match
	P - Partial match

Loose match uses the method described in "Trim by Sequences" with the following caveat: An input sequence with a length < 4 bp cannot be used for Loose match; however, the sequence can be used for Partial match and miRNA trimming. (See "miRNA Trimming" on page 372.)

In a Partial match, just a single base can be matched. Partial match allows for mismatches up to 10% of the matched length. This means the following:

- No mismatches are allowed if the adapter is < 10 bp in length or if only 10 bp of the adapter are overlapped.
- The adapter must be at the end of the read. 3' sequences can only partially overlap at the beginning of the sequence and the end of the read while 5' sequences can only partially overlap at the end of the sequence and the beginning of the read.

Values for the first and fourth fields are always required. Because you are trimming by sequence, you must have at least one sequence. This means that a trim sequence for either the second or third fields is required. If you have a 5' trim sequence (second field), then the 3' trim sequence (third field) is optional. Conversely, if you have a 3' trim sequence (third field), then the 5' trim sequence (second field) is optional. You still must use a placeholder if you do not have values for an optional field. For example, if you have a 5' trim sequence (second field), but not a 3' trim sequence (third field), then you must still enter a dash (-) in the third field, which is used as a placeholder.



This option is backwards-compatible with older text formats. Loose match is assumed for the Match Type.

Chapter 8 NextGENe Tools

If both 5' and 3' sequences are specified, then the 5' sequences are checked first. If multiple matches are found, then the best match for both the 5' and 3' ends are used for trimming.

Advanced Settings

If you have selected Trim by Sequences (see "Trim by Sequences" on page 370) or Trim by Sequences in the File (see "Trim by Sequences in the File" on page 371), then you can use the Advanced Settings to modify the trimming method.

Setting	Description
miRNA Trimming	Select this option to trim miRNA reads. This function uses a trim by sequence algorithm that was specifically designed for miRNA data. It trims the input sequences only at the 3' ends of reads. It also allows for trimming where only a portion of the input sequence is found.
	 N/A if you have specified both 5' and 3' sequences in the text file loaded for "Trim by Sequences in the File" on page 371.
	 Option code of Exact, Loose, or Partial match can be specified. The default is Loose.
	 Exact—Must match the full primer exactly anywhere in the read. Loose—Can match as low as 80%.
	 Partial—Can appear as a partial sequence at the 3' end (only if not found earlier in the read).
Check for Primer Dimers/Trimers	Selected by default. Where the same sequence is repeated two or three times in a row, all the sequences are trimmed. Clear this option to always trim only the first sequence that is found.
	• If this option is selected, and you specified the following option code, then:
	 Exact—Can occur up to 3x length inside read. Must match exactly. Select farthest "inside" match.
	 Loose—Can occur up to 3x length into the read. Minimum 80% match. Select farthest "inside" match.
	 Partial—N/A. Processed the same as not selecting this option.
	 If this option is not selected, and you specified the following option code, then:
	 Exact—Must occur at the end of the read (5' or 3' end as specified). Must match exactly.
	 Loose—Can occur up to 1.5x length into the read. Minimum 80% match. Select the farthest "outside" match.
	 Partial—Must occur at the end of the read. Minimum 80% match. If the full sequence is not found, checks shorter portions of the sequence (end of 5' sequence or beginning of 3' sequence). Selects the match with the largest number of matching positions. As few as one bp can be found.

To arrange paired reads

You use this option to arrange the reads in your sample files before you carry out sequence alignment. (NextGENe skips the step of arranging the sample files when you load the arranged files as the input files in the Project Wizard. See "Sequence Alignment Project Output Files" on page 208.)

- 1. In the Input pane, click Add to browse to and select the paired read files that are to be arranged.
- 2. In the Output field, you can leave the default value for the location of the output files as is (the default value is the directory path for the input files), or you can click Set to select a different location.
- 3. Optionally, before you process the files, click Save to save the settings that you have specified to a Settings file (.ini file).



You can always load this file at a later date and process other data files according to the saved settings in the file.

4. Click OK.

A message opens when the process is completed. Two output files that contain the arranged reads are created, for example, sampleA_1_arranged.fasta and sampleA_2_arranged.fasta.

To remove duplicate reads

Two algorithms are available for removing duplicate reads:

- Algorithm 1 uses the nucleotide sequence. See "The Nucleotide Sequence algorithm for removing duplicate reads" below.
- Algorithm 2 uses an index file that relates to Unique Molecular Identifiers (UMIs). See "The UMI algorithm for removing duplicate reads" on page 374.

The Nucleotide Sequence algorithm for removing duplicate reads

If Remove Duplicate Reads is selected, then the Sequence Operation Tool uses an algorithm that assigns a numerical value to every base in a read, where A = 0, C = 1, G = 2, and T = 3. A hash value is then calculated for every read according to the following formula:

sum(Base's code*(4^Base's position))

where the starting base position is = 0. For example, for the sequence ATTC, the hash value is calculated as:

 $0^{*}(4^{0}) + 3^{*}(4^{1}) + 3^{*}(4^{2}) + 1^{*}(4^{3}) = (0^{*}1) + (3^{*}4) + (3^{*}16) + (1^{*}64) = 124$

If multiple reads have the same hash value, indicating identical sequences and identical sequence length, then a single copy of this sequence is kept. For paired reads, if there are

multiple pairs where both forward reads have the same hash value, and both reverse reads have the same hash value, indicating identical sequences and identical sequence lengths, then only one pair of the reads is kept. For example, if Read 1F = Read 2F and Read 1R = Read 2R, then only one pair of reads is kept; however, if Read 1F = Read 2F, but Read $1R \neq \text{Read } 2R$, then both pairs of reads are kept.

- 1. In the Input pane, click Add to browse to and select the .fasta or .fastq files for which the duplicate reads are to be removed.
- 2. Optionally, specify the settings for removing the duplicate reads.

Setting	Description
Check 5' End Only for Paired Reads	If this option is selected, then only the first 32 base pairs at the 5' end of both paired reads must be identical to be considered duplicates.
Check After 1st Homopolymer	Available only if Check 5' End Only for Paired Reads is selected. Select this option to check for duplicate reads based on the first 32 base pairs <i>after</i> the first homopolymer sequence.

- 3. In the Output field, you can leave the default value for the location of the output files as is (the default value is the directory path for the input file), or you can click Set to select a different location.
- 4. Optionally, before you process the files, click Save to save the settings that you have specified to a Settings file (.ini file).



You can always load this file at a later date and process other data files according to the saved settings in the file.

5. Click OK.

A message opens when the process is completed.

Two data output files are created: _Duplicate.fasta, which contains duplicate reads that were discarded for analysis, and _Unique.fasta, which contains a single copy of all duplicated reads as well as all reads that were not duplicated. A log file, RemoveDuplicates_Log.txt, is also created. The file contains information about the input file, the reads (number of total reads, number of unique reads, and number of duplicate

reads), and the distribution of the reads and their counts.

The UMI algorithm for removing duplicate reads

Unique molecular identifiers (UMIs) are random sequences of bases that are used to tag each molecule (fragment) of DNA prior to library amplification, which aids in the identification of PCR duplicates. Illumina instruments generate an I2 Index File for paired-end runs, and an I2 Index File can store these UMIs. NextGENe can read an Illumina I2 Index File that contains UMIs. After reading an I2 Index File, NextGENe identifies all the reads that share the same UMI and retains only the read that has the highest total quality score for continued

processing. NextGENe classifies all other reads that share the same UMI as PCR duplicates and discards these reads. To use the UMI algorithm to remove duplicate reads, you must carry out the following prior to any Format Conversion preprocessing steps:

- 1. Select Process UMIs based on I2 Index File.
- 2. In the Input pane, click Add to browse to and select the R1 and R2 .fastq files for which the duplicate reads are to be removed.
- 3. In the Input pane, click Add to browse to and select the required I2 file, and optionally, an I1 file.
- 4. In the Output field, you can leave the default value for the location of the output files as is (the default value is the directory path for the input file), or you can click Set to select a different location.
- 5. Optionally, before you process the files, click Save to save the settings that you have specified to a Settings file (.ini file).



You can always load this file at a later date and process other data files according to the saved settings in the file.

6. Click OK.

A message opens when the process is completed.

Two data output files are created: _Removed.fastq, which contains duplicate UMIs that were discarded for analysis, and _Processed.fastq, which contains a single copy of all duplicated UMIs as well as all UMIs that were not duplicated. A log file, RemoveDuplicates_Log.txt, is also created. The file contains information about the input file, the reads (number of total reads, number of unique reads, and number of duplicate reads), and the distribution of the reads and their counts.

To reverse complement sequences

- 1. In the Input pane, click Add to browse to and select the .fasta file or .fastq file for which the sequence reads are being reverse complemented.
- 2. In the Output field, you can leave the default value for the location of the output files as is (the default value is the directory path for the input file), or you can click Set to select a different location.
- 3. Optionally, before you process the files, click Save to save the settings that you have specified to a Settings file (.ini file).



You can always load this file at a later date and process other data files according to the saved settings in the file.

Chapter 8 NextGENe Tools

4. Click OK

A message opens when the process is completed. A single file is produced and its name is appended with the phrase "_complemented" as shown in Figure 8-10 below.

Figure 8-10: Reverse Complemented file

SRR018422_converted_complemented.fasta 1/27/2010 2:55 PM FASTA File

To create a random subsample

You can select Random subsample to generate a random subsample from *any* dataset. If you select this option, then a reservoir sampling method is used to create the subsample.

- 1. In the Input pane, click Add to browse to and select the .fasta or .fastq file for which the random subsample is being.generated.
- 2. In the Output field, you can leave the default value for the location of the output files as is (the default value is the directory path for the input file), or you can click Set to select a different location.
- 3. In the Fraction of reads to keep field, enter any value between 1 and 99 to specify the percentage of the original reads that are to be included in the random subsample.
- 4. Optionally, before you process the files, click Save to save the settings that you have specified to a Settings file (.ini file).



You can always load this file at a later date and process other data files according to the saved settings in the file.

5. Click OK.

A message opens when the process is completed. A single file is produced and its name is appended with the phrase "_RandomSub" as shown in Figure 8-11 below.

Figure 8-11: Random subsample file

D_R1_converted_RandomSub.fasta 11/24/2015 11:34 ... FASTA File 34,355 KB

The NextGENe Reads Simulator Tool

Synthetic data can be a viable alternative to real data in many situations. For example, you might need to explore the effects of certain data characteristics on your data models and need to construct datasets exhibiting specific properties to test your data—for example, to verify the accuracy of the NextGENe Alignment function or to test the NextGENe assembly function. You can use the NextGENe Reads Simulator Tool to create synthetic read data, including paired reads, from a .fasta reference file.

To use the NextGENe Reads Simulator Tool

1. On the NextGENe main menu, click Tools > Reads Simulator.

The Reads Simulator dialog box opens.



s Simulator		
nput:		
		Add
		Remove
		Remove All
Dutput:		
		Set
Settings		
	✓ Both Directions	
SOLID Paired Read	✓ Both Directions	
SOLID Paired Read	Both Directions Include Indels	
SOLD Paired Read Read Length: 36 bases Steps: 2 bases		

- 2. In the Input pane, click Add to browse to and select the .fasta reference file from which the synthetic data is being created.
- 3. In the Output field, you can leave the default value for the location of the output files as is (the default value is the directory path for the input file), or you can click Set to select a different location.

Chapter 8 NextGENe Tools

4. Select the options for creating the synthetic data.

Setting	Description
SOLiD	Select this option to create reads in color-space.
Paired Reads	Select this option to create paired reads.
Both Directions	Select this option to create both forward and reverse reads, which by definition, doubles the number of reads and total coverage. If you do not select this option, then only forward reads are created.
Steps	The value that you enter for this option determines the number of references bases that are between the start of each read. A lower value results in more reads and therefore, greater coverage.
Error Rate	The Reads Simulator tool can incorporate errors into generated reads. Enter a value in this field to incorporate randomly generated errors, or set the value to "0" to have all the generated reads be an exact match to the reference genome.
Include Indels	Available only if the Error Rate is > 0. Select this option to include insertion errors and deletion errors in the generated reads.
Library Size	Available only if Paired Reads is selected. The size of the DNA fragment that is being simulated.
Random Library Size	Available only if Paired Reads is selected. Select this option to create pairs with random distribution of sizes that are centered based on the library size. For example, if the Library Size is set to 200, read pairs will have a gap size between 100 and 300.
	Note: If you do not select this option, all paired reads will have an identical library size.

5. Click OK.

A message opens when the process is completed. A single .fasta file is produced and its name is appended with the phrase "_SimulatedReads." The file is stored in a folder of the same name as shown in Figure 8-13 below.

Figure 8-13:	Simulated Reads output folder and file
--------------	--


merged_SimulatedReads	merged_SimulatedReads.fasta	2/5/2010 9:18 AM	FASTA File	2
-----------------------	-----------------------------	------------------	------------	---

6. Click OK to close the message and return to the Reads Simulator tool.

The NextGENe Pseudo Paired Read Constructor Tool

Paired reads are useful for detection of structural variations such as gene fusion, exon skipping, or read-throughs for transcriptome analysis. The NextGENe Pseudo Paired Read Constructor tool is another tool that you can use to construct paired reads. The NextGENe Pseudo Paired Read Constructor tool creates paired reads from either a reference genome (.fasta file) or sample files. For either file type, the Pseudo Paired Read Constructor tool creates two "paired" reads based on the read length that you specify. You can break the read in half using the entire read or you can specify that the new read length be less than half the original, using only the ends of reads and not the middle. The 5' end of the read is reversed to form one of the paired reads while 3' end is used directly as the other read in the pair.

Figure 8-14: Construction of pseudo paired reads from single sequence reads





To use sample file reads, the reads should be at least 76 bp in length. If original reads are less than 76 bp, you can use the Condensation Tool to increase read length prior to constructing the pseudo paired reads. See Chapter 4, "Sequence Condensation Tool," on page 95.



The other option for creating paired reads is the NextGENe Reads Simulator tool. See "The NextGENe Reads Simulator Tool" on page 377.

To use the NextGENe Pseudo Paired Read Constructor

1. On the NextGENe main menu, click Tools > Pseudo Paired Read Constructor.

The Pseudo Paired End Constructor dialog box opens. See Figure 8-15 on page 380.

	Add
	Remove
	Remove All
utput:	
	Set
Settings	
Output Read Length: 50	
Reverse Complement Output the 5' Ends	
reverse complement output the 5 chus	

Figure 8-15: Pseudo Paired Read Constructor dialog box

- 2. In the Input pane, click Add to browse to and select the input data files.
- 3. In the Output field, you can leave the default value for the location of the output files as is (the default value is the directory path for the input data file), or you can click Set to select a different location.
- 4. In the Settings pane, do the following:
 - Indicate the length of the output read files.
 - Optionally, indicate whether to reverse complement the 5' ends of the read output, the 3' ends of the read output, or both.
- 5. Click OK.

A message opens when the process is completed. As shown in Figure 8-16 below, two output files—one that contains all the reads for the first pair and one that contains all the reads for the second pair—are created and stored in a common folder. The folder name is appended with "_PseudoPairedReads" and the file names are appended with "_1" and "_2."

Figure 8-16: Pseudo paired end output folder and files

uncertainty 1 Decode Deine dDecode factor	merged_part_1.fasta_1.fasta	2/5/2010 9:27 AM	FASTA File
merged_part_1_PseudoPairedReads.fasta	merged_part_1.fasta_2.fasta	2/5/2010 9:27 AM	FASTA File

The NextGENe Condensation Results Filter Tool

You use the Condensation Filter tool to filter contaminants such as foreign DNA or primers from condensation reads or assembly results. The filtering is based on different characteristics of condensed reads or assembled contigs. You can remove primer contamination by selecting the Filter by Coverage option to remove very high coverage regions. If foreign DNA contamination is a concern, you can use the Reads Simulator Tool to break the genome and reassemble it with condensed reads. In this case, the option to Filter by Length removes contamination as reads that are assembled with the genome are likely contaminants. You use an Index Error Correction option for transcriptome analysis, where expression levels vary greatly. This option allows indices that differ by only a one base, but that have matching shoulder sequences, to be indexed together when the ratio of the frequency of the minor index to the frequency of the whole group falls below a set threshold.

To use the NextGENe Condensation Results Filter tool

1. On the NextGENe main menu, click Tools > Condensation Results Filter.

The Condensation Results Filter dialog box opens. The File Format section on the dialog box is an example of an output consensus sequence that is produced by the Condensation Tool. The sequences are assigned read names that reflect, from left to right, the anchor sequence, the shoulder sequences, and the counts of the forward and reserve reads that were used to create the sequence.

				Browse
Paired Reads				
				Browse
ïle Format: >944 GTGAGAATATAA :TGAATTTGAAGGTAGTGAGA	15 TGAAGGTA	ATTTAAGA	9 12	
TOAATTTGAAGGTAGTGAGA	ATATAAATTTAAGAGAAAAG	ACATITIOG		
tput:				Set
tput:				Set
	Each Direction:	20	Both Directions:	50 Set
tput:	Each Direction: Length Threshold:	20	Both Directions: [
tput: Settings Filter by Coverage			Both Directions:	

Figure 8-17: Condensation Results Filter dialog box

- 2. In the Input pane, do one of the following:
 - If you are not using paired reads data, then click Browse to browse to and select the input data file that is to be filtered.
 - If you are using paired reads data:
 - Click Browse to browse to and select the first input data file that is to be filtered.
 - Click Paired Reads, and then click Browse to browse to and select the second input data file that is to be filtered.
- 3. In the Output field, you can leave the default value for the location of the output files as is (the default value is the directory path for the (first) input data file), or you can click Set to select a different location.
- 4. In the Settings pane, select the appropriate options for your analysis. You can accept the default values for the selected settings or you can change the values as needed.
- 5. Click OK.

A message opens when the process is finished. A number of output files are created based on the options that you selected. The output files are appended with the phrase "_Filter" as shown in Figure 8-18 below.

Figure 8-18: Sample output files from the NextGENe Condensation Results Filter tool


SRR018422_converted_Filter_filtered.fasta	2/5/2010 9:39 AM	FASTA File
SRR018422_converted_Filter_removed.fasta	2/5/2010 9:40 AM	FASTA Fil

The NextGENe Condensation Results Tool

You use the NextGENe Condensation Results tool to view the results of the Condensation data analysis step. You can use this tool in one of two ways: to view the condensation results *immediately* after your data analysis is complete, or to view the results at a later date.

- To view the results immediately, when analyzing your data, you must select "Consolidation" as the Condensation Type and you must also select "View Condensation Results" on the Condensation Advanced Settings page. When data analysis is complete, click Tools > Condensation Results on the NextGENe main menu.
- To view the results at a later date, you must select "Consolidation" as the Condensation Type and you must also select "View Condensation Results" on the Condensation Advanced Settings page. At any time after data analysis is complete, click Tools > Condensation Results on the NextGENe main menu, and then click Load to browse to and select the TempViewDir.giv file, which is one of the output files that is created by the Consolidation method. This file contains all the consolidation results.

The Condensation Results dialog box graphically displays the reads that were used for each index and a table that shows the number of reads that were used in each direction for each index.





Condensed Reads pane

The Condensed Reads pane is the top pane of the dialog box. This pane shows a list of all the condensed reads for the index that is currently selected in the Index table. The first line in the pane is the currently selected index. The remaining lines show all the reads that were clustered in the selected group. The middle pane shows the consensus sequences for the subgroups. Reads that share a common anchor sequence can differ in the shoulder sequences because the index is not unique in the genome. Also, indices might not meet the criteria for any groups of reads to be created. As a result, the Condensed Reads pane can be blank, it can have one condensed read, or it can have multiple condensed reads.

Index table

The Index table is located in the lower pane of the Condensation Results dialog box. This table lists of all indices, or anchor sequences, there were found in the sample reads and that met all your consolidation settings. From left to right, the columns in the table are:

- Index—Lists the index number for each index.
- Anchor—Lists the corresponding index, or anchor sequence.
- Forward Number—Lists the number of forward reads for the index.
- Reverse Number—Lists the number of reverse reads for the index.

The NextGENe GC Percentage Calculation Tool

A GC base pair has three intermolecular hydrogen bonds whereas an AT base pair has just two intermolecular hydrogen bonds. Consequently, molecular regions with higher GC content have a more stable secondary structure, which, in turn, can have an impact on PCR. Higher GC content results in higher melting temperatures or specific reagents such as DMSO to break up this secondary GC structure and as a result, GC-rich regions of a sample might be underrepresented during data analysis. You use the NextGENe GC Percentage Calculation tool to determine the GC content of regions in a sample data file.

To use the NextGENe GC Percentage Calculation tool

1. On the NextGENe main menu, click Tools > GC Percentage Calculation.

The GC Percentage Calculation dialog box opens.

Figure 8-20: GC Percentage Calculation dialog box

(
GC Percentage Calculation	×
Input:	
	Set
Output GC Percentage File:	
	Set
ОК	Cancel

- 2. In the Load File pane, click Set to browse to and select the input file for which the GC content is being calculated.
- 3. In Output GC Percentage File pane, click Set to specify the name of the output file and the location of the output file.
- 4. Click OK.


The output file is saved as a .txt file. It lists the GC content every 31 bp for the sample data file.

Figure 8-21: Sample output file from the GC Percentage Calculation tool

File	Edit	Format	View	Help
	6129			
62 0	.451	613		
	0.37			
	0.38			
217		0323		

The NextGENe Overlap Merger Tool

You use the NextGENe Overlap Merger Tool to merge overlapping contigs or reads. You can merge overlapping contigs from assembled reads, or you can merge overlapping paired reads after elongation. (In this application of the tool, only reads that are in the same pair that overlap *and* the overlapping portions match are merged.) You can merge both .fasta and .fastq files with this tool.



To use the NextGENe Overlap Merger tool

1. On the NextGENe main menu, click Tools > Overlap Merger.

The Overlap Merger dialog box opens.

Figure 8-22: Overlap Merger dialog box

Overlap Merger	×
Input:	
	Add
	Remove
	Remove All
	< >
Output:	Set
O Merge Overlapping Contigs	
Merge Overlapping Paired Reads Overlap Min Bases 9	
Ignore Low Quality Ends for Non-Overlapped Pairs	
Merged Length 0 bp to 1000 bp	
Merged Length 70 % to 130 % of the longer read length	
ОК	Cancel

- 2. In the Input files pane, click Add to browse to and select the input files that are being merged.
- 3. In the Output field, you can leave the default value for the location of the output files as is (the default value is the directory path for the *first* data file added), or you can click Set to select a different location.

4. Specify your settings as appropriate.

Setting	Description
Merge Overlapping Contigs	Applicable only for <i>de novo</i> assembly results. Select this option to determine whether any of the contigs are overlapping and can be merged further.
Merge Overlapping Paired Reads	Applicable only for raw paired reads that are overlapping.Note: The library size and read length determine whether the paired reads are overlapping or not.
Ion Floton Illumina	Available only if Merge Overlapping Paired Reads is selected. Select the type of data that is being analyzed.
Overlap Min Bases	The minimum number of bases that must overlap for the contigs to be merged.
Ignore Low Quality Ends for Non-Overlapped Pairs	Applicable only for elongated paired reads data. Non- overlapped reads are saved in the unmatched.fasta files. If elongated reads are used for merging, then lowercase letters, which are used at the ends of elongated reads, are trimmed from the non-overlapped reads before the file is saved.
Merged Length [] bp to [1000] bp Merged Length [70] bp to [130] %	Applicable only for paired reads data. Set an acceptable length for the merged results.
of the longer read length	Note: Both options can be selected. If both options are selected, then the data must meet both criteria to be included in the results.



If you add multiple input files and you select Merge Overlapping Contigs, then both files are used for merging—for example, a contig from file A could be merged with a contig from file B.

5. Click OK.

A folder is created for the output files. The default folder name is based on the name of the files that were analyzed and is appended with the word "Merge" as shown in Figure 8-23 below. The folder contains several text files, which are detailed in the table below.

Figure 8-23: NextGENe Overlap Merger output folder and files

SRR018422_converted_PseudoPairedReads.fasta	SRR018422_converted.fasta_1_1_unmatched.fasta	3/12/201
SRR018422_converted.fasta_1_Merge_Output	SRR018422_converted.fasta_1_2_unmatched.fasta	3/12/201
Image: SRR018422_converted.fasta_1_Output	1000	
	SRR018422_converted.fasta_1_MergeLog.txt	3/12/201
	SRR018422_converted.fasta_1_PairMerge.fasta	3/12/201

File	Description
Merge Overlapping Contigs	
input file name_ContigMerge.fasta	Contains the merged contigs.
statinfo.txt	Details various statistics about the merge.

Chapter 8 NextGENe Tools

File	Description
Merge Overlapping Paired Reads	
File name 1_unmatched.fasta	Contain the reads that were not merged.
File name 2_unmatched.fasta	
MergeLog.txt	Details various statistics about the merge.
PairMerge.fasta	Contains the merged reads.

The NextGENe Long PE Assembly Mapping Tool

In the PE Assembly method (see "PE assembly method for Roche/454, Illumina, and Ion Torrent data" on page 123), NextGENe automatically decides which scaffold contigs are to be linked together based on the paired read information. You can use the Long PE Assembly Mapping tool to override these automatic selections and manually select the scaffold contigs that are to be linked together.



The FinalContig_ScaffoldContig_Mapping.txt file shows the scaffold linking that NextGENe automatically carried out. You must edit this file prior to using the Long PE Assembler Mapping tool. For assistance with editing this file, contact Technical Support at tech_support@softgenetics.com.

To use the NextGENe Long PE Assembly Mapping tool

1. On the NextGENe main menu, click Tools > Long PE Assembly Mapping.

The Long PE Assembly Mapping dialog box opens.

Figure 8-24: Long PE Assembly Mapping dialog box

Long PE Assembly Mapping	EX
Scaffold Contigs Input:	Browse
Scaffold Contigs Mapping:	Browse
Output:	
	Set
OK	Cancel

- 2. Next to the Scaffold Contigs Input field, click Browse to browse to and select the ScaffoldContigs.fasta file.
- 3. Next to the Scaffold Contigs Mapping field, click Browse to browse to and select the FinalContig_ScaffoldContig_Mapping.txt file that you have edited.
- 4. In the Output field, you can leave the default value for the location of the output files as is (the default value is the directory path for the ScaffoldContigs.fasta file), or you can click Set to select a different location.
- 5. Click OK.

A message opens when the process is completed. An output file named AssemsbledSequences.fasta is generated.


The NextGENe File Preview Tool


You use the NextGENe File Preview tool to view some basic information about a sample file such as its format, typical read length, and possible patterns in quality scores. This information can be helpful in determining file format conversion settings and in other areas of the NextGENe application as well.

To use the NextGENe File Preview tool

1. On the NextGENe main menu, click Tools > File Preview.

The File Preview dialog box opens.





2. On the File menu, click Open to browse to and select the file for previewing.

Chapter 9 The NextGENe AutoRun Tool

NextGENe provides many tools for optimizing input data and exporting and analyzing results. The NextGENe AutoRun tool is a multi-functional tool that you can use for the following purposes:

- To carry out the batch analysis of multiple projects, where each project is referred to as a *job*, and jobs are contained in a single job file.
- To carry out the batch processing of previously processed sequence alignment projects and export outputs of your choosing.
- To carry out a secondary batch analysis of multiple projects.
- To create and modify templates for facilitating job setup in the NextGENe AutoRun tool, including jobs for analysis of data for RainDance Thunderbolts panels.

This chapter covers the following topics:

- "The NextGENe AutoRun Job Editor Dialog Box" on page 393.
- "Batch Processing of Multiple Projects" on page 398.
- "Batch Processing of Previously Processed Projects to Output Reports and Other Export Files" on page 420.
- "Secondary Batch Analysis of Multiple Projects" on page 427.
- "Managing NextGENe AutoRun Templates" on page 429.
- "Working With NextGENe AutoRun Pre-Built Templates" on page 436.



With the exception of the NextGENe AutoRun tool, you can open all the NextGENe tools only from the Tools option on the NextGENe main menu. You can, however, also open the NextGENe AutoRun tool independently of NextGENe through the Start menu and that is why it is afforded its own chapter. The NextGENe Format Conversion tool is discussed in Chapter 3, "File Format and Conversion," on page 85. All other NextGENe tools are discussed in Chapter 8, "NextGENe Tools," on page 359.

Chapter 9 The NextGENe AutoRun Tool

The NextGENe AutoRun Job Editor Dialog Box

The NextGENe Autorun Job Editor dialog box is your starting point for the NextGENe AutoRun tool. The dialog box provides access to all the functions and tools that are needed for setting up AutoRun jobs. The dialog box has five major components:

- The title bar.
- The Job Tree pane.
- The Job Editing pane.
- The main menu.
- The toolbar.

Figure 9-1: Job Editor dialog box

File Edit Tools			
	1 @		
 Job 1 Sample File(s) Preprocessing 	Job name; Job 1 Template: Choose Template	יו הפונט שו דו הכ	2089782_196 Save
- None Reference File(s)			
NextGENe Settings File	Input sequence files:	11	Load
Output Path			
l			Remove
	Output:		Set
			56(
	Preprocesses: 0 (Add)		
	Reference:		
			Select
			Remove
	Process & report settings file:	Inspect input files to set optimum parameters	
			Load
	Report & Expern 0 (Edit details)		
	Dutput to Geneticist Assistant		
	BunName	Sample Name Job 1	
	rearrance 1	Signific manie inter 1	_
		OK	Cancel

Title bar

The name "NextGENe AutoRun Job Editor" is displayed in the title bar at the top of the main. When the dialog box first opens, "Untitled" is displayed after the name. After you load a NextGENe job file, the full path to the loaded file as well as the file name are displayed after NextGENe AutoRun Job Editor.

Figure 9-2: Job Editor dialog box title bar showing loaded job file


🚺 NextGENe AutoRun Job Editor - C:\Users\Spectrum Writing\Desktop\Mayo clinic.ngjob

Chapter 9 The NextGENe AutoRun Tool

Job Tree pane

The Job Tree pane is the left pane of the NextGENe AutoRun Job Editor dialog box. It displays all the jobs that are contained in a loaded job file. You can expand and collapse the Job Tree structure as needed to view all the information (sample files, preprocessing settings, and so on) for each job in the job file.

Figure 9-3: NextGENe AutoRun Job Editor dialog box, Job Tree pane



Job Editing pane

The Job Editing pane is the right pane of the NextGENe AutoRun Job Editor dialog box. You carry out all the work that you need for setting up a new job or modifying an existing job in this pane.

Figure 9-4: NextGENe AutoRun Job Editor dialog box, Job Editing pane

Job name:	piname: Job 1 (01)		51111-31110708 <u>_</u> 657	
Template:	Choose Template	T	Save	
Input séqu	ence files:			
			Load	
		I	Remove	
Output:				
Dergoux.			Set	
Process &	report settings file:	Inspect input files to set optimum parameters	Remove	
			Load	
Repol V E	open di l <u>'Edju details</u>)			
🗌 Output	to Geneticist Assistant (Edu details)			
Ronth	me	Sample Marre Job 1		
		OK	Cancel	

Main menu

The main menu is set up in a standard Windows menu format with menu commands grouped into menus (File, Edit, Tools) across the menu bar.



Some of these menu commands are also available on the toolbar of the Job Editor dialog box. See "Toolbar" on page 396.

Figure 9-5:	Job Editor dialog box main menu

File Edit Tools

Main Menu Option	Menu Selections
File	 New Job File – Clears all the information that is currently displayed in the dialog box and creates a placeholder named "Job1" for a brand new AutoRun job.
	 Load Job File – Loads and displays all the information for a selected NextGENe Job file (*.ngjob) in the dialog box.
	 Save Job File – Saves the information for all jobs in a NextGENe AutoRun job file. You can specify a file name and location for the job file.
	Note: The file has an extension of .ngjob and you cannot change this.
	 .Save As – Saves a copy of the job file that is currently loaded in the dialog box. You must enter a different name for the copy.
	 Close – Closes the NextGENe AutoRun Job Editor dialog box.
Edit	 Add a New Job File – Refreshes the Job Editor dialog box with a placeholder for another job to add to the current job file.
	 Add a Report-only Job – Used to load Settings files for previously processed projects to output reports and other export files. See "To load and run the projects" on page 422.
	 Add a Secondary Analysis Job – Used for carrying out the secondary batch analysis of multiple projects. See "Secondary Batch Analysis of Multiple Projects" on page 427.
	 Delete Job – Deletes the job that is currently selected in the Job Tree pane.
	 Duplicate Job – Creates a new job with options that are identical to options for the job that is currently displayed in the Job Editing pane.
	 Group Samples into Jobs – If you have loaded data from multiple samples, you might want to group these samples into separate jobs. This option opens the Group Jobs dialog box so that you can do this. The same job options are applied to all the separate job files. See "To group jobs" on page 412.
	 Apply Settings to All Jobs – Applies all the settings for the job that is currently displayed in the Job Editing pane to all the jobs that are contained in the job file.
Tools	Manage Templates – Opens the Manage Templates dialog box, which displays the name and other details for all the system-supplied and custom templates for your NextGENe AutoRun tool. It also contains a Delete option that you can use to Delete any custom template. See "Managing NextGENe AutoRun Templates" on page 429.

Chapter 9 The NextGENe AutoRun Tool

Toolbar

The Job Editor toolbar provides quick access to a variety of editor functions.

Figure 9-6: NextGENe AutoRun Job Editor dialog box toolbar



Toolbar icon	Description
	Create New Job File icon – Clears all the information that is currently displayed in the Job Editor dialog box and creates a placeholder named "Job1" for a brand new AutoRun job.
	 Save current jobs to file icon – Saves the information for all the jobs that are displayed in the Job Tree pane in a NextGENe AutoRun job file. You can specify a file name and location for the job file. Note: The file has an extension of .ngjob and you cannot change this.
	Add a new job icon – Multiple options are available on the icon's dropdown menu:
	 Add a New Job option – Refreshes the Job Editor dialog box with a placeholder for another job. You must add the necessary information for each additional job. After you have added all the necessary jobs, click Save.
	 Add a Report-only Job – Used for batch processing of previously processed sequence alignment projects to output reports and other export files. See "Batch Processing of Previously Processed Projects to Output Reports and Other Export Files" on page 420.
	 Add a Secondary Analysis Job – Initiates the secondary batch analysis of multiple projects. See "Secondary Batch Analysis of Multiple Projects" on page 427.
	Delete current job icon – Deletes the job that is currently selected in the Job Tree pane.
B	Duplicate current job icon – Create a new job with options that are identical to options for the job that is currently selected in the Job Tree pane.
	Note: This is useful to create a new job that needs only minor modifications.
8	Group samples into jobs icon – If you have loaded data from multiple samples, then you might want to group these samples into separate jobs. This option opens the Group Jobs dialog box so that you can do this. The same job options are applied to all the separate job files. See "To group jobs" on page 412.

Toolbar icon	Description
₽₽	Apply settings to all jobs icon – Applies all the settings for the job that is currently displayed in the Job Editing pane to all the jobs that are contained in the job file.

Batch Processing of Multiple Projects

You use the NextGENe AutoRun tool to carry out the batch analysis of multiple projects, where each project is referred to as a *job*, and jobs are contained in a single job file. The tool scans for queued job files at an interval that you set. When a job file is available for processing, the NextGENe AutoRun tool automatically launches an instance of NextGENe for analyzing the data in the job files. Sample files can be in pre-fasta format.

Using the NextGENe AutoRun function is a two-step process. First, you must create a job file that specifies the parameters for processing the jobs (projects). To create a job file, you can do one of the following:

• You can create a new job file. You can use the options that are available on the Job Editor dialog box (included in the NextGENe AutoRun tool) to create this file, or you can use a text editor.



If you want to use a text editor to create a job file, SoftGenetics recommends that you first use the Job Editor to create a file with a single job, which ensures that the file has the correct format. You can then open this file in a text editor and copy the information for the existing job and modify it as needed to create other jobs. Contact SoftGenetics at tech_support@softgenetics.com for assistance.

- You can load an existing job file and modify it as needed.
- You can create a job file from an existing AutoRun template.

Second, you must specify the settings for the AutoRun tool, which includes the job file directory, the time interval for detecting job files, and the maximum number of parallel jobs.



To export any output to Geneticist Assistant, User Management must be turned on for your NextGENe instance. See "To turn on user management" on page 35.

To create a new job file in the NextGENe AutoRun Tool

- 1. Do one of the following:
 - On the NextGENe main menu, click Tools > NextGENe AutoRun.
 - On the Start menu, select All Programs\SoftGenetics\NextGENe\NG_<Version>\NG_AutoRun.

The NextGENe AutoRun window opens. See Figure 9-7 on page 399.

NextGENe AutoRun (Administrator) File Tool Help	
x = x	

Figure 9-7: NextGENe AutoRun window

2. On the NextGENe AutoRun main menu, click Tool > Job Editor.

The Job Editor dialog box opens. It contains a placeholder for creating a job, which is identified with the default name of Job<#>, for example, Job1.

	<i>a</i>	
■ Job 1 — Sample File(s)	Job name: Job 1	20161(12089732_106
Preprocessing	Template: Choose Template	• Save
	Input sequence files:	
		Load
L		Remove
	Output:	_
	Corpus.	Set
	Preprocesses: 0 (Add)	
	Reference:	
		Select
		Remove
	Process & report settings file: Inspect input files to set optimum parame	eters
		Load
	Repert & Expert Q (Edit details)	
	Output to Geneticist Assistant	
	Finn Marrie Job 1	

Figure 9-8: Job Editor dialog box

3. For each sample file that is to be analyzed, click Load in the Sample File(s) pane to open a dialog box, and then browse to and select the sample file.

The job name is automatically updated based on the file name of the first file loaded, but you can modify as needed.



You can load multiple samples for analysis with the same job options and then use the Group Jobs option to automatically group samples into separate jobs. The same job options are applied to all the separate job files. See "To group jobs" on page 412.

- 4. In the Output field, leave the default value for the location of the output files as is (the directory path for the *first* data file added), or click Set to select a different location.
- 5. If your project sample files require preprocessing, then you must load the appropriate Settings files (.ini files) to specify the required preprocessing options.
 - If the project sample files are not in .fasta or .bam format, then you must load a Settings file that specifies the format conversion settings.
 - If the project sample files contain barcodes, then you must load a Settings file that specifies the barcode sorting settings to demultiplex the data.
 - If the project sample files need to be modified further before analysis (for example, trimming adapters), then you must load a Settings file that specifies the appropriate sequence operation settings.

If applicable, for any of the above, go to "To specify preprocessing options" on page 403; otherwise, continue to Step 6.

- 6. In the Reference pane, click the arrow that is next to Select to open a dropdown menu, and then do one of the following:
 - To select a preloaded reference, click Select Preloaded Reference to open a Load Reference Files dialog box in which you can select the preloaded reference, and then continue to Step 9.
 - To select a GenBank or a .fasta reference file, click Add Sequence Files to open a dialog box in which you can browse to and select the reference file, and then continue to Step 7.
- 7. If you loaded a GenBank reference file, then "Query annotation and & tracks from preloaded" is displayed below the reference pane with a Select option. If you do not want to query the imported databases (tracks) for the project, then continue to Step 9; otherwise, click Select to open the Select a reference to query annotation and tracks dialog box and select the appropriate preloaded reference. See Figure 9-9 on page 401.




Figure 9-9: Select a reference to query annotation and tracks dialog box

8. Click OK.

The Select a reference to query annotation and tracks dialog box closes. The Job Editor dialog box remains open.

9. Next to the Process & report settings file field, click Load to open a dialog box, and then browse to and select a configuration file with the appropriately saved settings for the condensation, assembly, and/or alignment steps. (See "Saving and Loading Project Settings" on page 74.)

After you load the Settings file, Report & Export is enabled and the number of post-processing options that the loaded file contains is displayed. An Edit details link is also enabled.

Figure 9-10: Loaded Settings file with two post-processing options



- 10. Optionally, consider the following; otherwise, continue to Step 11.
 - If the configuration file that you loaded in Step 9 does not contain post-processing options, and you want to post-process the data:

or

• If the configuration file that you loaded in Step 9 does contain post-processing options, but you want to add more options or use different settings to post-process the data:

then click Edit details to open the Outputs dialog box. See Figure 9-11 on page 402.

Figure 9-11: Outputs dialog box	Figure 9-11:	Outputs dialog box
---------------------------------	--------------	--------------------

Report	Settings		Ad
Mutation	-	Set Remove	Remov
Save summary f	eport Settings		bA
Export Sequence	*	Set Bemove	Remov
Export BAM			

- 11. Select the appropriate post-processing outputs and the corresponding Settings files (.ini files) by which to post-process the data. See:
 - "To select report post-processing options" on page 405.
 - "To export aligned sequences as a post-processing option" on page 409.
 - "To export a BAM file relative to an ROI BED file" on page 409.
 - "To export the project output to a BAM file" on page 410.
- 12. Click OK on the Outputs dialog box.

The Outputs dialog box closes. The Job Editor dialog box remains opens.

- 13. Optionally, if *either* of the following are applicable, then select Inspect input files to set optimum parameters.
 - If you loaded a Configuration file that contains condensation settings for Illumina data, SOLiD System data, or Ion Torrent data, and you select this option, then NextGENe inspects the input files and adjusts the condensation settings accordingly. If you select this option for Roche data, then NextGENe simply ignores it.



This option is identical to the Inspect Input Files option on the Condensation page in the Project Wizard. See "Inspect Input Files" on page 102.

• If you loaded a Configuration file that contains alignment settings for a preloaded reference, and you select this option, then NextGENe inspects the input files and adjusts the alignment settings accordingly.



This option is identical to the Inspect Input Files option on the Alignment page for preloaded reference files in the Project Wizard. See "Inspect Input Files" on page 135.

- 14. If the output is to be exported to Geneticist Assistant, then go to "To export the output to Geneticist Assistant" on page 411; otherwise, continue to Step 15.
- 15. Optionally, do any of the following as needed; otherwise, continue to Step 16.
 - Save the job file.
 - Add a new job to the job file.
 - Add a secondary analysis job.
 - Delete a job.
 - Duplicate a job.
 - Group samples into jobs.



See "Main menu" on page 395 and "Toolbar" on page 396 for a detailed discussion about the accessing these options.

16. Click OK.

If you have not already clicked Save to save the job file, then you are prompted to specify a file name and location for the job file and after you save the file, the Job Editor dialog box closes; otherwise, the Job Editor dialog box simply closes. You have now created the necessary job files.

17. Continue to "To specify the NextGENe AutoRun settings" on page 417.

To specify preprocessing options

When you specify preprocessing options, you must select a previously saved Settings file (.ini file). If the appropriate Settings file is not available, then you must create it. See:

- For a Format Conversion Settings file, see "To convert a sample file" on page 87.
- For a Barcode Sorting Settings file, see "To parse barcoded sample files" on page 362.
- For a Sequence Operation Settings file, see "The NextGENe Sequence Operation Tool" on page 366.
- 1. Next to Preprocesses, click Add.

The Preprocessing Steps dialog box opens. See Figure 9-12 on page 404.

<< Barcode Sorting << Sequence Operation
<u>U</u> p
Dawn
Remoye
Remove Al

Figure 9-12: Preprocessing Steps dialog box

2. Click Format Conversion, Barcode Sorting, or Sequence Operations, as appropriate.

The Load Settings File dialog box opens.

3. Browse to and select the appropriate Settings file (.ini file) for the project, and then click Open.

The Load Settings dialog box closes. The selected Settings file is displayed in the Preprocessing Steps dialog box with an Edit option next to it. The Preprocessing Steps dialog box remains open.

- 4. Repeat Step 2 and Step 3 as needed to add all the appropriate Settings files (.ini files).
- 5. Optionally, do any of the following as needed:
 - To change the order of a loaded Settings files, select the file, and then click Up or Down as needed.
 - To remove a file, select the file, and then click Remove.
 - To remove all files in a single step, click Remove All.
 - To edit a loaded file, click Edit next to the file.



For detailed information about editing the settings for a:

- Format Conversion Settings file, see "To convert a sample file" on page 87.
- Barcode Sorting Settings file, see "To parse barcoded sample files" on page 362.
- Sequence Operation Settings file, see "The NextGENe Sequence Operation Tool" on page 366.

6. Click OK.

The Preprocessing Steps dialog box closes. The number of preprocessing Settings files that you loaded is indicated next to Preprocesses, and hyperlinks that identify each type of file (Format Conversion, Barcode Sorting, and/or Sequence Operations) are also displayed as shown in Figure 9-13 below.

Figure 9-13: Loaded preprocessing Settings files

Preprocesses: 2 (Format Conversion, Barcode Sorting)



After you load at least one preprocessing Settings file, Edit is no longer displayed. next to Preprocesses. To open the Preprocessing Steps dialog box again, you must click a hyperlink for a Settings file.

- 7. Return to one of the following as appropriate:
 - Step 6 of "To create a new job file in the NextGENe AutoRun Tool" on page 398.
 - Step 4 of "To create a NextGENe AutoRun template" on page 429.
 - Step 5 of "To modify a NextGENe AutoRun template" on page 434.
 - Step 6 of "To modify a NextGENe AutoRun pre-built template" on page 443.

To select report post-processing options

If you specify report post-processing options, then selected reports are automatically generated and saved for the project after analysis is complete. Each report is generated and saved based on the settings that were specified in a saved Settings file (.ini file) for the report. You can generate and save multiple versions of different reports, or multiple versions of the same report as long as each report version uses a different Settings file. To specify post-processing options for the *first* time, you must have previously saved a Settings file for at least one of the following reports:

- Mutation report. See "Mutation Report settings" on page 213.
- Distribution report. See "Distribution report" on page 254.
- Coverage Curve report. See "Coverage Curve report" on page 258.
- Expression report. See "Expression Report" on page 265.
- Structural Variation report. See "Structural Variation report" on page 273.
- HLA report. See "HLA project report" on page 197.



The HLA report is available as a post-processing option only if HLA was selected as the application type for the project. See "HLA Project" on page 195.

• Transcript report. See "Transcript report" on page 173.



The Transcript report is available as a post-processing option only if Transcriptome with Alternative splicing is selected as the application type. See "Transcriptome Alignment Project with Alternative Splicing" on page 168.

• Summary report. See "Summary report" on page 246.



The Summary report is available only after you select at least one other post-processing report and its Settings file. The information that the report contains is relative to the post-processing reports that you select for the project.

Continue to one or both of the following as needed:

- "To select the Mutation Report as a post-processing option" below.
- "To select a report other than the Mutation report as a post-processing option" on page 408.

To select the Mutation Report as a post-processing option

If you select the Mutation report as a post-processing option, two different Settings files are available. The General Report Settings file contains all the general options for the Mutation report. The Variation Tracks Settings file contains all the tracks settings for the Mutation report based on the variation databases that were imported for the project.



For information about the various options for the Mutation report, see "Mutation Report settings" on page 213. For information about importing variation databases into NextGENe, see the Reference & Track Manager User's Manual or Online Help.


1. On the Report dropdown list, select Mutation Report.

A blank Settings field opens next to the selected report.

2. Next to the blank Settings field, click Set.

The Set Mutation Report Settings dialog box opens.

Figure 9-14: Set Mutation Report Settings dialog box



- 3. Under General Report Settings click Set to display the Open dialog box, and then browse to and select a saved Settings file (*.ini file) for the report.
- 4. Optionally, to specify display or filtering settings based on imported variation tracks, under Variation Tracks Settings, click Set to display the Open dialog box, and then browse to and select a saved Settings file (*.ini file) for the report.
- 5. Click OK.

The Set Mutation Report Settings dialog box closes. The Outputs dialog box remains opens.

6. Optionally, click Save Summary report to have a Summary report automatically generated for the project as well.



Remember, Save Summary report is available only after you select at least one other post-processing report and its Settings file. For information about the Summary report, see "Summary report" on page 246.

- 7. If you are done with specifying the needed post-processing options, then return to one of the following as appropriate:
 - Step 12 of "To create a new job file in the NextGENe AutoRun Tool" on page 398.
 - Step 5 of "To create a single post-processing Settings file" on page 420.
 - Step 7 of "To create a new job from an existing AutoRun template" on page 416.
 - Step 9 of "To create a NextGENe AutoRun template" on page 429.
 - Step 5 of "To modify a NextGENe AutoRun template" on page 434.
 - Step 6 of "To modify a NextGENe AutoRun pre-built template" on page 443.

Otherwise, continue specifying any other needed post-processing options. See:


- "To select a report other than the Mutation report as a post-processing option" on page 408.
- "To export aligned sequences as a post-processing option" on page 409.
- "To export a BAM file relative to an ROI BED file" on page 409.
- "To export the project output to a BAM file" on page 410.
- "To export the output to Geneticist Assistant" on page 411.

To select a report other than the Mutation report as a post-processing option

1. On the Report dropdown list, select the report that is to be automatically generated and saved for the project after project analysis is complete.

A blank Settings field opens next to the selected report.

- 2. Next to the blank Settings field, click Set and then browse to and select a saved Settings file (.ini file) for the report.
- 3. Repeat Step 1 and Step 2 until you have added all the needed reports and their Settings files.



4. Optionally, click Save Summary report to have a Summary report automatically generated for the project as well.



Remember, Save Summary Report is available only after you select at least one other post-processing report and its Settings file. For information about the Summary report, see "Summary report" on page 246.

- 5. If you are done with specifying the needed post-processing options, then return to one of the following as appropriate:
 - Step 12 of "To create a new job file in the NextGENe AutoRun Tool" on page 398.
 - Step 5 of "To create a single post-processing Settings file" on page 420.
 - Step 7 of "To create a new job from an existing AutoRun template" on page 416.
 - Step 9 of "To create a NextGENe AutoRun template" on page 429.
 - Step 5 of "To modify a NextGENe AutoRun template" on page 434.
 - Step 6 of "To modify a NextGENe AutoRun pre-built template" on page 443.

Otherwise, continue specifying any other needed post-processing options. See:

- "To select the Mutation Report as a post-processing option" on page 406.
- "To export aligned sequences as a post-processing option" on page 409.
- "To export a BAM file relative to an ROI BED file" on page 409.
- "To export the project output to a BAM file" on page 410.
- "To export the output to Geneticist Assistant" on page 411.

To export aligned sequences as a post-processing option



For information about generating and saving an export sequence Settings file, see "Export Sequences tool" on page 278.

1. On the Export dropdown list, select Export Sequence.

A blank Settings field opens next to the Export Sequence option.

- 2. Next to the blank Settings field, click Set, and then browse to and select a saved Settings file (.ini file) for the sequence that is to be generated.
- 3. Repeat Step 1 and Step 2 until you have added all the needed sequences and their Settings files.
- 4. If you are done with specifying the needed post-processing options, then return to one of the following as appropriate:
 - Step 12 of "To create a new job file in the NextGENe AutoRun Tool" on page 398.
 - Step 5 of "To create a single post-processing Settings file" on page 420.
 - Step 7 of "To create a new job from an existing AutoRun template" on page 416.
 - Step 9 of "To create a NextGENe AutoRun template" on page 429.
 - Step 5 of "To modify a NextGENe AutoRun template" on page 434.
 - Step 6 of "To modify a NextGENe AutoRun pre-built template" on page 443.

Otherwise, continue specifying any other needed post-processing options. See:

- "To select the Mutation Report as a post-processing option" on page 406.
- "To select a report other than the Mutation report as a post-processing option" on page 408.
- "To export a BAM file relative to an ROI BED file" below.
- "To export the project output to a BAM file" on page 410.
- "To export the output to Geneticist Assistant" on page 411.

To export a BAM file relative to an ROI BED file

To export a BAM file for the alignment results for the regions defined only in the BED file, select ROI BAM as an export option.

1. On the Export dropdown list, select ROI BAM.

A blank Settings field opens next to the ROI BAM option.

- 2. Next to the blank Settings field, click Set and then browse to and select a saved BED (*.bed) file.
- 3. Repeat Step 1 and Step 2 until you have added all the needed BED files.

- 4. If Export ROI BAM is the only needed processing option, then return to one of the following as appropriate:
 - Step 12 of "To create a new job file in the NextGENe AutoRun Tool" on page 398.
 - Step 5 of "To create a single post-processing Settings file" on page 420.
 - Step 7 of "To create a new job from an existing AutoRun template" on page 416.
 - Step 9 of "To create a NextGENe AutoRun template" on page 429.
 - Step 5 of "To modify a NextGENe AutoRun template" on page 434.
 - Step 6 of "To modify a NextGENe AutoRun pre-built template" on page 443.

Otherwise, continue specifying any other needed post-processing options. See:

- "To select the Mutation Report as a post-processing option" on page 406.
- "To select a report other than the Mutation report as a post-processing option" on page 408.
- "To export aligned sequences as a post-processing option" on page 409.
- "To export the project output to a BAM file" below.
- "To export the output to Geneticist Assistant" on page 411.

To export the project output to a BAM file

Select Export BAM to automatically generate a BAM file for the alignment results for the project. If you export NextGENe sequence alignment project files to a BAM format, then the standard index file, index.bai, that other alignment viewers require is also exported. If you do not select this post-processing option, you always have the option of exporting the project output to a BAM format from the File menu on the NextGENe viewer. (See "NextGENe Viewer main menu" on page 142.) If Export BAM is the only needed processing option, then return to one of the following as appropriate:

- Step 12 of "To create a new job file in the NextGENe AutoRun Tool" on page 398.
- Step 5 of "To create a single post-processing Settings file" on page 420.
- Step 7 of "To create a new job from an existing AutoRun template" on page 416.
- Step 9 of "To create a NextGENe AutoRun template" on page 429.
- Step 5 of "To modify a NextGENe AutoRun template" on page 434.
- Step 6 of "To modify a NextGENe AutoRun pre-built template" on page 443.

Otherwise, continue specifying any other needed post-processing options. See:

- "To select the Mutation Report as a post-processing option" on page 406.
- "To select a report other than the Mutation report as a post-processing option" on page 408.
- "To export aligned sequences as a post-processing option" on page 409.
- "To export a BAM file relative to an ROI BED file" on page 409.
- "To export the output to Geneticist Assistant" below.

To export the output to Geneticist Assistant

For Output to Geneticist Assistant to be enabled, User Management must be turned on for your NextGENe instance and you must be logged in appropriately. See "To turn on user management" on page 35. Also, the path for the Geneticist Assistant executable must be specified in the NextGENe process options. See "Specifying NextGENe Process Options" on page 81.

1. Select Output to Geneticist Assistant.

Edit details is enabled as are the Run Name and Sample Name fields. By default, the Sample Name is set to the same as that of the first sample file that was loaded for the AutoRun job.



When output is exported to Geneticist Assistant, an unfiltered VCF file is automatically produced and exported, even if loaded post-processing options specify both an unfiltered VCF file and a filtered VCF file.

- 2. Enter a Run Name and/or edit the Sample Name.
- 3. Click Edit details.

The Geneticist Assistant Input Settings dialog box opens. The first time that the dialog box opens, all options are blank; otherwise, the settings that were last specified or the settings that are saved for the template that you have selected are displayed.

Figure 9-15: Geneticist Assistant Input Settings dialog box

neticist Assistant Input Settings	
Settings	
Reference	•
Panel	*
Chemistry	•
Instrument	*
Submit BAM	
	OK Cancel

- 4. Specify the Geneticist Assistant Run variables.
- 5. To submit the BAM and VCF output to Geneticist Assistant, select Submit BAM; otherwise, to import only the VCF output, leave this option cleared.
- 6. Click OK.

The Geneticist Assistant Input Settings dialog box closes. The NextGENe AutoRun Job Editor dialog box remains opens.

- 7. If you are done with specifying the needed post-processing options, then return to one of the following as appropriate:
 - Step 15 of "To create a new job file in the NextGENe AutoRun Tool" on page 398.
 - Step 5 of "To create a single post-processing Settings file" on page 420.
 - Step 7 of "To create a new job from an existing AutoRun template" on page 416.
 - Step 13 of "To create a NextGENe AutoRun template" on page 429.
 - Step 5 of "To modify a NextGENe AutoRun template" on page 434.
 - Step 6 of "To modify a NextGENe AutoRun pre-built template" on page 443.

Otherwise, continue specifying any other needed post-processing options. See:

- "To select the Mutation Report as a post-processing option" on page 406.
- "To select a report other than the Mutation report as a post-processing option" on page 408.
- "To export aligned sequences as a post-processing option" on page 409.
- "To export a BAM file relative to an ROI BED file" on page 409.
- "To export the project output to a BAM file" on page 410.

To group jobs

You can load multiple samples for analysis with the same job options. You can then use the Group Jobs option to automatically group the samples into separate jobs. The same job options are applied to all the separate jobs.

 If you have not already done so, on the Job File Editor window main menu, click Edit > Group Samples into Jobs.

The Group Jobs dialog box opens. The dialog box displays all the sample files that are currently loaded in the NextGENe AutoRun tool. See Figure 9-16 on page 413.

Figure 9-16: Group Jobs dialog box

Samp	ole L	ist					Job	o List				
	t	2	3	4 (G)	5	6		Job	Sample 1		Sample 2	
1	F	信1	converted	unmatched	fasta	1	1	unmatched	F_R1_conv	erted_unmatched.fasta	F_R2_converted	_unmatched.
2	F	R2	converted	unmatched	fasta							
3	D	R1	converted	unmatched	fasta							
4	D	R1	converted	unmatched	paired	fasta						
5	D	R2	converted	unmatched	fasta	1						
6	D	R2	converted	unmatched	paired	fasta						
Gro	up b	y Sec	tions Grou section(s) 4	ip by Fixed Pos	sition Delimite	Group By Order		T Match	Case ob Name:		[Group ID] +	

2. Indicate how the jobs are to be grouped.



The grouping option that was last selected remains selected when the Group Jobs dialog box opens.

Setting	Description
Group by Sections	Group the jobs based on a user-defined section in the sample file names. The default values for delimiters are a dash (-), a period (.), and an underscore (_). For example, a sample file named F_R1_converted.fasta would have four sections based on the default underscore and period delimiters:
	• Section 1 = F
	• Section 2 = R1
	Section 3 = converted
	Section 4 = fasta
Group by Fixed Position	Group by user-specified position or range of positions in the sample file names.
Group by Order	Group the jobs based on the order in which the sample files were loaded in to the NextGENe AutoRun tool.

3. By default, the Job ID for each group is automatically created based on how the jobs are grouped. You do have the option of modifying some of the settings that affect how the Job ID is created.

Job Grouping	Default Group Name
By Sections	The Group ID: section(s) indicates which section of the file name is used to group the sample files. This section is also used for the Job ID. For example, for the following six sample files with the Group ID: section(s) = 1 for grouping:
	F_R1_converted.fasta
	D_R1_converted.fasta
	E_R1_converted.fasta
	F_R2_converted.fasta
	D_R2_converted.fasta
	E_R2_converted.fasta
	creates three jobs with two sample files each and each job identified by one of the following three JOB IDs:
	• F
	• D
	• E
By Fixed Position	The Job ID is based on the user-specified character (for example, 1) or range of characters (for example, 1-4) in the file names that were used to group the jobs. For example, considering the same sample files above, using Group ID: character(s) = 1 for grouping creates three jobs with two sample files each and each job identified by one of the following three Job IDs:
	• F
	• D
	• E
	Note: You can select Match Case to further refine the grouping and the Job IDs.
By Order	By default, Group ID: the first item name is selected, which means that the ID that is assigned to each job is based on the name of the first file in each group. For example, considering the same sample files above, and using a Group Size = 2, then three jobs would be created with two sample files per group and each job identified by one of the following three Job IDs: • F_R1_converted
	D_R1_converted
	• E_R1_converted
	Note: If you clear Group ID: the first item name, then the Job ID is a numeric value and it is created based on the order in which they groups are listed in the Group Jobs dialog box (e.g., 1, 2, 3, and so on).

- 4. Optionally, build out the Job ID by assigning a prefix and/or suffix to the Group ID. For example:
 - If the Group ID for three separate jobs is "D," "E," and "F," then specifying Sample in the first blank Build Job Name field results in Job IDs of "SampleD," "SampleE," and "SampleF."

- If you specified another value in the second blank Build Job Name field (such as the date of the job), then the job IDs would be "SampleD08062014," "SampleE08062014," and "SampleF08062014."
- 5. Return to Step 5 or Step 15 as appropriate in "To create a new job file in the NextGENe AutoRun Tool" on page 398.

To modify an existing job file

When you modify a job file, you can add a new job to the job file, you can modify the information for an existing job in the job file, and/or you can delete a job from the job file.

- 1. Do one of the following:
 - On the NextGENe main menu, click Tools > NextGENe AutoRun.
 - On the Start menu, select All Programs\SoftGenetics\NextGENe\NG_<Version>\NG_AutoRun.

The NextGENe AutoRun window opens. See Figure 9-7 on page 399.

2. On the NextGENe AutoRun main menu, click Tool > Job Editor.

The Job Editor dialog box opens. See Figure 9-8 on page 399.

3. On the Job Editor main menu, click File > Load Job File.

An Open dialog box is displayed.

4. In the Open dialog box, browse to and select the .ngjob file that you are modifying, and then click Open.

The selected job file is loaded into the Job Editor.

- 5. Do any of the following as needed:
 - To add another job to an existing job file, do either of the following:
 - Click Add a New Job, and then specify the information for the new job. (You can add multiple new jobs to an existing job file.)
 - Select a job in the Job Tree, and then click Duplicate Job to duplicate the selected job, and then modify the duplicated job as needed.
 - To modify a job, select a job in the Job Tree, and then modify any of the settings for the job as needed, including adding and/or removing sample files, and adding and/or removing reference files.
 - To delete a job, select a job in the Job Tree, and then click Delete Job.



See "Main menu" on page 395 and "Toolbar" on page 396 for a detailed discussion about accessing these options.

- 6. After you have modified the existing job file as needed, on the Job Editor dialog box main menu, click File > Save Job File or File > Save As.
- 7. Continue to "To specify the NextGENe AutoRun settings" on page 417.

To create a new job from an existing AutoRun template

If you use an existing AutoRun template to create a new job in the NextGENe AutoRun tool, you must provide the sample files and specify the output directory folder. You can leave all other settings the same, or you can modify the template as needed *before* you carry out the run.



For information about creating a NextGENe AutoRun template, see "Managing NextGENe AutoRun Templates" on page 429.

- 1. Do one of the following:
 - On the NextGENe main menu, click Tools > NextGENe AutoRun.
 - On the Start menu, select All Programs\SoftGenetics\NextGENe\NG_<Version>\NG_AutoRun.

The NextGENe AutoRun window opens. See Figure 9-7 on page 399.

2. On the NextGENe AutoRun main menu, click Tool > Job Editor.

The Job Editor dialog box opens. See Figure 9-8 on page 399.

3. On the Template dropdown list, select the appropriate AutoRun template.

The selected template is loaded into the Job Editor dialog box.

- 4. Load the sample files.
- 5. In the Output field, leave the default value for the location of the output files as is (the directory path for the *first* data file added), or click Set to select a different location.
- 6. Load the reference.
- 7. Optionally, do one or both of the following as needed:
 - To modify the template:
 - Next to the Template dropdown list, click Edit to modify the template settings. (See Step 5 through Step 14 of "To create a new job file in the NextGENe AutoRun Tool" on page 398.)

Save replaces Edit next to the Template dropdown list.

b. Click Save to save the modified template settings.

- 8. Optionally, do any of the following as needed; otherwise, continue to Step 9.
 - Save the job file.
 - Add a new job to the job file.
 - Add a secondary analysis job.
 - Delete a job.
 - Duplicate a job.
 - Group samples into jobs.



See "Main menu" on page 395 and "Toolbar" on page 396 for a detailed discussion about the options that are available.


- 9. To save the new job file, on the Job Editor dialog box main menu, click File > Save Job File or File > Save As.
- 10. Continue to "To specify the NextGENe AutoRun settings" on page 417.

To specify the NextGENe AutoRun settings

- 1. Do one of the following:
 - On the NextGENe main menu, click Tools > NextGENe AutoRun.
 - On the Start menu, select All Programs\SoftGenetics\NextGENe\NG_AutoRun.

The NextGENe AutoRun window opens.

Figure 9-17: NextGENe AutoRun window



2. On the NextGENe AutoRun toolbar, click the Settings icon \cancel{R} .

The NextGENe AutoRun Settings dialog box opens.

Figure 9-18: NextGENe AutoRun Settings dialog box

NextGENe AutoRun Settings	
Directory	
Job file detecting directory	
C:\Data\test\2.4.2\delay detect\	941
Time	
Detect time interval 1 🕞 min	
Parallel jobs	
Max parallel jobs (1-9) 1 😨 Available RAM for	each job: 2768
	contribution and a
Automatically detect when AutoRun is launched	
Minimize to taskbar	
OK	Cancel
	C 1990 GEN

3. Specify the Autorun settings.

Option	Description
Job File Detecting Directory	The directory in which you saved the NextGENe AutoRun job file.
Time	Detect Time Interval—The time interval between searches. (When NextGENe searches for job files to process.)
Max parallel jobs	The maximum number of AutoRun jobs to run in a parallel (simultaneously). The default value is one.
	Note: To increase this value above the default value of one, the appropriate number of concurrent NextGENe licenses are required. Also, before you adjust this value, you should know that your client has ample RAM to run parallel jobs. The RAM that is currently available per job is always displayed on the AutoRun Settings dialog box, and the value is modified accordingly if you select a different number of jobs to run in parallel. You can use the RAM that was required for previously run jobs as a guideline, or while a job is running, you can use the Task Manager to look at the total RAM that is being used to determine the amount of RAM that will be required per run. Typically, at least 12 GB of RAM is recommended per run.
Automatically detect when AutoRun is launched	Automatically start AutoRun when it is launched.

Option	Description
Minimize to Taskbar	When the NextGENe AutoRun function starts, it opens NextGENe. Select this option to automatically minimize the NextGENe window after it opens.

4. Click OK.

The NextGENe AutoRun Settings dialog box closes. You return the NextGENe AutoRun window.

5. If Automatically detect when AutoRun is launched is *not* selected, then on the AutoRun window main menu, click File > Detect.

The AutoRun tool confirms that the job file is valid and that all the files that are needed for processing the jobs in the job file are available.

- If all the necessary files are available to process all the jobs in the job file, NextGENe processes the project data according to the instructions that are detailed in the job file and saves the data to the designated Output folder. The job file is moved to the Completed Jobs folder.
- If all the necessary files are available to process some, but not all, the jobs in the jobs file, NextGENe processes the project data for the jobs for which the necessary files are available according to the instructions that are detailed in the job file. The job file is moved to the Incomplete Jobs folder. The AutoRun tool continues to scan the job file according to the specified time interval, for example, every ten minutes, and as the necessary files become available, NextGENe processes the project data for the appropriate jobs. After all the jobs are processed, the jobs file is moved to the Completed Jobs folder.
- If none of necessary files are available for the jobs in the jobs file, the AutoRun tool continues to scan the job file according to the specified time interval, for example, every ten minutes, and as the necessary files become available, NextGENe processes the project data for the appropriate jobs. After all the jobs are processed, the jobs file is moved to the Completed Jobs folder.



At any time, you can click the Pause icon || on the toolbar to pause AutoRun, or you can click the Stop icon to stop the tool altogether [0].

Batch Processing of Previously Processed Projects to Output Reports and Other Export Files

You can use the NextGENe AutoRun tool to carry out the batch processing of previously processed sequence alignment projects and export outputs of your choosing. This option is particularly helpful in the event that you have multiple projects that have been run without post-processing options as it prevents you from having to reprocess each project individually or having to load each project in the NextGENe Viewer and manually exporting the post-processing options through the viewer. Batch processing previously processed projects is a three step process. First, you must create the needed report Settings files (.ini files) and then load all these files on the post-processing page of the Project Wizard to save a single Settings file that contains all the settings for all the selected reports and outputs. Second, you must load the projects and this single Settings file. Third, you must specify the settings to run the job.



To export any output to Geneticist Assistant, User Management must be turned on for your NextGENe instance. See "To turn on user management" on page 35.

To create a single post-processing Settings file

- 1. Create and save the needed output Settings files. See:
 - "Mutation Report settings" on page 213.



Remember, you can create and save up to two different Settings files for the Mutation report—the General Settings file and the Variation Tracks Settings file.

- "Distribution report" on page 254.
- "Coverage Curve report" on page 258.
- "Expression Report" on page 265.
- "Structural Variation report" on page 273.
- "HLA project report" on page 197.



The HLA report is available as a post-processing option only if HLA was selected as the application type for the project. See "HLA Project" on page 195.

• See "Transcript report" on page 173.



The Transcript report is available as a post-processing option only if Transcriptome with Alternative splicing is selected as the application type. See "Transcriptome Alignment Project with Alternative Splicing" on page 168.

• See "Summary report" on page 246.



The Summary report is available only after you select at least one other post-processing report and its Settings file. The information that the report contains is relative to the post-processing reports that you select for the project.

- "Export Sequences tool" on page 278.
- 2. Do one of the following to open the Project Wizard.
 - Click the Project Wizard icon 🛐 on the application toolbar.
 - On the NextGENe main menu, click File > Open Project Wizard.
 - On the NextGENe main menu, click Process > Project Wizard.
- 3. Click Post-Processing.

The Post-Processing page opens.

Figure 9-19: Post-processing page for a sequence alignment project

		Show Project Log>
Step Application	Post processing Report	Settings
Load Data		
Condensation	Seve summery report	Add Remove All
Assembly	Export	Settings
Alignment Past Processing		
	Export BAM Output to Geneticist Assistant	Add Remove All
ve Settings Lo	ad Settings << Ba	Sample Name

- 4. Select the appropriate post-processing outputs and, if applicable, the corresponding Settings files (.ini files) by which to post-process the data. See:
 - "To select report post-processing options" on page 405.
 - "To export aligned sequences as a post-processing option" on page 409.
 - "To export the project output to a BAM file" on page 410.
 - "To export a BAM file relative to an ROI BED file" on page 409.
 - "To export the output to Geneticist Assistant" on page 411.
- 5. Click Save Settings, and then name the Settings file and save it to a location of your choice.

This file is the single Settings file (.ini file) that contains all the settings for all the post-processing outputs that you selected in Step 4.


6. Continue to "To load and run the projects" below.

To load and run the projects

- 1. Do one of the following:
 - On the NextGENe main menu, click Tools > NextGENe AutoRun.
 - On the Start menu, select All Programs\SoftGenetics\NextGENe\NG_<Version>\NG_AutoRun.

The NextGENe AutoRun window opens.

Figure 9-20: NextGENe AutoRun window



2. On the NextGENe AutoRun main menu, click Tool > Job Editor.


The Job Editor dialog box opens.

Figure 9-21: Job Editor dialog box

NextGENe AutoRun Job Editor - Untit	ed 🖌	
File Edit Tools		
	1	
 Job 1 Sample File(s) Preprocessing None 	Job name: Job 1 IE 30 Template: Choose Template	nen (12089782_19 • Save
Reference File(s)	Input sequence files.	
 NextGENe Settings File 	n pur sequence nes.	Load
 Dutput Path 		Bemove
	Output:	
		Set
	Preprocesses: 0 (Add)	
	Reference:	Select
		Remove
		Lannac
	Process & report settings file: Inspect input files to set optimum parameter	eis
		Load
	Report & Elizard (Epit. distants)	
	Output to Geneticist Assistant Edit detail	
	Gun Name Job 1	
	OK	Cancel
	OK.	Cano

3. On the main menu, click Edit > Add a Report-only Job.

Only the pane in which you load the previously processed projects and the field in which you load the single Settings file (.ini file)—the Process and report settings file field—remain available.



- 4. For each previously processed project (.pjt file) that is to be post-processed, click Load in the Input project file pane to open a dialog box, and then browse to and select the project.
- 5. Next to the Process and report settings file field, click Load to open a dialog box, and then browse to and select the single Settings file (.ini file) that you created in "To create a single post-processing Settings file" on page 420.



You can load multiple projects for post-processing with the same Settings file. In the next step, you can use the Group Jobs option to group the projects into separate jobs. The same Settings file is applied to all the separate job files.

- 6. Optionally, do any of the following as needed; otherwise, continue to Step 7.
 - Save the job file.
 - Add a new job to the job file.
 - Delete a job.
 - Duplicate a job.
 - Group samples into jobs.



See "Main menu" on page 395 and "Toolbar" on page 396 for a detailed discussion about the accessing these options.

7. Click OK.

If you have not saved the job file, then you are prompted to specify a file name and location for the job file and after you save the file, the Job Editor dialog box closes; otherwise, the Job Editor dialog box simply closes. You have now created the necessary job files.

8. Continue to "To specify the NextGENe AutoRun settings" below.

To specify the NextGENe AutoRun settings

- 1. Do one of the following:
 - On the NextGENe main menu, click Tools > NextGENe AutoRun.
 - On the Start menu, select All Programs\SoftGenetics\NextGENe\NG_AutoRun.

The NextGENe AutoRun window opens.

Figure 9-22: NextGENe AutoRun window

NextGENe AutoRun [Administrator]	
File Tool Help	
文 ■ 次	

2. \Box On the NextGENe AutoRun toolbar, click the Settings icon \clubsuit .

The NextGENe AutoRun Settings dialog box opens.

Figure 9-23: NextGENe AutoRun Settings dialog box

VextGENe AutoRun Settings	
Directory	
Job file detecting directory	
C:\Data\test\2.4.2\delay detect\	9.41
and the second second	
Time	
Detect time interval 1 🚡 min	
Parallel jobs	
Max parallel jobs (1-8) 1 🕞 Available BA	M for each job: 2768
A STANDE OF	inter courtour ando
Automatically detect when AutoRun is launched	
Minimize to taskbar	
	OK Cancel
-	The day

3. Specify the Autorun settings.

Option	Description	
Job File Detecting Directory	The directory in which you saved the NextGENe AutoRun job file.	
Time	Detect Time Interval—The time interval between searches. (When NextGENe searches for job files to process.)	
Max parallel jobs	The maximum number of AutoRun jobs to run in a parallel (simultaneously). The default value is one.	
	Note: To increase this value above the default value of one, the appropriate number of concurrent NextGENe licenses are required. Also, before you adjust this value, you should know that your client has ample RAM to run parallel jobs. The RAM that is currently available per job is always displayed on the AutoRun Settings dialog box, and the value is modified accordingly if you select a different number of jobs to run in parallel. You can use the RAM that was required for previously run jobs as a guideline, or while a job is running, you can use the Task Manager to look at the total RAM that is being used to determine the amount of RAM that will be required per run. Typically, at least 12 GB of RAM is recommended per run.	
Automatically detect when AutoRun is launched	Automatically start AutoRun when it is launched.	

Option	Description
Minimize to Taskbar	When the NextGENe AutoRun function starts, it opens NextGENe. Select this option to automatically minimize the NextGENe window after it opens.

4. Click OK.

The NextGENe AutoRun Settings dialog box closes. You return the NextGENe AutoRun window.

5. If Automatically detect when AutoRun is launched is *not* selected, then on the AutoRun window main menu, click File > Detect.

The AutoRun tool confirms that the job file is valid and that all the files that are needed for processing the jobs in the job file are available.

- If all the necessary files are available to process all the jobs in the job file, NextGENe processes the project data according to the instructions that are detailed in the job file and saves the data to the designated Output folder. The job file is moved to the Completed Jobs folder.
- If all the necessary files are available to process some, but not all, the jobs in the jobs file, NextGENe processes the project data for the jobs for which the necessary files are available according to the instructions that are detailed in the job file. The job file is moved to the Incomplete Jobs folder. The AutoRun tool continues to scan the job file according to the specified time interval, for example, every ten minutes, and as the necessary files become available, NextGENe processes the project data for the appropriate jobs. After all the jobs are processed, the jobs file is moved to the Completed Jobs folder.
- If none of necessary files are available for the jobs in the jobs file, the AutoRun tool continues to scan the job file according to the specified time interval, for example, every ten minutes, and as the necessary files become available, NextGENe processes the project data for the appropriate jobs. After all the jobs are processed, the jobs file is moved to the Completed Jobs folder.



At any time, you can click the Pause icon || on the toolbar to pause AutoRun, or you can click the Stop icon to stop the tool altogether [0].

Secondary Batch Analysis of Multiple Projects

To export any output to Geneticist Assistant, User Management must be turned on for your NextGENe instance. See "To turn on user management" on page 35.

You can use the NextGENe AutoRun tool to set up a new project, a *secondary analysis project*, based on the output from a previously created job that has yet to be processed. After the previously created job is processed, then the secondary analysis of its output files is automatically carried out.

- 1. Set up the job for the primary analysis as needed in the Auto Run tool. See "To create a new job file in the NextGENe AutoRun Tool" on page 398.
- 2. On the main menu, click Edit > Add a secondary analysis job.




See "Toolbar" on page 396 for an alternate method for the accessing this option.

The NextGENe AutoRun window is refreshed and a placeholder (Job2) is created for the secondary analysis job.

3. In the Input sequence files pane, click Load > Load previous run output for secondary analysis.

The Load Previous Run Result dialog box opens. The files that are displayed in the dialog box depend on the settings file that was loaded for the previously created job.

Figure 9-24: Load Previous Run Result dialog box



4. Select the appropriate files for secondary analysis, and then click OK.

The Load Previous Run Result dialog box closes. You return to the Job Editor dialog box.

- 5. Continue with setting the job options for the secondary analysis in the NextGENe AutoRun tool as needed.
- 6. Click OK.

If you have not saved the job file, then you are prompted to specify a file name and location for the job file and after you save the file, the Job Editor dialog box closes; otherwise, the Job Editor dialog box simply closes. You have now created the necessary job files.

Managing NextGENe AutoRun Templates

A NextGENe AutoRun *template* is a file that serves as a starting point for a new job in the NextGENe AutoRun tool. With the exception of the sample files and the output directory folder, an AutoRun template contains all the information and settings that are necessary for an AutoRun job, including reference files, post-processing settings, and so on. Managing NextGENe AutoRun templates consists of creating new AutoRun templates, modifying existing AutoRun templates, and deleting AutoRun templates.

To create a NextGENe AutoRun template

- 1. Do one of the following:
 - On the NextGENe main menu, click Tools > NextGENe AutoRun.
 - On the Start menu, select All Programs\SoftGenetics\NextGENe\NG_<Version>\NG_AutoRun.

The NextGENe AutoRun window opens.

Figure 9-25: NextGENe AutoRun window

NextGENe AutoRun [Administrator]	X
File Tool Help	
史 ■ 父	

2. On the NextGENe AutoRun main menu, click Tool > Job Editor.

The Job Editor dialog box opens. It contains a placeholder for creating a job, which is identified with the default name of Job<#>, for example, Job1 in the Job name field. See Figure 9-26 on page 430.

	ed l	-
File Edit Tools		
	1	
 Job 1 Sample File(s) 	Job name: Job 1	(12089782_10
 Preprocessing None 	Template: Choose Template	Save
 Reference File(s) A NextGENe Settings File 	Input sequence files.	
Dutput Path		Load
		Remove
	Output:	-
		Set
	Preprocesses: 0 (Add)	
	Reference:	
		Select
		Remove
	Process & report settings file: Inspect input files to set optimum parameters	
		Load
	Report's Export (1) (Edit details)	
	Output to Geneticist Assistant	
	From Name Job 1	


Figure 9-26: Job Editor dialog box

- 3. If your project sample files require preprocessing, then you must load the appropriate Settings files (.ini files) to specify the required preprocessing options.
 - If the project sample files are not in .fasta or .bam format, then you must load a Settings file that specifies the format conversion settings.
 - If the project sample files contain barcodes, then you must load a Settings file that specifies the barcode sorting settings to demultiplex the data.
 - If the project sample files need to be modified further before analysis (for example, trimming adapters), then you must load a Settings file that specifies the appropriate sequence operation settings.

If applicable, for any of the above, go to "To specify preprocessing options" on page 403; otherwise, continue to Step 4.

- 4. In the Reference pane, click the arrow that is next to Select to open a dropdown menu, and then do one of the following:
 - To select a preloaded reference, click Select Preloaded Reference to open a Load Reference Files dialog box in which you can select the preloaded reference, and then continue to Step 7.
 - To select a GenBank or a .fasta reference file, click Add Sequence Files to open a dialog box in which you can browse to and select the reference file, and then continue to Step 5.

5. If you loaded a GenBank reference file, then "Query annotation and & tracks from preloaded" is displayed below the reference pane with a Select option. If you do not want to query the imported databases (tracks) for the project, then continue to Step 7; otherwise, click Select to open the Select a reference to query annotation and tracks dialog box and select the appropriate preloaded reference.




Available preloaded reference:	
human_v36_1_dna_compressed	
Human_v36_3_dna	
Human_v37_1_dna	
Human_v37_2_dna	
Human_v37_2_snp134_dna	

6. Click OK.

The Select a reference to query annotation and tracks dialog box closes. The Job Editor dialog box remains open.

 Next to the Process & report settings file field, click Load to open a dialog box, and then browse to and select a configuration file with the appropriately saved settings for the condensation, assembly, and/or alignment steps. (See "Saving and Loading Project Settings" on page 74.)

After you load the Settings file, Report & Export is enabled and the number of post-processing options that the loaded file contains is displayed. An Edit details link is also enabled.



	Process & report settings file:	Inspect input files to set optimum parameters	
	C:\Users\Spectrum Writing\Spectrum Writing	Info\Active Client Work\SoftGenetics\WIP\Next(Load
 ►(Report & Export: 2 (Edit details)		

- 8. Optionally, consider the following; otherwise, continue to Step 11.
 - If the configuration file that you loaded in Step 7 does not contain post-processing options, and you want to post-process the data:

or

• If the configuration file that you loaded in Step 7 does contain post-processing options, but you want to add more options or use different settings to post-process the data:

then click Edit details to open the Outputs dialog box.

Figure 9-29: Outputs dialog box

Report	Settings		Add
Mutation		Set Remove	Remove All
☑ Save summary repo Export	ort Settings		Add
Export Sequence	*	Set Bemove	Remove All
Export BAM			

- 9. Select the appropriate post-processing outputs and the corresponding Settings files (.ini files) by which to post-process the data. See:
 - "To select report post-processing options" on page 405.
 - "To export aligned sequences as a post-processing option" on page 409.
 - "To export a BAM file relative to an ROI BED file" on page 409.
 - "To export the project output to a BAM file" on page 410.
- 10. Click OK on the Outputs dialog box.

The Outputs dialog box closes. The Job Editor dialog box remains opens.

- 11. Optionally, if *either* of the following are applicable, then select Inspect input files to set optimum parameters.
 - If you loaded a Configuration file that contains condensation settings for Illumina data, SOLiD System data, or Ion Torrent data, and you select this option, then NextGENe inspects the input files and adjusts the condensation settings accordingly. If you select this option for Roche data, then NextGENe simply ignores it.



This option is identical to the Inspect Input Files option on the Condensation page in the Project Wizard. See "Inspect Input Files" on page 102.

• If you loaded a Configuration file that contains alignment settings for a preloaded reference, and you select this option, then NextGENe inspects the input files and adjusts the alignment settings accordingly.



This option is identical to the Inspect Input Files option on the Alignment page for preloaded reference files in the Project Wizard. See "Inspect Input Files" on page 135.

- 12. If the output is to be exported to Geneticist Assistant, then go to "To export the output to Geneticist Assistant" on page 411; otherwise, continue to Step 13.
- 13. Next to the Template dropdown list, click Save.

The Create a New Template dialog box opens.

Figure 9-30: Create a New Template dialog box

Create a New Template		×
Template name	ОК	Cancel

14. Enter a name for the template, and then click OK.

The Create a New Template dialog box closes. The saved template remains loaded in the Job Editor.



All NextGENe AutoRun templates are saved in the Template root directory, which is specified in your NextGENe process options. See "Specifying NextGENe Process Options" on page 81.

To modify a NextGENe AutoRun template

When you modify a NextGENe AutoRun template, you can modify any of the settings that have been specified for the template.

- 1. Do one of the following:
 - On the NextGENe main menu, click Tools > NextGENe AutoRun.
 - On the Start menu, select All Programs\SoftGenetics\NextGENe\NG_<Version>\NG_AutoRun.

The NextGENe AutoRun window opens. See Figure 9-25 on page 429.

2. On the NextGENe AutoRun main menu, click Tool > Job Editor.

The Job Editor dialog box opens. See Figure 9-26 on page 430.

3. On the Template dropdown list, select the appropriate template.

The selected template is loaded into the Job Editor.

4. Next to the Template dropdown list, click Edit.

The template settings become available for editing.

- 5. To modify the template settings, see Step 3 through Step 12 of "To create a NextGENe AutoRun template" on page 429.
- 6. Next to the Template dropdown list, click Save.

To delete an AutoRun template

When you delete an AutoRun template, any NextGENe jobs that were previously run using this template are unaffected. Going forward, the template is simply not available for selection.

- 1. Do one of the following:
 - On the NextGENe main menu, click Tools > NextGENe AutoRun.
 - On the Start menu, select All Programs\SoftGenetics\NextGENe\NG_<Version>\NG_AutoRun.

The NextGENe AutoRun window opens. See Figure 9-25 on page 429.

2. On the NextGENe AutoRun main menu, click Tool > Job Editor.

The Job Editor dialog box opens. See Figure 9-26 on page 430.

3. On the Job Editor dialog box main menu, click Tools > Manage Templates.

The Template Details dialog box opens. The dialog box displays all the available AutoRun templates for your NextGENe installation. The AutoRun templates for RainDance ThunderBolts panels are displayed alphabetically by name first, and then all other AutoRun templates are displayed alphabetically by name second. It also displays the creation time, the date of last modification, and the template version for each template, as well as the NextGENe version in which each template was created.

Figure 9-31:	Template Details dialog box
1 19010 0 01.	

Template Name	Created Time	Last Modified	Template Version	NextGENe Version	Delete
RainDance Cancer Panel (Built-in)	2015/02/13 12:31:09		1.0	2.4.1	
RainDance Cancer Panel High Sensitivity (Built-in)	2015/02/13 12:31:09		1.0	2.4.1	
RainDance Myeloid Panel (Built-in)	2015/02/10 15:10:48		1.0	2.4.1	
RainDance Myeloid Panel High Sensitivity (Built-in)	2015/02/10 15:10:48		1.0	2.4.1	
RainDance ThunderBolts Cancer Panel (1% MAF) (B	2015/02/13 12:31:09		1.0	2.4.1	
RainDance ThunderBolts Cancer Panel (5% MAF) (B	2015/02/13 12:31:09		1.0	2.4.1	
RainDance ThunderBolts Myeloid Panel (1% MAF) (2015/04/30 14:33:10		1.0	2.4.1	
RainDance ThunderBolts Myeloid Panel (5% MAF) (2015/04/30 14:33:10		1.0	2.4.1	
Documentation Template III	2015/04/20 14:58:51	2015/04/20 14:58:51	1.0	2.4.1	
Mayo Cancer Panel	2015/11/12 12:43:08	2015/11/12 12:43:08	1.0	2.4.2	
Personal Cancer Panel	2015/11/12 12:56:24	2015/11/12 12:56:24	1.0	2.4.2	
Test Template	2015/11/13 14:55:01	2015/11/13 14:55:01	1.0	2.4.2	

4. Select the *AutoRun* template that is to be deleted.



The Delete option is not available for the built-in AutoRun templates for RainDance ThunderBolts panels.

A message opens, asking you if you are sure that you want to delete the selected template.

5. Click OK.

The template is deleted and no longer displayed on the Template Details dialog box. The Template Details dialog box remains open.

6. Click Close.

The Template Details dialog box closes. You return to a blank Job Editor dialog box.

Working With NextGENe AutoRun Pre-Built Templates

A NextGENe AutoRun *template* is a file that serves as a starting point for a new job in the NextGENe AutoRun tool. The following pre-built AutoRun templates are supplied with your NextGENe installation:

- RainDance Thunderbolts Cancer panels
- RainDance Thunderbolts Myeloid panels
- NEBNext Cancer Direct panels

All the pre-built templates include SoftGenetics's recommended settings for Whole Genome Alignment of samples from these panels. Unlike other NextGENe AutoRun templates, however, none of the pre-built templates specify the reference that is to be used for a project.

You cannot modify any of the settings for a pre-built template. You must use the template as-is. Using a NextGENe AutoRun pre-built template is a two-step process. First, you must select the sample files and reference. Second, as with all other NextGENe AutoRun templates, you must then specify the settings for the tool, which includes the job file directory, the time interval for detecting job files, and the maximum number of parallel jobs. To modify a pre-built template, you must save the template with a different name, and then you can modify any or all the settings as needed.

To select the samples and reference for a NextGENe AutoRun pre-built template

- 1. Do one of the following:
 - On the NextGENe main menu, click Tools > NextGENe AutoRun.
 - On the Start menu, select All Programs\SoftGenetics\NextGENe\NG_<Version>\NG_AutoRun.

The NextGENe AutoRun window opens. See Figure 9-32 on page 437.

File Tool Help	
史 四 シ	

Figure 9-32: NextGENe AutoRun window

2. On the NextGENe AutoRun main menu, click Tool > Job Editor.

The Job Editor dialog box opens. It contains a placeholder for creating a job, which is identified with the default name of Job<#>, for example, Job1.

Figure 9-33: Job Editor dialog box

NextGENe AutoRun Job Editor - Untitl File Edit Tools			
	1.0		
iJob 1 Sample File(s) Preprocessing None Reference File(s) NexiGE Ne Settings File Dutput Path	Job name: Job 1	0 2015111	2089732_106
	Template: Choose Template	*	Save
	Input sequence files:		
			Load
			Remove
	Dutput:		
			Set
	Preprocesses: 0 (Add) Reference:		
			Select
			Remove
	Process & report settings file:	am parameters	
			Load
	Reports Expand (Edit Netals)		
	Output to Geneticist Assistant		
	Hun Name Job 1		
	F	OK	Cancel
	L	UK	Lancel

3. On the Template dropdown list, select the appropriate pre-built template.

All the Settings file are loaded for the selected template. The full path for the Alignment Settings file is displayed in the Process and report settings file field. You cannot edit any of these settings.

4. For each sample that is to be analyzed, click Load in the Input sequence files pane to open a dialog box, and then browse to and select the files.

The job name is automatically updated based on the file name of the first file loaded, but you can modify as needed.



You can load multiple samples for analysis with the same job options and then use the Group Jobs option to automatically group samples into separate jobs. The same job options are applied to all the separate job files. See "To group jobs" on page 439.

- 5. In the Output field, leave the default value for the location of the output files as is (the directory path for the *first* data file added), or click Set to select a different location.
- 6. In the Reference pane, click Select, and then select the appropriate preloaded reference. (See "To load a preloaded reference" on page 57.)
- 7. Optionally, do any of the following as needed; otherwise, go to Step 8.
 - Save the job file.
 - Add a new job to the job file.
 - Delete a job.
 - Duplicate a job.
 - Group samples into jobs.

See "Main menu" on page 395 and "Toolbar" on page 396 for a detailed discussion about the accessing these options.

8. Click OK.

If you have not already clicked Save to save the job file, then you are prompted to specify a file name and location for the job file and after you save the file, the Job Editor dialog box closes; otherwise, the Job Editor dialog box simply closes. You have now created the necessary job files.

9. Continue to "To specify the NextGENe AutoRun settings" on page 417.

To group jobs

You can load multiple samples for analysis with the same job options. You can then use the Group Jobs option to automatically group the samples into separate jobs. The same job options are applied to all the separate jobs.

1. If you have not already done so, on the Job File Editor window main menu, click Edit > Group Samples into Jobs.

The Group Jobs dialog box opens. The dialog box displays all the sample files that are currently loaded in the NextGENe AutoRun tool.

Figure 9-34: Group Jobs dialog box

Sar	nple L	ist					Job	List				
1	11	2	3	4 (G)	5	6	1	Job	Sample 1		Sample 2	
1	F	信1	converted	unmatched	fasta		1	unmatched	F_R1_conv	erted_unmatched.fasta	F_R2_converted_unr	natched.f
2	F	R2	converted	unmatched	fasta							
3	D	R1	converted	unmatched	fasta							
4	D	B1	converted	unmatched	paired	fasta						
5	D	R2	converted	unmatched	fasta	1						
6	D	R2	converted	unmatched	paired	fasta						
t-			1.0		-		*					,
-			tions Grou	p by Fixed Pos	sition	Group By Order		-				
Gr	oup b	y Sec		p by r mour o	control I			Match	Case			
			section(s) 4		Delimite				Case ob Name:	+	[Group ID] +	_

2. Indicate how the jobs are to be grouped.



The grouping option that was last selected remains selected when the Group Jobs dialog box opens.

Setting	Description
Group by Sections	Group the jobs based on a user-defined section in the sample file names. The default values for delimiters are a dash (-), a period (.), and an underscore (_). For example, a sample file named F_R1_converted.fasta would have four sections based on the default underscore and period delimiters:
	• Section 1 = F
	• Section 2 = R1
	• Section 3 = converted
	Section 4 = fasta
Group by Fixed Position	Group by user-specified position or range of positions in the sample file names.
Group by Order	Group the jobs based on the order in which the sample files were loaded in to the NextGENe AutoRun tool.

Chapter 9 The NextGENe AutoRun Tool

3. By default, the Job ID for each group is automatically created based on how the jobs are grouped. You do have the option of modifying some of the settings that affect how the Job ID is created.

Job Grouping	Default Group Name
By Sections	The Group ID: section(s) indicates which section of the file name is used to group the sample files. This section is also used for the Job ID. For example, for the following six sample files with the Group ID: section(s) = 1 for grouping:
	F_R1_converted.fasta
	D_R1_converted.fasta
	E_R1_converted.fasta
	F_R2_converted.fasta
	D_R2_converted.fasta
	E_R2_converted.fasta
	creates three jobs with two sample files each and each job identified by one of the following three JOB IDs:
	• F
	• D
	• E
By Fixed Position	The Job ID is based on the user-specified character (for example, 1) or range of characters (for example, 1-4) in the file names that were used to group the jobs. For example, considering the same sample files above, using Group ID: character(s) = 1 for grouping creates three jobs with two sample files each and each job identified by one of the following three Job IDs:
	• F
	• D
	• E
	Note: You can select Match Case to further refine the grouping and the Job IDs.
By Order	By default, Group ID: the first item name is selected, which means that the ID that is assigned to each job is based on the name of the first file in each group. For example, considering the same sample files above, and using a Group Size = 2, then three jobs would be created with two sample files per group and each job identified by one of the following three Job IDs: • F_R1_converted
	 D_R1_converted
	• E_R1_converted
	Note: If you clear Group ID: the first item name, then the Job ID is a numeric value and it is created based on the order in which they groups are listed in the Group Jobs dialog box (e.g., 1, 2, 3, and so on).

- 4. Optionally, build out the Job ID by assigning a prefix and/or suffix to the Group ID. For example:
 - If the Group ID for three separate jobs is "D," "E," and "F," then specifying Sample in the first blank Build Job Name field results in Job IDs of "SampleD," "SampleE," and "SampleF."


- If you specified another value in the second blank Build Job Name field (such as the date of the job), then the job IDs would be "SampleD08062014," "SampleE08062014," and "SampleF08062014."
- 5. Return as appropriate to one of the following:
 - Step 4 in "To select the samples and reference for a NextGENe AutoRun pre-built template" on page 436.
 - Step 7 in "To modify a NextGENe AutoRun pre-built template" on page 443.

To specify the NextGENe AutoRun settings

- 1. Do one of the following:
 - On the NextGENe main menu, click Tools > NextGENe AutoRun.
 - On the Start menu, select All Programs\SoftGenetics\NextGENe\NG_AutoRun.

The NextGENe AutoRun window opens.

Figure 9-35: NextGENe AutoRun window



On the NextGENe AutoRun toolbar, click the Settings icon ⅔.
 The NextGENe AutoRun Settings dialog box opens.

Chapter 9 The NextGENe AutoRun Tool

Directory	
Job file detecting directory	
C:\Data\test\2.4.2\delay detect\	9.01
Time	
Detect time interval 1 🚡 min	
Parallel jobs	
Max parallel jobs (1-8) 1 😨 Available RAM for each job. 27	/GB
Automatically detect when AutoRun is launched	
Minimize to taskbar	
OK	Cancel

Figure 9-36: NextGENe AutoRun Settings dialog box

3. Specify the Autorun settings.

Option	Description
Job File Detecting Directory	The directory in which you saved the NextGENe AutoRun job file.
Time	Detect Time Interval—The time interval between searches. (When NextGENe searches for job files to process.)
Max parallel jobs	The maximum number of AutoRun jobs to run in a parallel (simultaneously). The default value is one.
	Note: To increase this value above the default value of one, the appropriate number of concurrent NextGENe licenses are required. Also, before you adjust this value, you should know that your client has ample RAM to run parallel jobs. The RAM that is currently available per job is always displayed on the AutoRun Settings dialog box, and the value is modified accordingly if you select a different number of jobs to run in parallel. You can use the RAM that was required for previously run jobs as a guideline, or while a job is running, you can use the Task Manager to look at the total RAM that is being used to determine the amount of RAM that will be required per run. Typically, at least 12 GB of RAM is recommended per run.
Automatically detect when AutoRun is launched	Automatically start AutoRun when it is launched.
Minimize to Taskbar	When the NextGENe AutoRun function starts, it opens NextGENe. Select this option to automatically minimize the NextGENe window after it opens.

4. Click OK.

The NextGENe AutoRun Settings dialog box closes. You return the NextGENe AutoRun window.

5. If Automatically detect when AutoRun is launched is *not* selected, then on the AutoRun window main menu, click File > Detect.

The AutoRun tool confirms that the job file is valid and that all the files that are needed for processing the jobs in the job file are available.

- If all the necessary files are available to process all the jobs in the job file, NextGENe processes the project data according to the instructions that are detailed in the job file and saves the data to the designated Output folder. The job file is moved to the Completed Jobs folder.
- If all the necessary files are available to process some, but not all, the jobs in the jobs file, NextGENe processes the project data for the jobs for which the necessary files are available according to the instructions that are detailed in the job file. The job file is moved to the Incomplete Jobs folder. The AutoRun tool continues to scan the job file according to the specified time interval, for example, every ten minutes, and as the necessary files become available, NextGENe processes the project data for the appropriate jobs. After all the jobs are processed, the jobs file is moved to the Completed Jobs folder.
- If none of necessary files are available for the jobs in the jobs file, the AutoRun tool continues to scan the job file according to the specified time interval, for example, every ten minutes, and as the necessary files become available, NextGENe processes the project data for the appropriate jobs. After all the jobs are processed, the jobs file is moved to the Completed Jobs folder.



At any time, you can click the Pause icon || on the toolbar to pause AutoRun, or you can click the Stop icon to stop the tool altogether [o].

To modify a NextGENe AutoRun pre-built template



To export any output to Geneticist Assistant, User Management must be turned on for your NextGENe instance. See "To turn on user management" on page 35.

- 1. Do one of the following:
 - On the NextGENe main menu, click Tools > NextGENe AutoRun.
 - On the Start menu, select All Programs\SoftGenetics\NextGENe\NG_<Version>\NG_AutoRun.

The NextGENe AutoRun window opens. See Figure 9-32 on page 437.

Chapter 9 The NextGENe AutoRun Tool

2. On the NextGENe AutoRun main menu, click Tool > Job Editor.

The Job Editor dialog box opens. See Figure 9-33 on page 437.

3. On the Template dropdown list, select the appropriate template for your RainDance panel.

All the Settings file are loaded for the selected template. The full path for the Alignment Settings file is displayed in the Process and report settings file field. You cannot edit any of these settings.

4. Next to the Template dropdown list, click Save As.

The Create a New Template dialog box opens.

Figure 9-37: Create a New Template dialog box

create a New Template		×
Template name		
	ОК	Cancel

5. Enter a name for the template, and then click OK.

The Create a New Template dialog box closes. The saved template remains loaded in the Job Editor.



All NextGENe AutoRun templates are saved in the Template Root directory, which is specified in your NextGENe process options. See "Specifying NextGENe Process Options" on page 81.

6. Next to the Template dropdown list, click Edit.

The template settings are now editable. To modify the template settings, see Step 3 through Step 12 of "To create a NextGENe AutoRun template" on page 429.

Appendix A Mutation Report Scores

SoftGenetics developed the *Overall Mutation score* to provide an empirical estimation of the likelihood that a given variant call is real and not an artifact of sequencing or alignment errors. Multiple different scores are used to calculate the Overall Mutation Score. This appendix provides a detailed explanation of the Overall Mutation Score. It also provides a detailed description, including the underlying algorithms, for each of the scores that are used in the calculation of the Overall Mutation Score.

This appendix covers the following topics:

- "Overall Mutation Score" on page 446.
- "Coverage score" on page 447.
- "Read Balance Score" on page 448.
- "Allele Balance Score" on page 449.
- "Homopolymer Score" on page 450.
- "Mismatch Score" on page 451.
- "Wrong Allele Score" on page 452.

Overall Mutation Score

SoftGenetics developed the *Overall Mutation score* to provide an empirical estimation of the likelihood that a given variant call is real and not an artifact of sequencing or alignment errors. This score is based on the concept of Phred scores, where quality scores are logarithmically linked to error probabilities as shown in Figure A-1 below.

Phred quality score	Probability that the base is called wrong	Accuracy of the base call
10	1 in 10	90%
20	1 in 100	99%
30	1 in 1,000	99.9%

The Overall Mutation score is calculated according to the following equation:

Overall Mutation score = (Coverage Score) x (Five Optional Scores)

The Overall Mutation score does not have a set maximum value; however, its value does depend on the coverage. For example, if all the optional scores are ignored for the calculation (value = 1), then the Overall Mutation score would be as shown below:

Coverage	Score
10,000	32
1,000	24
100	16

If any of the optional scores is less than one, then the Overall Mutation score is reduced. A low Overall Mutation score, however, does not mean that the variant is more than likely a false variant. The low score implies only that the variant cannot be called a true variant with absolute certainty. As a general guideline, if the coverage is high (500 to several thousand reads) and the data is bi-directional, then scores that are 5 and lower indicate that the variant is most likely false, while scores of 25 and higher indicate that the variant is most likely true. Even true variants that occur in a high percentage of reads can have low Overall Mutation scores if the coverage is low.

For detailed information about the scores that are used to calculate the Overall Mutation Score, see the following:

- "Coverage score" on page 447.
- "Read Balance Score" on page 448.
- "Allele Balance Score" on page 449.
- "Homopolymer Score" on page 450.
- "Mismatch Score" on page 451.
- "Wrong Allele Score" on page 452.

Coverage score

For elongated data, error-corrected data, or data sets in which condensation was not used, the Coverage score is based on the *adjusted coverage*. Because reads near the 5' end are more accurate than reads at the 3' end, mismatches that are found at the at the beginning of a read are weighted more heavily than mismatches that are found in the 3'end of the read. As result, adjusted coverage is calculated according to the following:

Adjusted Coverage = $1.2*(1^{\text{st}} 1/3 \text{ mismatch}) + (2^{\text{nd}} 1/3 \text{ mismatch}) + 0.7*(3^{\text{rd}} 1/3 \text{ mismatch})$ and the Coverage score is then calculated according to the following:

Coverage Score = $8\log_{10}(\text{Adjusted Coverage})$

For example, consider a nucleotide with 200x coverage that has 100 reads with a mismatch:

- No mismatch = 100
- 1st 1/3 mismatch = 50
- 2nd 2/3 mismatch = 30
- 3rd mismatch = 20
- Normal coverage 100 + 50 + 30 + 20 = 200
- Adjusted coverage = 100 + 1.2(50) + 30 + 0.7(20) = 204x

For data sets in which consolidation was used, the Coverage score is based on the normal coverage and is calculated according to the following:

Coverage Score = 8log₁₀(Normal Coverage)

Read Balance Score

If the sequencing data has reads in both the forward and reverse directions, then biasing errors or systematic sequencing errors are greatly reduced and the data is more likely to be a true sequence. If the ratio of the number of forward reads to the number of reverse reads is within one, then value for the Read Balance score is set to one and no penalty is applied to the Overall Mutation score; otherwise, the score is calculated according to the following formula:

Score =
$$0.3 + \left(1 - \frac{|\#F/C - 0.5|}{\log_{10} C}\right)^2$$

where:

- #F = the number of forward reads
- C = Coverage (forward reads + reverse reads)

Allele Balance Score

The Allele Balance score penalizes variations that occur at different frequencies in the forward and reverse directions because such variations are more likely to be the result of sequencing errors or alignment errors. The score is based on a Yate's chi-square test which is less likely than normal chi-square tests to reject the null hypothesis because of a lack of data, which, in this case, would be low coverage. The following value is calculated first:

$$W = |(\#F SNP)^*(\#R non-SNP) - (\#R SNP)^*(\#F non-SNP)| - C/2$$

where:

- #F = the number of forward reads
- #R = the number of reverse reads
- C = coverage

If this value is negative, then the value for Allele Balance score is set to one and no penalty is applied to the Overall Mutation score; otherwise, the score is calculated according to the following:

$$Score = \left(1 - \sqrt{\frac{W^2}{(\#F) * (\#R) * (\#SNP) * (\#non - SNP)}}\right)^2$$

where:

- #F = the number of forward reads
- #R = the number of reverse reads

Homopolymer Score

The Homopolymer score is applicable only for Roche/454 and Ion Torrent data. The Homopolymer score penalizes indels that are found in homopolymer regions because such indels are typically the result of sequencing errors. The penalty is higher for longer homopolymer regions because the likelihood of sequencing errors in such regions is also higher. The software first determines which length of homopolymer region is present more often (A) and which length is present less often (B). If A or B is < 3, then the value for the Homopolymer score set to one; otherwise, the score is calculated according to the following:

$$Score = \sqrt{\frac{|A - B|}{A}}$$

For example, deletion from four bases to three bases that occurs less than half of the time, where A = 4 and B = 3 results in a score of 0.5, which reduces the Overall Mutation score.

Mismatch Score

Several variations from the reference sequence that occur very close together often indicates a region where variant calls are less reliable. The Mismatch score penalizes a specific variant call if other mismatched bases are found nearby. The software first looks for mismatches that occur in a minimum percentage of reads in the 10 bp region that is found on either of side of the variant that is being scored. The number of mismatches is used to calculate the score. If the number of nearby variations is < 3, then the Mismatch Score is set to one and no penalty is applied; otherwise, the score is calculated according to the following:

$$Score = \left(\frac{0.95^{2N}}{0.8145}\right)^2$$

where N = the number of nearby mismatches.

Wrong Allele Score

Mismatches that are different from the consensus are referred to as *wrong mismatches*. These wrong mismatches most likely result from sequencing errors. For example, A, C insertions and deletions would represent wrong mismatches when a G > T variant is called at a position. The Wrong Allele score is calculated according to the following:

$$1 - \left(\frac{\# \ of \ Wrong \ Mismatches}{\# \ of \ Correct \ Mismatches}\right)^2$$

For elongated data, error-corrected data, or data sets in which condensation was not used, both numbers are based on the adjusted coverage:

 $1.2*(1^{st} 1/3 mismatch) + (2^{nd} 1/3 mismatch) + 0.7*(3^{rd} 1/3 mismatch)$

For data sets in which consolidation was used, both numbers are based on the normal coverage.

Index

Α

Advanced GBK Editor tool 280
Auto Create ROI tool284
GenBank Tree File281
output options284
Save options285
Sequence View pane
advanced settings
sequence condensation (Illumina data, SOLiD System, or Ion Torrent data)
sequence condensation (Roche/ 454 data)112
algorithms
for removing duplicate reads 373
for sequence alignment projects
for a preloaded reference 132
for genomic regions or genomes smaller than 250 Mbp
for transcriptome project with alternative splicing
Alignment viewer
in the NextGENe Viewer 150
functions153
navigation of151
segment breakpoints in 155
Allele Balance score
defined451
alternative splicing analysis project
see transcriptome project with alternative splicing
Ambiguous Gain penalty
calculating227
defined227

Ambiguous Loss penalty
calculating227
defined227
application type
specifying in the Project Wizard53
assembly methods
De Bruijn for Illumina, SOLiD System, and Ion Torrent data120
Floton/Floton-PE for Roche/454 and Ion Torrent data
Greedy for Roche/454 data 121
Maximum Overlap for Illumina data121
PE for Roche/454, Illumina, and Ion Torrent data
Skeleton for Roche/454 data 122
Assumptions for the manual 18
Auto Create ROI tool in the Advanced GBK Editor tool284



BAM output

exporting sequence alignment project files to144	
Barcode Sorting tool	
Barcode/Primer file for361	
output files365	
Barcode/Primer file	
defined361	
barcoded sample files, parsing	
see Barcode Sorting tool361	
Batch CNV Graphs350	
Batch CNV Tool348	

batch processing

previously processed sequence alignment projects using the NextGENe AutoRun tool420
project files in the Project Wizard73
project files using the NextGENe AutoRun tool
project files using the Project Log76
project files using the Project Log and the Project Wizard79
BED file
creating for a specified input sequence range for a sequence alignment project144
Block CNV report
HMM and Dispersion326
SNP-Based Normalization with Smoothing343
•

С

causative variations, identifying in family studies	
see Variant Comparison tool	
CNV Graphs	
Dispersion and HMM329	
SNP-Based Normalization with Smoothing346	
CNV tool	
Dispersion and HMM317	
SNP-based Normalization with Smoothing330	
Condensation Results Filter	
tool	
output files382	
Condensation Results tool	
Condensed Reads pane	

Index table	
Condensed Reads pane in the Condensation Results tool	
Consensus Sequence pane in the HLA project view206	
consolidation	
defined for Illumina data98	
defined for Ion Torrent data98	
defined for SOLiD System data98	
contaminants, filtering from sample files	
see Condensation Results Filter tool	
contigs, merging when overlapping	
see Overlap Merger tool	
Conventions used in the manual17	
Copy Number Variation tool	
see CNV tool	
core number	
specifying in the Project Wizard53	
Coverage Curve report258	
viewing the data for in Pathway Studio264	
Coverage score	
defined449	
Create SAGE Library from mRNA tool289	
customized header file	
loading for a Summary report251	

D

data requirements for a
Mitochondrial amplicon analysis
project

De Bruijn assembly method for Illumina, SOLiD System, and Ion Torrent data120
differential gene expression analysis of transcriptome data176
Distribution report254
duplicate reads
removing
algorithms for373
duplicate reads, removing from sample files
see Sequence Operation tool

Ε

elongation	
defined for Illumina data99	
defined for Ion Torrent data99	
defined for SOLiD System data99	
error correction	
defined for Illumina data99	
defined for Ion Torrent data99	
defined for Roche/454 data 100	
defined for SOLID System data99	
ovairation data	
expiration date	
viewing for the NextGENe license	
viewing for the NextGENe	
viewing for the NextGENe license29 Export Sequences to CSFASTA	
viewing for the NextGENe license29 Export Sequences to CSFASTA tool279	
viewing for the NextGENe license	
viewing for the NextGENe license	

viewing the data for in Pathway
Studio 265
Expression Report for SAGE
studies

F

family data, analyzing		
see Variant Comparison tool		
fasta files		
creating a custom one for an STR analysis project		
File Format Conversion tool 87		
File Preview tool 390		
Filtered VCF Report 241		
Floton/Floton-PE assembly method		
for Roche/454 and Ion Torrent data 124		
output files 125		
Fragment Output 245		

G

Gap.fasta file

exporting sequence alignment project files to 144
GC content, calculating for sample files
see GC Percentage Calculation tool
GC Percentage Calculation tool 385
output files 385
GenBank reference file
viewing, editing, and/or annotating
see Advanced GBK Editor tool
GenBank Tree File in the Advanced GBK Editor tool 281

Gene CNV report			
general settings			
sequence condensation project102			
Geneticist Assistant			
specifying the installation directory for82			
Greedy assembly method for Roche/ 454 data121			
group			
defined 39			
adding 39			
deleting 39			
editing 39			

Η

HLA project
data requirements 195
purpose195
settings195
HLA project view205
Consensus Sequence pane206
Reference Sequence pane 206
Top Allele Pair Matches pane206
Unmatched Reads pane207
HLA report197
settings199
toolbar198
Homopolymer score
defined 452

Illumina
advanced settings for sequence condensation106
De Bruijn assembly method for data120
Maximum Overlap assembly method for data121
PE assembly method for data123
sequence condensation methods explained for data97
Index table in the Condensation Results tool
instrument type
specifying for a project in the Project Wizard53
Ion Torrent
advanced settings for sequence condensation106
De Bruijn assembly method for data 120
Floton/Floton-PE assembly method for data124
PE assembly method for data123
sequence condensation methods explained for data97

license type
viewing for NextGENe29
log file
viewing for your NextGENe users44
Long PE Assembly Mapping tool

Μ

Seek Sample Position245
settings213
gene tracks240
general214
variation tracks232
viewing the data for in Pathway Studio210

Ν

navigating
Alignment viewer151
Whole Genome Viewer
NEBNext Cancer Direct panels
NextGENe AutoRun pre-built templates for437
modifying444
network data
confirming the processing options for82
NextGENe
installing24
main window
main menu28
title bar27
toolbar 28, 395
starting24
system requirements22
NextGENe AutoRun pre-built templates for
NEBNext Cancer Direct panels437
modifying444
RainDance ThunderBolts panels437
modifying444

45	NextGENe AutoRun template
13	creating430
40	defined 430, 437
14	deleting435
32	modifying435
10	viewing the location of the Root template directory for82
	NextGENe AutoRun tool
	using for secondary batch analysis of multiple projects
51 50	using to batch process previously processed sequence alignment projects420
	using to batch process project files398
37	NextGENe tools
,, 14	AutoRun tool391
	Barcode Sorting tool
S	Barcode/Primer file for361
32	output files365
24	Condensation Results Filter tool381
4	output files382
28	Condensation Results tool383
27	Condensed Reads pane384
., 95	Index table
24	File Format Conversion tool87
22	File Preview tool
	GC Percentage Calculation tool385
	output files385
37	Long PE Assembly Mapping
14	tool
7	output files
37	Overlap Merger tool
14	output files387

Pseudo Paired Read Constructor tool
output files
Reads Simulator tool 377
output files 378
Sequence Operation tool 366
output files (arranged paired reads)
output files (merged reads) 367
output files (random subsample) 376
output files (remove duplicate reads) 374, 375
output files (reverse complemented reads) 375, 376
output files (sequence trimmed reads)
output files (split reads) 368
NextGENe Viewer
Alignment viewer
Alignment viewer 150
Alignment viewer 150 Batch CNV graphs
Alignment viewer 150 Batch CNV graphs 350 CNV graphs
Alignment viewer
Alignment viewer 150 Batch CNV graphs 350 CNV graphs 329 SNP-Based Normalization with 329 Smoothing 346 Comparison reports Block CNV HMM and Dispersion 326 SNP-Based Normalization with 343 Expression Comparison 291
Alignment viewer150Batch CNV graphs350CNV graphs0Dispersion and HMM329SNP-Based Normalization with Smoothing346Comparison reports0Block CNVHMM and DispersionHMM and Dispersion326SNP-Based Normalization with Smoothing343Expression Comparison report291Gene CNV340
Alignment viewer150Batch CNV graphs350CNV graphsDispersion and HMM

SNP-based Normalization v Smoothing	
Somatic Mutation Compariso	
Variant Comparison tool	. 295
loading a sequence alignment project in	
main menu	. 142
Status bar	. 155
title bar	. 142
toolbar	. 147
tracks display	. 148
Whole Genome viewer	. 149
NextGENe Viewer reports	
Coverage Curve report	.258
Distribution report	.254
Expression report	.265
Expression report for SAGE studies	.272
Matched/Unmatched report	.253
Mismatched Base Numbers report	.264
Mutation report	.210
Peak Identification report	.286
Score Distribution report	.276
Structural Variation report	.273
Summary report	.246
NextGENe Viewer tools	
Advanced GBK Editor tool	.280
Create ROI tool	.284
GenBank Tree File	.281
output options	.284
Save options	.285
Sequence View pane	. 282
Create SAGE Library from mR tool	

Export Sequences to CSFASTA tool279
Export Sequences tool278
Modify Titles for mRNA GBK tool290
Peak Identification tool
Peak Identification report286
Resume Project and Load Project290
Synthetic SAGE Data tool288
Nucleotide Sequence algorithm for removing duplicate reads

0

Opposite Direction Paired Reads report159
Organization of the manual18
output file name and location
specifying for a project in the Project Wizard59
output files
arranged paired reads
condensation results filter 382
for Floton/Floton-PE assembly method125
for manually linked scaffold contigs
GC calculation385
merged overlapping reads or contigs
merged reads367
parsed sample files (barcoded files)
pseudo paired reads
random subsample
remove duplicate reads 374, 375

reverse complemented reads
sequence alignment project208
sequence assembly project127
sequence condensation project113
sequence trimmed reads
simulated reads378
split reads368
output options
Advanced GBK Editor tool284
Overall Mutation score
calculating 447, 448
defined448
Overlap Merger tool
output files
overlapping contigs, merging
see Overlap Merger tool
overlapping reads, merging
see Overlap Merger tool

Ρ

paired reads
arranging in sample files
see Sequence Operation tool366
constructing
see Pseudo Paired Read Constructor tool
Paired Reads alignment
defined156
functions156
Export SV Reads167
reports156

Opposite Direction Paired Reads report159
Paired Reads Gap Distribution report157
Paired Reads Graph report 165
Paired Reads Statistics report158
Same Direction Paired Reads report161
Single Reads report163
Paired Reads Gap Distribution report157
Paired Reads Graph report 165
Paired Reads Statistics report 158
Pathway Studio
visualizing Coverage report data in264
visualizing Expression Comparison report data in
visualizing Expression report data in265
visualizing Mutation report data in210
visualizing Transcript report data in
PE assembly method for Roche/454 data, Illumina, and Ion Torrent data
peak identification reference file
aligning sample files to
creating with the Peak Identification tool
Peak Identification report286
Peak Identification tool
using to create a peak identification reference file355
phasing
defined221

р	ost processing options
	specifying for a sequence alignment project in the Project Wizard64
р	ost-processing output
	specifying the directory in which to save82
р	rocess options
	directory for the Geneticist Assistant executable82
	for processing local or network data82
	saving reference annotation information in the project output folder or linking to information82
р	roject
	carrying out a secondary analysis on in the Project Wizard73
	creating multiple new ones using the Project Log77
	loading reference files for in the Project Wizard56
	loading sample data files for in the Project Wizard55
	saving and loading the settings for74
	setting up new in the Project Wizard, overview of53
	specifying the instrument type, application type, and number of cores for in the Project Wizard53
	specifying the output file name and location for in the Project Wizard
	specifying the post-processing options for in the Project Wizard64
	specifying the values for the Sequence Alignment step in the Project Wizard

	specifying the values for the Sequence Assembly step in the Project Wizard
4	specifying the values for the Sequence Condensation step in the Project Wizard
) 2	project files
<u>_</u>	batch processing in the Project Wizard 73
2	batch processing using the NextGENe AutoRun tool 398
2	batch processing using the Project Log76
2	batch processing using the Project Log and the Project Wizard 79
-	Project Log
	defined 76
3	using to batch process project files 76
7	using to create multiple new projects77
6 9	using with the Project Wizard to batch process project files 79
5	project settings
	saving and loading74
4	Project Wizard
3	batch processing project files in 73
3	carrying out a secondary analysis for a single project in
ł	defined 51
0	loading reference files 56
9	loading sample data files 55
	opening 51
4	setting up a new project in, overview of53
3	specifying instrument type, application type, and number of cores53

specifying post processing options for a sequence alignment project64
specifying the output file name and location59
specifying values for sequence alignment step63
specifying values for sequence assembly step63
specifying values for sequence condensation step60
using with the Project Log to batch process project files79
Pseudo Paired Read Constructor tool
output files

R

RainDance ThunderBolts panels	
NextGENe AutoRun pre-built templates for437	
modifying444	
Read Balance score	
defined450	
Reads Simulator tool	
output files	
reads, merging when overlapping	
see Overlap Merger tool	
reference annotation information	
exporting to the project output folder when linked to a sequence alignment project	
saving to project output folder or linking to the project82	
reference files	
creating custom .fasta files for an STR analysis project	

creating using the Peak Identification tool
loading for a project in the Project Wizard56
merging
see Sequence Operation tool
Reference Sequence pane in the HLA project view206
reports
Block CNV (SNP-Based Normalization with Smoothing)343
Block CNV(HMM and Dispersion)326
Coverage Curve258
Distribution254
Expression265
Expression Comparison
Expression for SAGE studies272
Filtered VCF241
Gene CNV
HLA 197
Matched/Unmatched253
Mismatched Base Numbers 264
Mitochondrial Amplicon
Mutation210
Opposite Direction Paired Reads159
Paired Reads Gap Distribution157
Paired Reads Graph165
Paired Reads Statistics 158
Same Direction Paired Reads161
Score Distribution276
SIFT241

Single Reads163
STR181
STR Reads Histogram
Structural Variation273
Summary246
Transcript173
Unfiltered VCF241
Resume Project and Load Project option290
RNA-Seq data, aligning
see transcriptome project with alternative splicing
Roche/454
advanced settings for sequence condensation112
Floton/Floton-PE assembly method for data124
Greedy assembly method for data121
PE assembly method for data123
sequence condensation methods explained for data100
Skeleton assembly method for data122
Root template directory
specifying for NextGENe AutoRun templates82
S
SAGE studies
Expression report for272
SAM output

exporting sequence alignment project files to
Same Direction Paired Reads
report161

sample files

aligning to a peak identification reference file
arranging paired reads in
see Sequence Operation tool366
calculating GC content in
see GC Percentage Calculation tool
converting87
filtering contaminants from
see Condensation Results Filter tool
loading in the Project Wizard55
merging
see Sequence Operation tool
parsing when barcoded
see Barcode Sorting tool
previewing
see File Preview tool
removing duplicate reads from
see Sequence Operation tool
reverse complementing sequences
see Sequence Operation tool
splitting
see Sequence Operation tool
trimming sequence reads for
see Sequence Operation tool
Save Consensus Sequence function242
Save options for Advanced GBK Editor tool285
Save SNP Consensus Sequence function244

scaffold contigs, manually linking together
see Long PE Assembly Mapping tool
Score Distribution report276
secondary analysis
carrying out for a project in the Project Wizard73
carrying out in batch for multiple projects using the NextGENe AutoRun tool428
Seek Sample Position245
segment breakpoints in the Alignment viewer155
sequence alignment project
algorithms for131
genomic regions or genomes smaller than 250 Mbp
preloaded reference
batch processing when previously processed using the NextGENe AutoRun tool420
creating a BED file for a specified input sequence range
exporting and saving to a location of your choice146
exporting linked reference annotation information for to the project output folder144
exporting linked tracks for to the project output folder144
exporting project files for to a BAM or SAM output144
exporting project files for to a Gap.fasta file144
loading into the NextGENe Viewer140
output files208

settings

for a transcriptome project with alternative splicing
for an STR analysis 181
for any application type other than transcriptome with alternative splicing
specifying the values for in the Project Wizard
sequence alignment project reports
Coverage Curve report 258
Distribution report 254
Expression report for SAGE studies
Matched/Unmatched report 253
Mismatched Base Numbers report
Mutation report 210
Score Distribution report 276
Structural Variation report 273
Summary report 246
sequence assembly methods
De Bruijn assembly method for Illumina, SOLiD System, and Ion Torrent data
final assembly methods 119
Floton/Floton-PE assembly method for Roche/454 and Ion Torrent data124
general settings for any method 120
Greedy assembly method for Roche/454 data 121
Maximum Overlap assembly method for Illumina data 121
overview of 119
PE assembly method for Roche/ 454 data, Illumina, and Ion Torrent data 123

Skeleton assembly method for Roche/454 data122
sequence assembly project
output files 127
settings
specifying the values for in the Project Wizard63
sequence condensation methods
Illumina data97
consolidation98
elongation99
error correction99
Ion Torrent data97
consolidation98
elongation99
error correction99
Roche/454 data
error correction 100
SOLiD System data97
consolidation98
elongation99
error correction99
sequence condensation project
advanced settings for Illumina data, SOLiD System data, or Ion Torrent data106
advanced settings for Roche/454 data112
general settings 102
output files 113
settings
specifying the values for in the Project Wizard60
Sequence Operation tool
output files
arranged paired reads

random subsample
remove duplicate reads
reverse complemented reads
sequence trimmed reads
split reads
output files (merged reads) 367
sequence reads, trimming for sample files
see Sequence Operation tool
Sequence View pane in the Advanced GBK Editor tool282
SIFT Report241
Single Reads report 163
Skeleton assembly method for Roche/454 data122
SOLiD System
advanced settings for sequence condensation106
De Bruijn assembly method for data120
sequence condensation methods explained for data97
Somatic Mutation Comparison tool
somatic variants, analyzing
see Variant Comparison tool or Somatic Mutation Comparison tool
Special information about the manual17
Status bar
NextGENe Viewer
STR (Short Tandem Repeats) analysis project
alignment settings181

creating custom .fasta reference files for180
purpose180
STR Reads Histogram report 184
STR report 181, 184
settings186
toolbar184
Structural Variation report273
Summary report246
customizing the header for251
loading a customized header file for251
modifying the report view for250
synthetic read data, creating
see Reads Simulator tool
Synthetic SAGE Data tool
system requirements for NextGENe22

Т

title bar
NextGENe main window27
NextGENe Viewer142
toolbar
NextGENe main window 28, 395
NextGENe Viewer147
Top Allele Pair Matches pane in the HLA project view206
Top List function
see Variant Comparison tool
track
defined148
exporting to the project output folder when linked to a sequence alignment project144

tracks display

NextGENe Viewer148
Transcript report173
settings174
viewing the data for in Pathway Studio173
transcriptome project view 171
transcriptome project with alternative splicing
algorithm for 168
alignment settings169
differential gene expression analysis of176
overview of168
project view171
purpose

U

UMI Sequence algorithm for removing duplicate reads
Unfiltered VCF Report241
Unmatched Reads pane in the HLA project view207
user
adding44
deleting44
editing44
viewing the activity for in a log file44
user management
configuring 30, 31
defined 30, 31
turning off37
turning on35
Using the manual17

V

Variant Comparison tool295 variation tracks specifying the settings for in the Mutation report232

W

Glossary

BED file

Also known as Region of Interest (*.bed file). A BED file is a tab-delimited text file. You can upload a BED file only if the reference sequence contains chromosome information, which means that the reference sequence must be either a preloaded reference that NextGENe supplies, or a GenBank reference file that contains chromosome information. Each row in the file contains a region of the reference that is to be used for the report, and at a minimum, the file must contain the following information:

- Field #1 Chromosome number for the region
- Field #2 Chromosome start position
- Field #3 Chromosome end position
- Field #4 Optional description column

Comma-delimited text file

There are no special requirements for uploading a comma-delimited text file. If the input text file is a comma-delimited text file, it must contain one of the following lists:

- A list of specific reference locations (position number) separated by commas
- A list of reference ranges (start position number end position number) separated by commas